

Cloud Native Contrail Networking

Cloud-Native Contrail Networking Feature Guide

Published 2024-05-02

Juniper Networks, Inc. 1133 Innovation Way Sunnyvale, California 94089 USA 408-745-2000 www.juniper.net

Juniper Networks, the Juniper Networks logo, Juniper, and Junos are registered trademarks of Juniper Networks, Inc. in the United States and other countries. All other trademarks, service marks, registered marks, or registered service marks are the property of their respective owners.

Juniper Networks assumes no responsibility for any inaccuracies in this document. Juniper Networks reserves the right to change, modify, transfer, or otherwise revise this publication without notice.

Cloud Native Contrail Networking Cloud-Native Contrail Networking Feature Guide Copyright © 2024 Juniper Networks, Inc. All rights reserved.

The information in this document is current as of the date on the title page.

YEAR 2000 NOTICE

Juniper Networks hardware and software products are Year 2000 compliant. Junos OS has no known time-related limitations through the year 2038. However, the NTP application is known to have some difficulty in the year 2036.

END USER LICENSE AGREEMENT

The Juniper Networks product that is the subject of this technical documentation consists of (or is intended for use with) Juniper Networks software. Use of such software is subject to the terms and conditions of the End User License Agreement ("EULA") posted at https://support.juniper.net/support/eula/. By downloading, installing or using such software, you agree to the terms and conditions of that EULA.

Table of Contents

1

2

About This Guide | viii

Со	nfigure Kubernetes and Contrail
Ena	ble IP Fabric Forwarding and Fabric Source NAT 2
Ena	ble Pods with Multiple Network Interfaces 7
Dis	play Microservice Status 14
IPv	4 and IPv6 Dual-Stack Networking 19
Рос	Scheduling 21
Рос	Scheduling for Multi-cluster Deployments 32
Pric	ority Classes for Critical CN2 Components 47
CN	2 Apstra Integration
Ext	end Virtual Networks to Apstra 50
	Overview 50
	Example: CN2 Kubernetes Deployment with SR-IOV Pods 51
	Prerequisites 53
	Considerations 54
	Installation Workflow 55
	Install and Configure the CN2 Apstra Plug-In 57
	Install the CN2 IPAM Plug-In 61
	Intra-VN and Inter-VN Approaches 62
	Introduction to Configuring Intra-VN Communication 66
	Configure Intra-VN Communication 69
	Before You Begin 69
	Configure Intra-VN Communication Between SR-IOV Pods 70
	Configure Intra-VN Communication Between SR-IOV Pods and Non-SR-IOV Pods 71

Introduction to Configuring Inter-VN Communication | 77

Configure Inter-VN Communication | 79

Before You Begin | 79

Configure Inter-VN Communication Between SR-IOV Pods | 80

Configure Inter-VN Communication Between SR-IOV Pods and Non-SR-IOV Pods | 82

Configure Inter-VN Communication Between SR-IOV Pods, Non-SRIOV Pods and BMS | 87

CN2 Security

Kubernetes Network Policies | 90

Namespace Security Policies | 96

Overview | 96

Encrypt Secret Data at Rest | 101

Configure Management and Control Plane Authentication with TLS Encryption | 101

Overview | 101

Configure TLS Encryption for Contrail Control Plane and vRouter | 102

Routing Policies | 106

Global Security Policy | 116

Enable Namespace Isolation by Default | 120

Advanced Virtual Networking

Create an Isolated Namespace | 126

Namespace Overview | 126

Example: Isolated Namespace Configuration | 127

Isolated Namespace Objects | 130

Create an Isolated Namespace | 131

Optional Configuration: IP Fabric Forwarding and Fabric Source NAT | 133

Enable IP Fabric Forwarding | 133

4

Enable Fabric Source NAT | 135

Configure Allowed Address Pairs | 137

Enable Packet-Based Forwarding on Virtual Interfaces | 139

Configure Reverse Path Forwarding on Virtual Interfaces | 142

Configure Fast Convergence | 144

What Is Convergence | 144

Fast Convergence in a Network Managed by CN2 | 145

Configure Fast Convergence | 148

Configure Graceful Restart and Long-Lived Graceful Restart | 150

Overview | 150

Configure Graceful Restart and LLGR | 152

vRouter Interface Health Check | 156

vRouter Interface Health Check Overview | **156**

Create a Health-Check Object | 156

Health-Check Process | 162

Kubernetes Ingress Support | 162

Deploy VirtualNetworkRouter in Cloud-Native Contrail Networking | 166

Configure Inter-Virtual Network Routing Through Route Targets | 186

Configure IPAM for Pod Networking | 191

Enable VLAN Subinterface Support on Virtual Interfaces | 195

Subinterface Support with Multus | 202

EVPN Networking Support | 211

Customize Virtual Networks for Pod Deployments, Services, and Namespaces | 215

Deploy Kubevirt DPDK Dataplane Support for VMs | 222

Pull Kubevirt Images and Deploy Kubevirt Using a Local Registry | 232

Static Routes | 235

	VPC to CN2 Communication in AWS EKS 251
	Stickiness for Load-Balanced Flows 259
	Configure BFD Health Check for BGPaaS Sessions 261
	Configure BFD Health Check 262
	Configure a Service Account to Assume an IAM role 265
5	Configure DPDK
	Deploy DPDK vRouter 269
6	Configure eBPF
	eBPF Kernel Data Plane (Tech Preview) 278
7	Configure Services
	Enable BGP as a Service 291
	Configure BGP Color Extended Communities 304
	Overview 304
	Configure a BGP Color Extended Community 304
	Create a Load Balancer Service 307
	Load Balancer Service Overview 307
	Create a Load Balancer Service 308
	Dual-Stack Networking Support 315
	Configure Load Balancer Services Without Selectors 315
	NodePort Service Support in Cloud-Native Contrail Networking 319
	Configure ClusterIP Service by Assigning Endpoints 329
	ClusterIP Service without a Selector and Manually Assigned Endpoints 329
	Configure ClusterIP Service 330
	FloatingIP/DNAT for IPv6 Addresses 333
8	Analytics
	Contrail Networking Analytics 338

vi

Contrail Networking Metric List | 344

Kubernetes Metric List | 358

Cluster Node Metric List | 396

Contrail Networking Alert List | 414

vRouter Session Analytics in Contrail Networking | 424

Extend TLS Analytics | 432

Overview | 432

Enable TLS on Analytics Components | 433

Centralized Logging | 439

Port-Based Mirroring | 442

Overview: Port-Based Mirroring | 442

Example: Configure Port-Based Mirroring | 443

Summary | 445

Flow-Based Mirroring | 447

Overview | 447

Configure Flow-Based Mirroring | 448

Configurable Categories of Metrics Collection and Reporting (Tech Preview) | 453

Overview: Configurable Categories of Metrics Collection and Reporting | 453

Install and Upgrade | 455

Manage MetricGroup with Kubectl Commands | 456

Manage Metric Groups with UI | 457

Juniper CN2 Technology Previews (Tech Previews) | 459

About This Guide

This guide provides an understanding of the features and tasks that you can configure for Juniper Cloud-Native Contrail® Networking[™] (CN2) Release 23.3. This guide is appropriate for administrators and operators who need to know how to use CN2.



Configure Kubernetes and Contrail

Enable IP Fabric Forwarding and Fabric Source NAT | 2 Enable Pods with Multiple Network Interfaces | 7 Display Microservice Status | 14 IPv4 and IPv6 Dual-Stack Networking | 19 Pod Scheduling | 21 Pod Scheduling for Multi-cluster Deployments | 32 Priority Classes for Critical CN2 Components | 47

Enable IP Fabric Forwarding and Fabric Source NAT

IN THIS SECTION

- Overview: IP Fabric Forwarding | 2
- Overview: Fabric Source NAT | 3
- Example: Configure Fabric Source NAT | 3
- Example: Configure External Networks with IP Fabric Forwarding | 5

Cloud-Native Contrail® Networking[™] (CN2) supports IP fabric forwarding and fabric source Network Address Translation (NAT) in Kubernetes-orchestrated environments using Juniper Networks' Cloud-Native Contrail® Networking[™] Release 22.1 or later.

Cloud-Native Contrail Networking supports IP fabric forwarding and fabric source NAT. IP fabric forwarding provides clusters running in the overlay network with a path to access the underlay network through the external virtual network. Fabric source NAT enables a gateway device in a fabric to translate the source IP address of data plane node traffic exiting the fabric into a public-side IP address.

You can use IP fabric forwarding and fabric source NAT in cloud-networking environments to provide access to the underlay network. The underlay network access provided by IP fabric forwarding and fabric source NAT enables resources within pods to directly access the Internet or to pull external artifacts from the underlay network. This underlay network access is provided without adding significant network complexity like other underlay network options, such as complex BGP topologies or firewall setups.

Overview: IP Fabric Forwarding

Starting with Release 22.1, Cloud-Native Contrail Networking supports IP fabric forwarding.

You enable IP fabric forwarding within virtual networks that have access to the external network. These virtual networks require direct access to the underlay network.

A virtual network that has access to the external network is named the *default-externalnetwork* by default. You can create a customized user-defined external network name, if you choose. When you enable IP fabric forwarding, the path to the underlay network is directly available to clusters running in the overlay network through this external virtual network. This direct connection between the overlay network and the underlay network gives hosts in the overlay network access to the underlay network.

Because IP fabric forwarding enables a virtual network to span both the overlay network and the underlay network, data packets traversing the two networks are not encapsulated and de-encapsulated. Packet processing, therefore, is more efficient.

IP fabric forwarding is also extremely useful for load balancing network traffic. A LoadBalancer service automatically detects any external virtual network that has enabled IP fabric forwarding when load-balancing external network traffic.

Overview: Fabric Source NAT

Starting in Release 22.1, Cloud-Native Contrail Networking supports fabric source NAT. Fabric source NAT provides a method for traffic from a data plane node in a Kubernetes environment to directly access the Internet without traversing a separate NAT firewall. You can also use source NAT to pull external artifacts into pods when needed.

Traffic from data plane nodes destined for the Internet must traverse a gateway device. This gateway device is a member device in the fabric that also has at least one interface connected to the public network. When fabric source NAT is enabled, the gateway device translates the source IP address of the originating packet from the data plane node into its own public side IP address. This address translation allows traffic from the data plane node to access the Internet.

The IP address translation that source NAT performs also updates the source port in the packet. Multiple data plane nodes can reach the public network through a single gateway public IP address using fabric source NAT.

You need fabric source NAT to translate the IP addresses of traffic exiting the fabric to the Internet. You are not using NAT to translate incoming Internet traffic with this feature.

Example: Configure Fabric Source NAT

Fabric source NAT is disabled by default in user-created virtual networks.

You can enable fabric source NAT manually in any individual virtual network by setting the *fabricSNAT:* variable in the *VirtualNetwork* object to **true**. You can disable fabric source NAT by setting this value to **false**.

The following example shows a virtual network object that has enabled fabric source NAT. This example assumes that a subnet object named *virtual-network-subnet1* is configured in a separate YAML file.

```
apiVersion: core.contrail.juniper.net/v2
kind: VirtualNetwork
metadata:
 name: virtualnetwork1
 namespace: namespace1
 labels:
   vn: virtualnetwork1
  annotations:
   core.juniper.net/display-name: virtualnetwork1
   core.juniper.net/description:
      Virtual Network 1 is a collection of end points that can communicate with each other.
spec:
 v4SubnetReference:
    apiVersion: core.contrail.juniper.net/v2
   kind: Subnet
   namespace: namespace1
    name: virtual-network-subnet1
  fabricSNAT: true
```

You can also configure your environment to enable fabric source NAT in any user-created virtual network when the virtual network is created. If you want to enable fabric source NAT in any user-created virtual network upon creation, set the *enableSNAT* variable in the *ApiServer* resource to **true** when initially deploying your environment.

You must set this configuration in the *ApiServer* resource during initial deployment. You cannot change this setting in your environment after you apply the deployment YAML file. If you want to change the fabric source NAT setting for an individual virtual network after initial deployment, you must change the configuration manually for that virtual network.

Following is a representative YAML file configuration:

```
kind: ApiServer
metadata:
...
spec:
enableSNAT: true
common:
```

containers:

Fabric source NAT is enabled in any user-created virtual network upon creation when the *enableSNAT* variable is **true**. You can disable fabric source NAT when user-created virtual networks are created by setting the *enableSNAT* variable to **false**. Fabric source NAT is disabled by default.

Fabric source NAT automatically selects the IP addresses for translation. You do not need to configure address pools for fabric source NAT in most Cloud-Native Contrail Networking use cases. Address pools are configurable, however, using the *portTranslationPools:* hierarchy within the *GlobalVrouterConfig* resource.

Example: Configure External Networks with IP Fabric Forwarding

IP fabric forwarding is disabled by default.

You can enable IP fabric forwarding in any virtual network by setting the *fabricForwarding:* variable to **true**.

The following example shows how to enable IP fabric forwarding in an external virtual network that accesses the Internet through an IPv4 gateway:

```
apiVersion: core.contrail.juniper.net/v2
kind: VirtualNetwork
metadata:
  namespace: contrail
  name: external-vn
  labels:
    service.contrail.juniper.net/externalNetworkSelector: default-external
  annotations:
    core.juniper.net/display-name: Sample Virtual Network
    core.juniper.net/description:
      VirtualNetwork is a collection of end points (interface or ip(s) or MAC(s))
      that can communicate with each other by default. It is a collection of
      subnets whose default gateways are connected by an implicit router.
spec:
  v4SubnetReference:
    apiVersion: core.contrail.juniper.net/v2
    kind: Subnet
    namespace: contrail
```

```
name: external-subnet
fabricForwarding: true
```

You can also enable IP fabric forwarding while creating the external virtual network that has a path to the Internet.

You configure a virtual network's path to an external network through the *Kubemanager* resource in environments using CN2.

You enable external access for a virtual network by connecting the virtual network to an IPv4 or IPv6 gateway IP subnet address. You enable IP fabric forwarding for the external traffic in the virtual network using the same *Kubemanager* resource.

NOTE: You must configure the external network subnets and this IP fabric forwarding setting during the initial Cloud-Native Contrail deployment. You cannot configure these parameters after the initial deployment YAML file is applied.

The following example shows a YAML file used to configure a *Kubemanager* resource that creates a virtual network with external network access. The virtual network in this example runs with IP fabric forwarding. You would have to commit this YAML file during initial deployment.

```
kind: Kubemanager
metadata:
...
spec:
externalNetworkV4Subnet: # Fill V4 Subnet of an external network if any
externalNetworkV6Subnet: # Fill V6 Subnet of an external network if any
ipFabricFowardingExtSvc: true
common:
    containers:
    ...
```

You specify the IPv4 subnet or the IPv6 subnet of the external network using the *externalNetworkV4Subnet* or *externalNetworkV6Subnet:* variable in this YAML file. The subnet address is a public-side IP address that is reachable from the Internet through the gateway device. When you configure a Kubemanager resource using this YAML file, a new virtual network to the specified external network is created. This virtual network is named *default-externalnetwork* in the default namespace for CN2.

IP fabric forwarding runs in the virtual network with external network access when the *ipFabricFowardingExtSvc* variable is **true**. You can disable IP fabric forwarding for the external subnet by setting the *ipFabricFowardingExtSvc* variable to **false**.

Enable Pods with Multiple Network Interfaces

IN THIS SECTION

- Multiple Network Interfaces in Cloud-Native Contrail Benefits | 7
- Multiple Network Interfaces in Cloud-Native Contrail Overview | 8
- Cloud-Native Contrail Integration with Multus Overview | 9
- Create a Network Attachment Definition Object | 9
- Configure a Pod to Use Multiple Interfaces | 12
- Disable the Network Attachment Definition Controller | 13

Cloud-Native Contrail® Networking[™] (CN2) supports multiple network interfaces for a pod within Kubernetes. Multiple network interface support for a pod in Kubernetes provides a variety of environment-specific functionality, including the ability to segment traffic over multiple interfaces.

Cloud-Native Contrail Networking natively supports multiple network interfaces for a pod. You can also enable multiple network interfaces in Cloud-Native Contrail Networking using Multus. Multus is a container network interface (CNI) plugin for Kubernetes developed by the Kubernetes Network Plumbing Working Group. Cloud-Native Contrail can interoperate with Multus to provide support for multiple interfaces provided by multiple CNIs in a pod.

This document provides the steps to enable multiple interfaces for a pod in environments using CN2. It includes information about when and how to enable multiple networking interfaces. Multiple interface support for a pod was initially released in Contrail Networking Release 22.1.

Multiple Network Interfaces in Cloud-Native Contrail Benefits

Support for multiple network interfaces is useful or required in many cloud-networking environments. This list provides a few common examples:

- Pods routinely require a data interface to carry data traffic and a separate interface for management traffic.
- Virtualized network functions (VNFs) typically need three interfaces—a left, a right, and a management interface—to provide network functions. A VNF often can't provide its function with a single network interface.

- Cloud network topologies routinely need to support two or more network interfaces to isolate management networks from tenant networks.
- In customized or high-scale cloud-networking environments, you often must use a cloud-networking product that supports multiple network interfaces to meet a variety of environment-specific requirements.

A pod in a Kubernetes cluster using the default CNI has a single network interface for sending and receiving network traffic. You can use Cloud-Native Contrail Networking to provide multiple network interfaces. Cloud-Native Contrail Networking also supports Multus integration, allowing environments using Cloud-Native Contrail for networking to support multiple network interfaces using Multus.

Multiple Network Interfaces in Cloud-Native Contrail Overview

You can enable multiple network interfaces in Cloud-Native Contrail using Multus and without using Multus. Multus is a container network interface (CNI) plugin for Kubernetes that enables support for multiple network interfaces on a pod as well as multihoming between pods. Multus can simultaneously support interfaces from multiple delegate CNIs. This multiple delegate CNI support allows for the creation of cloud-networking environments that are interconnected using CNIs from different vendors, including CN2. Multus is often called a "meta-plugin" because of this multi-vendor support.

The following two paragraphs provide information on when to use the two methods of enabling multiple network interfaces.

You should enable multiple network interfaces using the native Cloud-Native Contrail Networking support for multiple network interfaces for the following reasons;

- You do not want the overhead of enabling and maintaining Multus in your environment.
- You are using Cloud-Native Contrail Networking as your only container networking interface (CNI).
- You do not want to create and maintain Network Attachment Definition (NAD) objects to support multiple network interfaces in your environment.

You must create a NAD object to enable multiple network interfaces with Multus. You do not have to configure a NAD object to enable multiple network interfaces if you are not using Multus.

Each NAD object notably creates a virtual network and a subnet that you have to monitor and maintain.

You should enable multiple network interfaces using Multus for the following reasons:

• You are using Cloud-Native Contrail in an environment that is already using Multus. Multus is especially common in environments using Openshift orchestration.

- You need the "meta-plugin" capabilities provided by Multus. You are using Cloud-Native Contrail in an environment where a pod is using multiple interfaces and the multiple interfaces are being managed by Cloud-Native Contrail and other CNIs.
- You are using Cloud-Native Contrail in an environment where it is integrated with Juniper Networks Apstra. You must enable Multus in order to enable Cloud-Native Contrail integration with Apstra.

Cloud-Native Contrail integration with Apstra was introduced in Release 22.4. For more information regarding Cloud-Native Contrail integration with Apstra, see "Extend Virtual Networks to Apstra" on page 50.

• You need some of the other Multus features in your environment.

Cloud-Native Contrail Integration with Multus Overview

A Contrail vRouter is natively Multus-aware. No Cloud-Native Contrail Networking-specific configuration is required to enable Multus interoperability with Cloud-Native Contrail.

This list summarizes Cloud-Native Contrail support interoperability options with Multus:

- Cloud-Native Contrail is compatible with Multus CNI version 0.3.1.
- Cloud-Native Contrail must be configured as the primary/default CNI with Multus.
- Cloud-Native Contrail can be configured as a delegate CNI with Multus only when Cloud-Native Contrail is also configured as the primary/default CNI. Cloud-Native Contrail is not supported as a delegate CNI when other CNIs are configured as the primary CNI.
- Cloud-Native Contrail supports interoperability with Multus when in vRouter kernel mode or Data Plane Development Kit (DPDK) mode.

Multus is a third-party plugin. You enable and configure Multus within Kubernetes but entirely outside of Cloud-Native Contrail. To enable Multus, you can apply the multus-daemonset.yml files provided by the Kubernetes Network Plumbing Working Group.

For detailed information about Multus, see the Multus CNI Usage Guide from the Kubernetes Network Plumbing Working Group.

Create a Network Attachment Definition Object

You do not need to create a *NetworkAttachmentDefinition* (NAD) object to enable multiple interfaces using the native multiple interfaces support in Cloud-Native Contrail Networking. You can skip this

section if you are not using Multus to enable multiple network interfaces in your environment. If you are not using NAD objects but need to create a virtual network, see "Deploy VirtualNetworkRouter in Cloud-Native Contrail Networking" on page 166.

This section illustrates how to create a NAD object using a YAML file. You configure Cloud-Native Contrail into the NAD object using the *juniper.net/networks* annotation. We provide a representative example of the YAML file that creates the NAD object and a field descriptions table later in this section.

Be sure to include the *juniper.net/networks* annotation when you create the *NetworkAttachmentDefinition* object. If you define the YAML file to create the *NetworkAttachmentDefinition* object without using the *juniper.net/networks* annotation, the *NetworkAttachmentDefinition* object is treated as a third-party object. No Contrail-related objects will be created in the network, including the *VirtualNetwork* object and the *Subnet* object.

You create the *NetworkAttachmentDefinition* object in a Kubernetes environment using the NAD controller. The NAD controller runs in kube-manager and either creates a *VirtualNetwork* object or updates an existing *VirtualNetwork* object when a *NetworkAttachmentDefinition* is successfully created. The NAD controller is enabled by default but you can disable it; see "Disable the Network Attachment Definition Controller" on page 13.

Following is an example of the YAML file used to create a *NetworkAttachmentDefinition* object:

```
apiVersion: "k8s.cni.cncf.io/v1"
kind: NetworkAttachmentDefinition
metadata:
  name: networkname-1
  namespace: nm1
  annotations:
    juniper.net/networks: '{
      "ipamV4Subnet": "172.16.10.0/24",
      "ipamV6Subnet": "2001:db8::/64",
      "routeTargetList": ["target:23:4561"],
      "importRouteTargetList": ["target:10.2.2.2:561"],
      "exportRouteTargetList": ["target:10.1.1.1:561"],
      "fabricSNAT": true
    }'
spec:
  config: '{
  "cniVersion": "0.3.1",
  "name": "juniper-network",
  "type": "contrail-k8s-cni"
}'
```

The *NetworkAttachmentDefinition Object Fields* table provides usage details for the variables in the *NetworkAttachmentDefinition* object file.

Variable	Usage
ipamV4Subnet	(Optional) Specifies the IPv4 subnet address for the virtual network.
ipamV6Subnet	(Optional) Specifies the IPv6 subnet address for the virtual network.
routeTargetList	(Optional) Provides a list of route targets that are used as both import and export routes.
importRouteTargetList	(Optional) Provides a list of route targets that are used as import routes.
exportRouteTargetList	(Optional) Provides a list of route targets that are used as export routes.
fabricSNAT	(Optional) Specifies if you'd like to toggle connectivity to the underlay network using the port-mapping capabilities provided by fabric source NAT.
	Set this parameter to true or false . It is set to false by default. If you want to allow connectivity to the underlay network, set the parameter to true .

Table 1: NetworkAttachmentDefinition Object Fields

You should note the following network activities related to the NetworkAttachmentDefinition object:

- The network attachment definition controller works in kube-manager and handles processing of all network attachment definition objects.
- You can monitor network attachment definition controller updates in juniper.net/network-status.
- IPAM updates are not allowed to the network attachment definition object.

The network attachment definition object creates a virtual network. The Network Attachment Definition Object Impact on Virtual Networks table on page 12 provides an overview of how events related to the network attachment definition object impact virtual networks.

lf	Then
You define a namespace for a network attachment definition object in a single cluster topology	A VirtualNetwork is created in the same namespace as the network attachment definition.
	This VirtualNetwork will have the same name as the Network Attachment Definition object. The NAD object is named using the name: field in the metadata: hierarchy.
You define a namespace for a network attachment definition object in a multi-cluster topology	The <i>VirtualNetwork</i> namespace is <i>cluster-name</i> - ns. .
A namespace is not defined for a network attachment definition object in a multi-cluster topology	The <i>VirtualNetwork</i> namespace is <i>cluster-name-</i> default.
You delete a network attachment definition resource	The associated <i>VirtualNetwork</i> object is also deleted.
You delete a virtual network that was created by the network attachment definition resource	The network attachment definition controller reconciles the issue and recreates the virtual network.

Table 2: Network Attachment Definition Object Impact on Virtual Networks

Configure a Pod to Use Multiple Interfaces

You configure multiple interfaces in the pod object. If you are using Multus, you must also configure the NAD object as outlined in "Create a Network Attachment Definition Object" on page 9.

In the following example, you create two interfaces for network traffic in the *juniper-pod-1* pod: *tap1* and *tap2*.



Disable the Network Attachment Definition Controller

The NAD controller is part of the kube-manager object. You enable and disable this controller using the **enableNad:** variable within the YAML file that defines the **kubemanager** object. The network attachment definition controller is enabled by default.

If you would prefer to prevent the application of *NetworkAttachmentDefinion* objects, you can disable the network attachment definition controller.

In the following example, the network attachment definition controller is disabled:

```
kind: Kubemanager
metadata:
   name: remote-cluster
   namespace: contrail
spec:
   common:
    nodeSelector:
        node-role.kubernetes.io/master: ""
enableNad: false
```

Display Microservice Status

IN THIS SECTION

- Overview: Microservice Status in Cloud-Native Contrail Networking | 14
- Display Microservice Status | 15
- Display Deployment Status | 15
- Display Resource Status | 16

Juniper® Cloud-Native Contrail Networking (CN2) supports microservices in environments using CN2 Release 22.1 or later in a Kubernetes-orchestrated environment.

To display microservice status in CN2 cluster, you need:

- A CLI tool, such as kubect1 to provide the overall system status of all the services running.
- The contrailstatus plugin must be installed along with kubectl.
- The use of command kubectl contrailstatus to request the status of various services.

Overview: Microservice Status in Cloud-Native Contrail Networking

Microservices exist as small, independent applications deployed without updating the entire Contrail Networking deployment. Microserves provide better ways to manage the life cycle of containers. The containers and their processes are grouped as services and microservices.

ContrailStatus is a kubect1 plugin used to display the status information of Contrail Networking services in the three different planes (configuration, control, and data). In addition to the usual containers in a specific service, you can also view:

- init (initialization) container status within the service.
- The relative software status, such as BGP and XMPP, in control_controller.

The contrailstatus plug-in is categorized into two sections:

Deployment status

Resource status

Display Microservice Status

The following outputs are examples showing deployment status updates and resource status updates to the pods for all planes.

Display Deployment Status

Display deployment status in either short form or default form.

All Planes Deployment Status

To display the deployment status for all of the planes and request the short form:

```
root@helper ~] # kubectl contrailstatus -short
```

STATUS
nok
ok
ok

The option -short for short form only displays output for the pod name and status. The following example outputs are using the default form.

Configuration Plane Deployment Status

To display the deployment status to the configuration plane:

root@helper ~] # kubectl contrailstatus deployment -p config					
PODNAME apiserver-86885bf7d8-q27qk	STATUS	NODE node	IP 10.1.1.1	MESSAGE process not up,	
init cont	HOK	libue	10.1.1.1	process not up,	
apiserver-86885bf7d8-sdsdd	ok	node2	10.1.1.2		
apiserver-86885bf7d8-sdsss	ok	node3	10.1.1.3		
controller-6998bd846f-5cgf7	ok	node1	10.1.1.1		

controller-6998bd846f-5cgf8 o	ok	node2	10.1.1.2	
controller-6998bd846f-5cg10 n	nok	node3	10.1.1.3	o/1 node is not
allocated.				
cluster1-kubemanager-7cff895-sd	lfsd ok	node2	10.1.1.2	
cluster1-kubemanager-7cff895-sd	lfsa ok	node3	10.1.1.3	

Data Plane Deployment Status

To display the deployment status to the data plane:

root@helper ~] # kubectl contrailstatus deployment -p data				
PODNAME vrouter-86885bf7d8-q27qk not up, init cont	STATUS nok	NODE node	IP 10.1.1.1	MESSAGE process
vrouter-86885bf7d8-sdsdd	ok	node2	10.1.1.2	

Control Plane Deployment Status

To display the deployment status to the control plane:

root@helper ~] # kubectl contrailstatus deployment -p control					
PODNAME contrail-control-0	STATUS nok	NODE node	IP 10.1.1.1	MESSAGE process not	
up, init cont contrail-control-1	ok	node2	10.1.1.2		

Display Resource Status

The contrailstatus plugin also displays status updates for deployment resources, such as XMPP and BGP.

Data Plane Resource Status

To display the resource status of bgprouter to the data plane:

root@helper ~] kubectl contrailstatus resource bgprouter

PODNAMESTATUSSERVICEbgprouter1nokxmpp, bgp not working/has error..bgprouter2nokbgprouter2 okk

Control Node Resource Status

To display the resource status in the control node, run the following command, which displays the output for the XMPP session:

root@helper ~] kubectl contrailstatus resource bgprouter -s xmpp					
LOCAL	NEIGHBOR	STATE	POD		
bgprouter1	vr1	established (ok)	contrail-control-0		
bgprouter1	vr2	active (nok)	contrail-control-0		
bgprouter2	vr1		contrail-control-1		
bgprouter2	vr3		contrail-control-1		

To display the resource status in the control node, run the following command, which gives the output for the BGP session:

root@helper ~] kubectl contrailstatus resource bgprouter -s bgp

LOCAL	NEIGHBOR	STATE	POD
bgprouter1	bgprouter2	established (ok)	contrail-control-0
bgprouter1	bgprouter3	active (nok)	contrail-control-0
bgprouter2	bgprouter1	established (ok)	contrail-control-1
bgprouter2	bgprouter3	established (ok)	contrail-control-1

All Planes Resource Status

To display the resource status on all of the planes:

```
[root@helper ~] # kubectl contrailstatus -all
NAME
                             STATUS
                                       PLANE
                                                 ERRORNOTES
apiserver-86789f7d8-q37qf
                             Active
                                       Config
NAME
                             STATUS
                                       PLANE
                                                 ERRORNOTES
                             Active
control-1
                                       control
BGP-1
                             Active
                                       control
XMPP-1
                             Active
                                       control
NAME
                             STATUS
                                       PLANE
                                                 ERRORNOTES
vrouter-86789f7d8-q37qk
                             Active
                                       data
[root@helper ~] #
```

Services Status for Multiple Nodes

The following (same) command displays the status of various services running on multiple nodes in a cluster. If the running controller is active without any errors, the status column next to the service is displayed as Active. If the controller has any errors, the status column of the controller is displayed as Not-Active. The output includes the status of various controllers and containers in the controllers.

To display the status of various services running on multiple nodes in a cluster:

[root@helper ~] # kubectl contrailstatus -all

NAME	STATUS	ERRORNOTES
apiserver-86885bf7d8-q27qk	Active	
apiserver-86885bf7d8-sdsdd	Active	
apiserver-86885bf7d8-sdsss	Active	
controller-6998bd846f-5cgf7	Active	
controller-6998bd846f-5cgf8	Active	
controller-6998bd846f-5cg10	Active	
cluster1-kubemanager-7cff895-sdfsd	Active	
cluster1-kubemanager-7cff895-sdfsa	Active	

NAME STATUS ERRORNOTES control-1 Active control-2 Active GGP-1 Active BGP-2 Active XMPP-1 Active Xmpp-2 Active			
control-2Activecontrol-3ActiveBGP-1ActiveBGP-2ActiveXMPP-1Active	NAME	STATUS	ERRORNOTES
control-3ActiveBGP-1ActiveBGP-2ActiveXMPP-1Active	control-1	Active	
BGP-1ActiveBGP-2ActiveXMPP-1Active	control-2	Active	
BGP-2ActiveXMPP-1Active	control-3	Active	
XMPP-1 Active	BGP-1	Active	
	BGP-2	Active	
Xmpp-2 Active	XMPP-1	Active	
	Xmpp-2	Active	

NAME	STATUS	ERRORNOTES
vrouter-86789f7d8-q37qk	Active	
vrouter-8905bf7d8-q47qk	Active	
vrouter-8688bf7d8-q57qk	Active	

[root@helper ~] #

RELATED DOCUMENTATION

Kubectl Contrailstatus for Upstream Kubernetes Kubectl Contrailstatus for OpenShift Container Platform Kubectl Contrailstatus for Amazon EKS

IPv4 and IPv6 Dual-Stack Networking

SUMMARY

Cloud-Native Contrail[®] Networking[™] (CN2) release 23.1 supports dual-stack networking for services. Previous releases supported dual-stack networking for pods, but 23.1 enables you to assign IPs to services from an IPv4 or IPv6 network. This article provides an overview of dual-stack and information

IN THIS SECTION

IPv4 and IPv6 Overview | 20

Dual-Stack Networking Prerequisites | 20

IPv4 and IPv6 Overview

A dual-stack device has network interfaces that send and receive both IPv4 and IPv6 packets. In the case of CN2 release 23.1, the dual-stack feature of your Kubernetes cluster assigns both IPv4 addresses and IPv6 addresses to pods and services.

Dual-Stack Networking Prerequisites

Dual-stack networking requires the following:

- Kubernetes version 1.20 or later
- Kubernetes nodes configured with dual stack IPv4/IPv6 network interfaces
- A Kubeadm or Kubespray Kubernetes cluster with dual-stack featureGate enabled

The CN2 deployer uses the IPv6 CIDR (podSubnet and serviceSubnet in the deployment) to create an IPv6 subnet for the podNetwork. Subsequent pod networks that you create contain an IPv6 subnet. As a result, pods receive IPv4 and IPv6 addresses.

RELATED DOCUMENTATION

IPv4/IPv6 dual-stack
Dual-stack support with kubeadm
Deploy a Production-Ready Kubernetes Cluster

Pod Scheduling

SUMMARY

Juniper Cloud-Native Contrail Networking (CN2) release 23.1 supports network-aware pod scheduling using contrail-scheduler. This feature enhances the Kubernetes pod scheduler with plugins that analyze the network metrics of a node before scheduling pods. This article provides overview, implementation, and deployment information about network-aware pod scheduling.

IN THIS SECTION

•	Pod Scheduling in Kubernetes 21
	Pod Scheduling in CN2 21
•	Network-Aware Pod Scheduling Overview 22
	Network-Aware Pod Scheduling Components 22
•	Deploy Network-Aware Pod Scheduling Components 23
•	Metrics Collector Deployment 23
•	Central Collector Deployment 24
	Contrail Scheduler Deployment 27
•	Use the Contrail Scheduler to Deploy Pods 31

Pod Scheduling in Kubernetes

In Kubernetes, scheduling refers to the process of matching pods to nodes so that the kubelet is able to run them. A scheduler monitors requests for pod creation and attempts to assign these pods to suitable nodes using a series of extension points during a scheduling and binding cycle. Potential nodes are filtered based on attributes like the resource requirements of a pod. If a node doesn't have the available resources for a pod, that node is filtered out. If more than one node passes the filtering phase, Kubernetes scores and ranks the remaining nodes based on their suitability for a given pod. The scheduler assigns a pod to the node with the highest ranking. If two nodes have the same score, the scheduler picks a node at random.

Pod Scheduling in CN2

CN2 release 22.4 enhanced the default Kubernetes pod scheduler to schedule pods based on the Virtual Machine Interface (VMI) considerations of DPDK nodes. This enhanced scheduler, called contrail-

scheduler, supports custom plugins that enable the scheduling of pods based on current active VMIs in a DPDK node.

CN2 release 23.1 improves on this feature by supporting two additional plugins. As a result of these plugins, contrail-scheduler schedules pods based on the following network metrics:

- Number of active ingress/egress traffic flows
- Bandwidth utilization
- Number of virtual machine interfaces (VMIs)

Network-Aware Pod Scheduling Overview

Many high-performance applications have bandwidth or network interface requirements as well as the typical CPU or VMI requirements. If contrail-scheduler assigns a pod to a node with low bandwidth availability, that application cannot run optimally. CN2 release 23.1 addresses this issue with the introduction of a metrics collector, a central collector, and custom scheduler plugins. These components collect, store, and process network metrics so that the contrail-scheduler scheduler pods based on these metrics.

Network-Aware Pod Scheduling Components

The following main components comprise CN2's network-aware pod scheduling solution:

- Metrics collector: This runs in a container alongside the vRouter pod that runs on each node in the cluster. The vRouter agent sends metrics data to the metrics collector over localhost: 6700 specified in the agent: default: collectors field of the vRouter CR Deployment. The metrics collector then forwards requested data to configured sinks which are specified in the configuration. The central collector is one of the configured sinks and recieves this data from the metrics collector.
- Central collector: This component acts as an aggregator and stores data received from all of the nodes in a cluster via the metrics collector. The central collector exposes gRPC endpoints which consumers use to to request this data for nodes in a cluster. For example, the contrail-scheduler uses these gRPC endpoints to retrieve and process network metrics and schedule pods accordingly.
- Contrail scheduler: This custom scheduler introduces the following three custom plugins:
 - VMICapacity plugin (available from release 22.4 onwards): Implements Filter, Score, and NormalizeScore extension points in the scheduler framework. The contrail-scheduler uses these extension points to determine the best node to assign a pod to based on active VMIs.

- FlowsCapacity plugin: Determines the best node to schedule a pod based on the number of active flows in a node. Too many traffic flows on a node means more competition for new pod traffic. Pods and nodes with a lower flow count are ranked higher by the scheduler.
- BandwidthUsage plugin: Determines the best node to assign a pod based on the bandwidth usage of a node. The node with the least bandwidth usage (ingoing and outgoing traffic) per second is ranked highest.

NOTE: Depending on the configured plugins, each plugin sends out scores to the scheduler. The scheduler takes the weighted scores from from all of the plugins and finds the best node to schedule a pod.

Deploy Network-Aware Pod Scheduling Components

See the following sections for information about deploying the components for network-aware pod scheduling:

"Metrics Collector Deployment" on page 23

"Central Collector Deployment" on page 24

"Contrail Scheduler Deployment" on page 27

Metrics Collector Deployment

CN2 includes the metrics collector in vRouter pod deployments by default. The agent: default: field of the vRouter spec contains a collectors: field which is configured with the metric collector reciever address. The example below shows the value collectors: - localhost: 6700. Since the the metrics collector runs in the same pod as the vRouter agent, it can communicate over the localhost port. Note that port 6700 is fixed as the metrics collector reciever address and cannot be changed. The vRouter agent sends metrics data to this address.

The following is a section of a default vRouter deployment with the collector enabled:

```
apiVersion: dataplane.juniper.net/v1
kind: Vrouter
metadata:
   name: contrail-vrouter-nodes
   namespace: contrail
```

spec:		
agent:		
default:		
collectors:		
- localhost:6700		
xmppAuthEnable: true		
sandesh:		
introspectSslEnable: true		

Central Collector Deployment

The central collector Deployment object must always have a replica count set to 1. The following Deployment section shows an example:

```
spec:
selector:
matchLabels:
component: central-collector
replicas: 1
template:
metadata:
labels:
component: central-collector
```

A configMap provides key-value configuration data to the pods in your cluster. Create a configMap for the central collector configuration. This configuration is mounted in the container.

The following is an example of a central collector config file:

```
http_port: 9090
tls_config:
   key_file: /etc/config/server.key
   cert_file: /etc/config/server.crt
   ca_file: /etc/config/ca.crt
service_name: central-collector.contrail
metric_configmap:
   name: mc_configmap
   namespace: contrail
   key: config.yaml
```

This config file contains the following fields:

- http_port: Specifies the port that the central collector gRPC service runs on.
- tls_config: Specifies what server_name and key_file the central collector service is associated with. This field contains upstream (northbound API) server information.
- service_name: Specifies the name of the service the central collector exposes. In this case, centralcollector.contrail is exposed as a service on top of the central collector Deployment. Consumers within the cluster can interact with the central collector using this service name.
- metric_configmap: The fields in this section designate the details of the metrics collector configMap.
 Central collector uses this information to configure a metrics-collector sink with the required metrics the sink wants to receive. The following is a sample command to create a configMap:

kubectl create cm -n contrail central-collector-config -from-file=config.yaml=<path-to-configfile>

The following is an example of a central collector Deployment:

```
apiVersion: apps/v1
kind: Deployment
metadata:
 name: central-collector
 namespace: contrail
 labels:
   app: central-collector
spec:
  replicas: 1
 selector:
    matchLabels:
      app: central-collector
 template:
    metadata:
      labels:
        app: central-collector
    spec:
      securityContext:
        fsGroup: 2000
        runAsGroup: 3000
        runAsNonRoot: true
        runAsUser: 1000
```

containers:

```
- name: contrail-scheduler
  image: enterprise-hub.juniper.net/contrail-container-prod/central-collector:latest
 command:
  - /central-collector
  - --kubeconfig=/tmp/config/kubeconfig
  - --config=/etc/central-collector/config.yaml
  imagePullPolicy: Always
  volumeMounts:
  - mountPath: /tmp/config
   name: kubeconfig
    readOnly: true
  - mountPath: /etc/central-collector
   name: central-collector-config
    readOnly: true
  - mountPath: /etc/config/tls
   name: tls
    readOnly: true
volumes:
- name: kubeconfig
 secret:
   secretName: cc-kubeconfig
- name: tls
 secret:
   secretName: central-collector-tls
- name: central-collector-config
  configMap:
```

NOTE: Verify the volume and volumeMounts fieds before deploying.

name: central-collector-config

The central collector service is exposed on top of the Deployment object. The following YAML file is an example of a central collector service file:

```
apiVersion: v1
kind: Service
metadata:
   name: central-collector
   namespace: contrail
spec:
```

```
selector:
  component: central-collector
ports:
  - name: grpc
  port: <port-as-per-config>
  - name: json
  protocol: TCP
  port: 10000
```

NOTE: The name field must match the service name specified in the central collector configuration. The namespace must match the namespace of the central collector Deployment. For example, namespace: contrail.

Contrail Scheduler Deployment

Perform the following steps to deploy the contrail-scheduler:

• Create a namespace for the contrail-scheduler.

kubectl create ns contrail-scheduler

- Create a ServiceAccount object (required) and configure the cluster roles for the ServiceAccount. A ServiceAccount assigns a role to a pod or component within a cluster. In this case, the fields kind: ClusterRole and name: system:kube-scheduler grant the contrail-scheduler ServiceAccount the same permissions as the default Kubernetes scheduler (kube-scheduler).
- Create a configMap for the VMI plugin configuration. You must create the configMap within the same namespace as the contrail-scheduler Deployment.

kubectl create configmap vmi-config -n contrail-scheduler --from-file=vmi-configconfig>

The following is an example of a VMI plugin config:

```
nodeLabels:
    "test-agent-mode": "dpdk"
```

maxVMICount: 64
address: "central-collector.contrail:9090"

• Create a Secret for the kubeconfig file. This file is then mounted in the contrail-scheduler Deployment. Secrets store confidential data as files in a mounted volume or as a container environment variable.

kubectl create secret generic kubeconfig -n contrail-scheduler --from-file=kubeconfig=<pathto-kubeconfig-file>

• Create a configMap for the contrail-scheduler config.

kubectl create configmap scheduler-config -n contrail-scheduler --from-file=schedulerconfig=<path-to-scheduler-config>

The following is an example of a scheduler config:

```
apiVersion: kubescheduler.config.k8s.io/v1beta3
clientConnection:
 acceptContentTypes: ""
 burst: 100
 contentType: application/vnd.kubernetes.protobuf
 kubeconfig: /tmp/config/kubeconfig
 qps: 50
enableContentionProfiling: true
enableProfiling: true
kind: KubeSchedulerConfiguration
leaderElection:
 leaderElect: false
profiles:
  - schedulerName: contrail-scheduler
 pluginConfig:
 - args:
   apiVersion: kubescheduler.config.k8s.io/v1beta3
   kind: VMICapacityArgs
   config: /tmp/vmi/config.yaml
  name: VMICapacity
      - args:
          apiVersion: kubescheduler.config.k8s.io/v1beta3
          kind: FlowsCapacityArgs
          address: central-collector.contrail:9090
```

```
name: FlowsCapacity
- args:
    apiVersion: kubescheduler.config.k8s.io/v1beta3
    kind: BandwidthUsageArgs
    address: central-collector.contrail:9090
    name: BandwidthUsage
    plugins:
    multiPoint:
    enabled:
        - name: VMICapacity
        weight: 50
        - name: FlowsCapacity
        weight: 1
        - name: BandwidthUsage
        weight: 20
```

Note the following fields:

- schedulerName: The name of the scheduler you want to deploy.
- pluginConfig: Contains information about the plugins included in the contrail-scheduler deployment. The deployment includes the following plugins:
 - VMICapacity
 - FlowsCapacity
 - BandwidthUsage
- config: This field contains the filepath where the VMI plugin config is mounted.
- multiPoint: You can enable extension points for each of the included plugins. Instead of having to enable specific extension points for a plugin, the multiPoint field let's you enable or disable all of the extension points that are developed for a given plugin. The weights of a plugin decide the priority of a particular score from a plugin. This means that at the end of scoring, all of the plugins send out a weighted score. A pod is scheduled on a node with the highest aggregated score.
- Create a contrail-scheduler Deployment. The following is an example of a Deployment:

```
apiVersion: apps/v1
kind: Deployment
metadata:
    name: contrail-scheduler
    namespace: contrail-scheduler
    labels:
```

```
app: scheduler
spec:
  replicas: 1
  selector:
   matchLabels:
      app: scheduler
  template:
    metadata:
      labels:
        app: scheduler
   spec:
      serviceAccountName: contrail-scheduler
      securityContext:
        fsGroup: 2000
        runAsGroup: 3000
        runAsNonRoot: true
        runAsUser: 1000
      containers:
      - name: contrail-scheduler
        image: <registry>/contrail-scheduler:<tag>
        command:
        - /contrail-scheduler
        - --authentication-kubeconfig=/tmp/config/kubeconfig
        - --authorization-kubeconfig=/tmp/config/kubeconfig
        - --config=/tmp/scheduler/scheduler-config
        - --secure-port=10271
        imagePullPolicy: Always
        livenessProbe:
          failureThreshold: 8
          httpGet:
            path: /healthz
            port: 10271
            scheme: HTTPS
          initialDelaySeconds: 30
          periodSeconds: 10
          timeoutSeconds: 30
        resources:
          requests:
            cpu: 100m
        startupProbe:
          failureThreshold: 24
          httpGet:
            path: /healthz
```



After you apply this Deployment, the new contrail-scheduler is active.

Use the Contrail Scheduler to Deploy Pods

Enter the name of your contrail-scheduler to the schedulerName field to use the contrail-scheduler to schedule (deploy) new pods. The following is an example of a pod manifest with the schedulerName defined:

apiVersion: v1 kind: Pod metadata: name: my-app labels: app: web

```
spec:
schedulerName: contrail-scheduler
containers:
    - name: app
    image: busybox
    command:
    - sh
    - -c
    - sleep 500
```

Pod Scheduling for Multi-cluster Deployments

SUMMARY

Juniper Cloud-Native Contrail Networking (CN2) release 23.2 supports network-aware pod scheduling for multi-cluster deployments. This article provides information about the changes to this feature from the previous release (23.1), and additional components for multi-cluster support.

IN THIS SECTION

•	Pod Scheduling in CN2 32
•	Network-Aware Pod Scheduling Overview 33
•	Custom Controlllers 33
•	multi-cluster Pod Scheduling Components 35
•	Metrics Collector Deployment 35
•	Create Permissions 36
•	Central Collector Deployment 40
•	Create Configmaps 40

Pod Scheduling in CN2

NOTE: This article provides information about network-aware pod scheduling for multi-cluster deployments. For information about this feature for single-cluster deployments, see "Pod Scheduling" on page 21.

Previous releases of CN2 enhanced the default Kubernetes pod scheduler to support custom plugins. This enhanced scheduler, called contrail-scheduler, schedules pods based on the following network metrics:

- Number of active ingress/egress traffic flows
- Bandwidth utilization
- Number of virtual machine interfaces (VMIs)

Network-Aware Pod Scheduling Overview

Many high-performance applications have bandwidth or network interface requirements as well as the typical CPU or VMI requirements. If contrail-scheduler assigns a pod to a node with low bandwidth availability, that application cannot run optimally. CN2 release 23.1 addressed this issue with the introduction of a metrics-collector, a central-collector, and custom scheduler plugins. These components collect, store, and process network metrics so that the contrail-scheduler scheduler pods based on these metrics. CN2 release 23.2 enables multi-cluster deployments to take advantage of this feature.

Custom Controlllers

In 23.2, CN2 introduces a metrics controller CR and a central collector CR. The following two new controllers manage the CRs:

- MetricsConfig controller: This controller reconciles and monitors the MetricsConfig custom resource (CR). This controller writes config information for the metrics-collectors in the central and distributed clusters. This controller also listens to create, read, update, delete (CRUD) events of kubemanager resources on the central cluster. The config file of a metrics-collector contains the following information:
 - The writeLocation field references the metrics-collector configMap details for mounting. The name, namespace, and key of the metrics-collector's configMap for writing it's configuration.
 - The receiving service's IP address and port. The metrics-collector uses this service IP and port to forward requested metrics data.
 - Configuration data regarding Transport Layer Security TLS (if required).
 - A metrics section which defines the types of metrics the receiving service is requesting.

The following is an example of a metrics-collector config:

```
receivers:
- encoding: json
metrics:
- <relevant_metrics>
- <relevant_metrics>
serviceName: <service_name_or_ip>
port: <receiver_listener_port>
writeLocation:
name: mc_configmap
namespace: contrail
key: config.yaml
```

• CentralCollector controller: This controller also reconciles and monitors the central collector CR. The CentralCollector controller manages the LCM of the central-collector. Additionally, it creates a MetricsConfig CR, which then configures the metrics-collector configuration. The CentralCollector controller also creates the clusterIP service for the central-collector. Unlike 23.1, you do not need to create a central-collector Deployment or configMap. Create and apply the CR and the central-collector controller manages all configuration, deployment, and LCM functions.

```
apiVersion: collectors.juniper.net/v1
kind: CentralCollector
metadata:
   name: central-collector
   namespace: contrail
spec:
   common:
    containers:
        - image: REGISTRY/central-collector:TAG
        name: central-collector
   metricsCollectorConfigmapLoc:
        name: "metrics-collector-configmap"
        namespace: contrail
```

multi-cluster Pod Scheduling Components

Aside from the CentralCollector controller and the MetricsConfig controller, the following components comprise CN2's network-aware pod scheduling solution for multi-cluster deployments:

- Metrics-collector: This component runs in a container alongside the vRouter pod that runs on each node in the central cluster and distributed clusters. The metrics-collector then forwards requested data to configured sinks which are specified in the configuration. The central collector is one of the configured sinks and recieves this data from the metrics collector. This release adds an additional field in the config file of the metrics collector. This field designates a cluster name, specifying which cluster the metrics collector is collecting data from and will send the same in the metadata to the reciever.
- Central-collector: This component acts as an aggregator and stores data received from all of the nodes in a cluster via the metrics collector. The central collector exposes gRPC endpoints which consumers use to request this data for nodes in a cluster.
- Contrail-scheduler: This custom scheduler introduces the following three custom plugins:
 - VMICapacity plugin (available from release 22.4 onwards): Implements Filter, Score, and NormalizeScore extension points in the scheduler framework. The contrail-scheduler uses these extension points to determine the best node to assign a pod to based on active VMIs.
 - FlowsCapacity plugin: Determines the best node to schedule a pod based on the number of active flows in a node. Too many traffic flows on a node means more competition for new pod traffic. Pods and nodes with a lower flow count are ranked higher by the scheduler.
 - BandwidthUsage plugin: Determines the best node to assign a pod based on the bandwidth usage of a node. The node with the least bandwidth usage (ingoing and outgoing traffic) per second is ranked highest.

Metrics Collector Deployment

CN2 includes the metrics collector in vRouter pod deployments by default. The agent: default: field of the vRouter spec contains a collectors: field which is configured with the metric collector reciever address. The example below shows the value collectors: - localhost: 6700. Since the the metrics collector runs in the same pod as the vRouter agent, it can communicate over the localhost port. Note that port 6700 is fixed as the metrics collector reciever address and cannot be changed. The vRouter agent sends metrics data to this address.

The following is a section of a default vRouter deployment with the collector enabled:

```
apiVersion: dataplane.juniper.net/v1
kind: Vrouter
metadata:
   name: contrail-vrouter-nodes
   namespace: contrail
spec:
   agent:
    default:
        collectors:
            localhost:6700
            xmppAuthEnable: true
        sandesh:
            introspectSslEnable: true
```

Create Permissions

After you configure the vRouter to send metrics to the metrics-collector over port 6700, you must apply a Role-Based Access (RBAC) manifest. Applying this manifest creates required permissions for the contrail-telemetry-controller. The contrail-telemetry-controller reconciles the MetricsConfig CR and creates the configMap for the metrics-collector.

The following is an example RBAC manifest. Note that this manifest also creates the namespace (contrail-analytics) for the metrics-collector.

```
apiVersion: v1
kind: Namespace
metadata:
   name: contrail-analytics
----
apiVersion: v1
kind: ServiceAccount
metadata:
   name: contrail-telemetry-controller
   namespace: contrail-analytics
----
apiVersion: rbac.authorization.k8s.io/v1
kind: ClusterRole
```

```
{\tt metadata:}
```

creationTimestamp: null

```
name: contrail-telemetry-controller-role
```

rules:

- apiGroups:

- ""

resources:

- configmaps
- verbs:
- get
- list
- watch
- create
- update
- patch
- delete
- apiGroups:

- ""

- resources:
- configmaps/status

verbs:

- get
- update
- patch
- apiGroups:

```
- ""
```

resources:

- namespaces
- pods
- pods/status

verbs:

- get
- list
- watch
- patch
- apiGroups:
 - apps

resources:

- deployments

verbs:

- get
- update
- list

- watch
- apiGroups:
 - ""
 - resources:
 - secrets
 - verbs:
 - create
 - delete
 - get
 - list
 - patch
 - update
 - watch
- apiGroups:
 - telemetry.juniper.net

resources:

- metricsconfigs

verbs:

- create
- delete
- get
- list
- patch
- update
- watch
- apiGroups:
 - telemetry.juniper.net

resources:

- metricsconfigs/status

verbs:

- get
- patch
- update

- apiGroups:

- configplane.juniper.net

resources:

- kubemanagers

verbs:

- create
- delete
- get
- list
- patch

39

```
- update
  - watch
- apiGroups:
 - configplane.juniper.net
  resources:
 - kubemanagers/status
 verbs:
 - get
  - patch
  - update
- - -
apiVersion: rbac.authorization.k8s.io/v1
kind: ClusterRoleBinding
metadata:
 name: contrail-telemetry-controller-role-rolebinding
roleRef:
 apiGroup: rbac.authorization.k8s.io
 kind: ClusterRole
 name: contrail-telemetry-controller-role
subjects:
- kind: ServiceAccount
 name: contrail-telemetry-controller
```

After applying the RBAC manifest, you must create a Deployment for the contrail-telemetry-controller. The following is an example Deployment.

```
apiVersion: apps/v1
kind: Deployment
metadata:
   name: contrail-telemetry-controller
   namespace: contrail-analytics
   labels:
      app: contrail-telemetry-controller
spec:
   replicas: 1
   selector:
      matchLabels:
      app: contrail-telemetry-controller
template:
      metadata:
      labels:
```

namespace: contrail-analytics

Central Collector Deployment

Apply the CentralCollector CR. Once applied, the CentralCollector controller creates all of the necessary objects for the central-collector. The following is an example CentralCollector CR.

```
apiVersion: collectors.juniper.net/v1
kind: CentralCollector
metadata:
    name: central-collector
    namespace: contrail
spec:
    common:
    containers:
        - image: <REGISTRY>/central-collector:<TAG>
        name: central-collector
    metricsCollectorConfigmapLoc:
        name: "metrics-collector-configmap"
        namespace: contrail
```

Create Configmaps

Perform the following steps to create configMaps for multi-cluster pod-scheduling components.

NOTE: Perform these steps in each of the clusters of your multi-cluster environment.

1. Create a configMap called cluster-details:

Applying the CentralCollector CR in the previous section also creates a configMap called cluster-details. You must replicate this configMap in the same namespace where you intend to deploy contrail-scheduler. The CR creates this configMap in the same namespace as the CR. The configMap includes the following information:

- Central-collector's service clusterIP
- Metrics gRPC service port: Used by the contrail-scheduler to retrieve and process network metrics and schedule pods accordingly.
- Name of the cluster where the configMap is located: Used to identify the cluster where contrailscheduler is running.

The following is an example cluster-details configMap:

clustername: <name_of_the_cluster>
centralcollectoraddress: <ip:port>

2. Create a vmi-config configMap: This configMap defines the maximum VMI count allowed on DPDK nodes. The following is an example configMap:

```
nodeLabels:
    "agent-mode": "dpdk"
maxVMICount: 64
```

3. Create a configMap for the contrail-scheduler: This configMap defines the contrail-scheduler configuration. The following is an example configMap with VMICapacity, FlowsCapacity, and BandwidthUsage pluigin information:

```
apiVersion: kubescheduler.config.k8s.io/v1
clientConnection:
    acceptContentTypes: ""
    burst: 100
    contentType: application/vnd.kubernetes.protobuf
    kubeconfig: /tmp/config/kubeconfig
```

```
qps: 50
enableContentionProfiling: true
enableProfiling: true
kind: KubeSchedulerConfiguration
leaderElection:
  leaderElect: false
profiles:
- schedulerName: no-plugins-scheduler
- schedulerName: vmi-scheduler
  pluginConfig:
  - args:
      apiVersion: kubescheduler.config.k8s.io/v1beta3
      kind: VMICapacityArgs
      config: /tmp/vmi/config.yaml
      clusterConfig: /tmp/cluster/config.yaml
    name: VMICapacity
  plugins:
    multiPoint:
      enabled:
      - name: VMICapacity
- schedulerName: flows-scheduler
  pluginConfig:
  - args:
      apiVersion: kubescheduler.config.k8s.io/v1beta3
      kind: FlowsCapacityArgs
      clusterConfig: /tmp/cluster/config.yaml
    name: FlowsCapacity
  plugins:
   multiPoint:
      enabled:
      - name: FlowsCapacity
- schedulerName: bandwidth-scheduler
  pluginConfig:
  - args:
      apiVersion: kubescheduler.config.k8s.io/v1beta3
      kind: BandwidthUsageArgs
      clusterConfig: /tmp/cluster/config.yaml
    name: BandwidthUsage
  plugins:
   multiPoint:
      enabled:
      - name: BandwidthUsage
- schedulerName: contrail-scheduler
```

pluginConfig:

- args: apiVersion: kubescheduler.config.k8s.io/v1beta3 kind: VMICapacityArgs config: /tmp/vmi/config.yaml clusterConfig: /tmp/cluster/config.yaml name: VMICapacity - args: apiVersion: kubescheduler.config.k8s.io/v1beta3 kind: FlowsCapacityArgs clusterConfig: /tmp/cluster/config.yaml name: FlowsCapacity - args: apiVersion: kubescheduler.config.k8s.io/v1beta3 kind: BandwidthUsageArgs clusterConfig: /tmp/cluster/config.yaml name: BandwidthUsage plugins: multiPoint: enabled: - name: VMICapacity weight: 50 - name: FlowsCapacity weight: 1 - name: BandwidthUsage

- weight: 20
- 4. Create a ServiceAccount object (required) and configure the ClusterRoles for the ServiceAccount. A ServiceAccount assigns a role to a pod or component within a cluster. In the example below, the ServiceAccount assigns the same permissions as the default Kubernetes scheduler (kube-scheduler). The following is an example ServiceAccount:

```
apiVersion: v1
kind: ServiceAccount
metadata:
  name: contrail-scheduler
  namespace: contrail-scheduler
```

The following is an example ClusterRoles object:

```
apiVersion: rbac.authorization.k8s.io/v1
kind: ClusterRoleBinding
metadata:
  name: contrail-scheduler
subjects:
- kind: ServiceAccount
  name: contrail-scheduler
  namespace: contrail-scheduler
roleRef:
  kind: ClusterRole
  name: system:kube-scheduler
  apiGroup: rbac.authorization.k8s.io
---
apiVersion: rbac.authorization.k8s.io/v1
kind: ClusterRoleBinding
metadata:
  name: contrail-scheduler-as-volume-scheduler
subjects:
- kind: ServiceAccount
  name: contrail-scheduler
  namespace: contrail-scheduler
roleRef:
  kind: ClusterRole
  name: system:volume-scheduler
  apiGroup: rbac.authorization.k8s.io
---
apiVersion: rbac.authorization.k8s.io/v1
kind: RoleBinding
metadata:
  name: contrail-scheduler-extension-apiserver-authentication-reader
  namespace: contrail-scheduler
roleRef:
  kind: Role
  name: extension-apiserver-authentication-reader
  apiGroup: rbac.authorization.k8s.io
subjects:
- kind: ServiceAccount
  name: contrail-scheduler
  namespace: contrail-scheduler
```

5. Create a kubeconfig Secret. Mount the kubeconfig file within the scheduler container when you apply the contrail-scheduler Deployment.

kubectl create secret generic kubeconfig -n contrail-scheduler --from-file=kubeconfig=<pathto-kubeconfig-file>

6. Create a Deployment for the contrail-scheduler. The following is an example Deployment:

```
apiVersion: apps/v1
kind: Deployment
metadata:
  name: contrail-scheduler
  namespace: contrail-scheduler
  labels:
    app: scheduler
spec:
  replicas: 1
  selector:
    matchLabels:
      app: scheduler
  template:
    metadata:
      labels:
        app: scheduler
    spec:
      serviceAccountName: contrail-scheduler
      securityContext:
        fsGroup: 2000
        runAsGroup: 3000
        runAsNonRoot: true
        runAsUser: 1000
      containers:
      - name: contrail-scheduler
        image: <REGISTRY>/contrail-scheduler:<TAG>
        command:
        - /contrail-scheduler
        - --authentication-kubeconfig=/tmp/config/kubeconfig
        - --authorization-kubeconfig=/tmp/config/kubeconfig
        - --config=/tmp/scheduler/scheduler-config
        - --secure-port=10271
        imagePullPolicy: Always
```

livenessProbe: failureThreshold: 8 httpGet: path: /healthz port: 10271 scheme: HTTPS initialDelaySeconds: 30 periodSeconds: 10 timeoutSeconds: 30 resources: requests: cpu: 100m startupProbe: failureThreshold: 24 httpGet: path: /healthz port: 10271 scheme: HTTPS initialDelaySeconds: 30 periodSeconds: 10 timeoutSeconds: 30 volumeMounts: - mountPath: /tmp/config name: kubeconfig readOnly: true - mountPath: /tmp/scheduler name: scheduler-config readOnly: true - mountPath: /tmp/vmi name: vmi-config readOnly: true - mountPath: /tmp/cluster name: cluster-details readOnly: true hostPID: false volumes: - name: kubeconfig secret: secretName: kubeconfig - name: scheduler-config configMap: name: scheduler-config - name: vmi-config

46

```
configMap:
    name: vmi-config
- name: cluster-details
    configMap:
    name: cluster-details
```

NOTE: When creating Secrets or configMaps, ensure that the key used during the creation matches the key used when mounting them in the Deployment. For example, in the Deployment above, the path /tmp/scheduler/scheduler-config is provided in the command section, and /tmp/ scheduler is provided in the volume mount section. In this case, the key is "scheduler-config". If the keys do not match, you will need to explicitly specify a custom key in the volume mounts for custom file names. If no file name is given explicitly, use "config.yaml" as the key name.

Priority Classes for Critical CN2 Components

SUMMARY

Juniper Cloud-Native Contrail Networking (CN2) release 23.2 supports PriorityClass objects for core CN2 components. Default priority classes designate critical CN2 pods and nodes with the highest priority for pod schedling and access to resources.

IN THIS SECTION

- CN2 Components Overview | 47
- CN2 Implementation | 48

CN2 Components Overview

CN2 components provide critical networking functionality to Kubernetes clusters. Most CN2 clusters contain a dedicated set of nodes where cluster-related services do not share the same resources with user applications. In managed clusters like Amazon Elastic Kubernetes Service (EKS), the default environment configuration doesn't support the same resource isolation. During times when cluster components and services are competing for compute resources, kube-scheduler should prioritize core CN2 components' access to resources.

CN2 Implementation

CN2 release 23.2 introduces the PriorityClass object. A PriorityClass lets you map a priority, in the form of an integer value, to a priority class name. The higher the value, the higher the priority. By default, the cn2-deployer controllers use Kubernetes' built-in high-priority classes:

- system-cluster-critical: For config and control pods.
- system-node-critical: For vRouter pods.

The cn2-deployer uses these default priority classes when you apply CN2 manifests. We strongly recommend that you use these classes because they have the highest priority value. This means that kube-scheduler prioritizes these pods for scheduling, maintenance, and access to resources.

You may restrict usage of high-priority classes to a specific list of namespaces. This custom list of namespaces must include contrail, contrail-system, and contrail-deploy or else you are not able to deploy essential CN2 resources. Alternatively, you can create a custom PriorityClass and enter the name of the custom class in the priorityClassName field of the common section of a CN2 custom resource manifest.

The following example is a common section of a CN2 manifest.

```
apiVersion: configplane.juniper.net/v1
kind: ApiServer
metadata:
    name: contrail-k8s-apiserver
    namespace: contrail-system
spec:
    common:
    priorityClassName: NAME_OF_CLASS
    containers:
        - image: image:tag
        name: contrail-k8s-apiserver
        serviceAccountName: contrail-system-serviceaccount
```

RELATED DOCUMENTATION

https://kubernetes.io/docs/tasks/administer-cluster/guaranteed-scheduling-critical-addon-pods/

https://kubernetes.io/docs/concepts/policy/resource-quotas/#limit-priority-class-consumption-by-default

https://kubernetes.io/docs/concepts/scheduling-eviction/pod-priority-preemption/#priorityclass



CN2 Apstra Integration

Extend Virtual Networks to Apstra | 50

Extend Virtual Networks to Apstra

SUMMARY

Starting in CN2 Release 23.1 or later, you can extend virtual networks from your Kubernetes cluster to the datacenter fabric managed by Apstra.

IN THIS SECTION

•	Overview 50
•	Example: CN2 Kubernetes Deployment with SR-IOV Pods 51
•	Prerequisites 53
•	Installation Workflow 55
•	Install and Configure the CN2 Apstra Plug- In 57
•	Install the CN2 IPAM Plug-In 61
•	Intra-VN and Inter-VN Approaches 62
•	Introduction to Configuring Intra-VN Communication 66
•	Configure Intra-VN Communication 69
•	Introduction to Configuring Inter-VN Communication 77
•	Configure Inter-VN Communication 79
•	Configure Inter-VN Communication Between SR-IOV Pods 80
•	Configure Inter-VN Communication Between SR-IOV Pods and Non-SR-IOV Pods 82
	Configure Inter-VN Communication Between SR-IOV Pods, Non-SRIOV Pods and BMS 87

Overview

Data centers typically have a mix of containerized workloads (SR-IOV pods, non-SR-IOV pods) and BMS. SR-IOV servers are being used extensively in data centers as these servers enable efficient I/O virtualization. When you create workloads on SR-IOV servers and attach virtual functions to the pods, the workloads use the fabric underlay directly. However, you might have a scenario where there is a need for communication between SRIOV pods, non-SRIOV pods, and BMS.

The different types of workloads are as follows:

- SR-IOV pods: SR-IOV pods use the IP fabric underlay directly for communication. The SR-IOV technology enables the physical NIC to be split into several virtual functions. The pods attach to the virtual functions of the SR-IOV enabled NICs. SR-IOV-enabled NICs on servers are used to deliver efficient I/O virtualization. These virtual NICs or virtual functions can transmit and receive packets directly from the fabric to which the CN2 data network is attached.
- Non-SR-IOV pods: Non-SR-IOV pods use the vRouter overlays for communication with other non-SR-IOV pods.
- **BMS**: BMS are physical nodes and are not part of the CN2 cluster. BMS use the fabric underlay for communication with pods. On the BMS, you can run applications directly on the native OS or run applications on containers.

Juniper Apstra is used to provision the fabric to provide the required underlay connectivity for the different workloads. Apstra is Juniper's intent-based networking software that automates and validates the design, deployment, and operation of data center networks. CN2 integrates with the Apstra software to provision the fabric underlay. For more information about Apstra, see the Juniper Apstra User Guide.

NOTE: We refer to *primary nodes* in our documentation. Kubernetes refers to *master nodes*. References in this guide to primary nodes correlate with master nodes in Kubernetes terminology.

Example: CN2 Kubernetes Deployment with SR-IOV Pods

Figure 1 on page 52 shows an example of a CN2 Kubernetes deployment. This deployment uses Apstra to provision the IP fabric underlay for the SR-IOV pods. Table 1 on page 52 describes the different components.

Figure 1: CN2 Kubernetes Deployment




Table 3: CN2 Apstra Components

Component	Description	
SR-IOV worker nodes	The SR-IOV worker nodes connect to the leaf devices in the IP fabric. These nodes, which are part of the CN2 cluster, have SRIOV-enabled NICs which can be split into virtual functions. When you create a pod on an SR-IOV worker node, the pod's interface can be attached to a virtual function on the SR-IOV-enabled NIC. The SRIOV- enabled NICs are in turn connected to the leaf devices in the IP fabric.	
CN2 Apstra plug-in	The CN2 Apstra plug-in extends the virtual network to the IP fabric. This plug-in listens for CN2 Kubernetes events such as creating a NAD, attaching pods to the virtual network, and creating a Virtual Network Router (VNR). The plug-in then configures the IP fabric for the underlay through Apstra.	

Table 3: CN2 Apstra Components (Continued)

Component	Description
Apstra	Apstra provisions the IP fabric to provide the required underlay connectivity for SR-IOV pods. Apstra also provides topology information regarding which leaf port is connected to which worker node. The CN2 Apstra plug-in uses this information to configure virtual network membership. The plug-in configures virtual-network membership on relevant fabric ports based on the worker node in which the SR-IOV pod is spawned.

Prerequisites

IN THIS SECTION

• Considerations | 54

To use this feature, you must install the following:

- Juniper Apstra version 4.1.2 or higher
- A CN2 cluster with the following items installed:
 - SR-IOV worker nodes that have SR-IOV-enabled NICs
 - Non-SR-IOV worker nodes
- The following plug-ins:
 - Multus Plug-In
 - SR-IOV Network Device Plug-In
 - CN2 IPAM Plug-In
- Licenses on the switches you are using in your topology

Juniper QFX switches require software licenses for advanced features. To ensure your that your IP fabric has the required licenses, see the Juniper Networks Licensing Guide.

NOTE: Make sure that you onboard the fabric to your Apstra blueprint as described in Step 4 in the "Installation Workflow" on page 55.

Considerations

Read through this list of considerations before you begin the installation:

- This feature assumes:
 - CN2 single-cluster deployments
 - Basic approaches for Intra-VN and Inter-VN communication between SR-IOV pods, non-SR-IOV pods, and BMS. Other forms of routing, such as hub-and-spoke routing, are not supported.
 - A simple spine-leaf topology where the SR-IOV worker node is connected to only one leaf device. If an SR-IOV worker node is connected to multiple leaf ports, ensure that you configure all the leaf ports on all the leaf devices to which this SR-IOV worker node is connected.
- Pods can be SR-IOV pods or non-SR-IOV pods. SR_IOV pods use the fabric underlay whereas Non-SR-IOV pods use the overlay though the vRouter.
- BMS is not part of the CN2 cluster.
- The entire BMS can be used exclusively for running applications directly on the host OS, where the IP is configured on the physical interface.

Or

BMS is running multiple VMs or containers, where the IP addresses are configured on the virtual interface.

- In the Intra-VN approach, the same subnet is used by CN2 for allocating IPs to both SR-IOV and non-SRI-OV pods. From the same subnet, you must use the unallocated IPs for configuring IPs in the BMS.
- When you create you a create BMS virtual network in Apstra, you must select all the leaf swtiches in that blueprint even if the BMS is connected to only one switch.
- You cannot edit the fields in the virtual networks and NADs (such as vlanID and VNI) that were created in CN2. To change these fields, you must re-create the virtual networks and NADs.
- Apstra accepts only VNIs greater or equal to 4096. Starting in CN2 release 23.1, on newer installations of CN2, we are allocating VNIs from 4096. Hence, this feature will not work on existing

CN2 setups. If you have an existing CN2 setup upgraded from a previous release, you must run a script to release free VNIs whose value is less that 4096.

- Ensure that the allocated vlanID does not conflict with those vlanID's allocated in Apstra. For example, you might want to use VLANs in the higher range (for example, 2000 and above) in CN2.
- The IP addresses for the pods are automatically allocated by the CN2 IPAM plug-in.
- In CN2, you must manually configure the routes on the pods for Inter-VN routing. For example: you can use the command ip route add 10.30.30.0/8 via 10.20.20.1 to reach the 10.30.30.0/8 subnet.
- Overlapping IP addresses and bonded interfaces (link from the SR-IOV-enabled NICs to the leaf switches) are not in use.
- Only IPv4 addressing is supported for this feature.

Installation Workflow

Follow the steps in this procedure to install and to configure the CN2 Apstra plug-in and its prerequisites:

1. Install the Apstra Software.

Install and configure Apstra version 4.1.2 or higher. See the Juniper Apstra Installation and Upgrade Guide.

If you have an existing data center network, Apstra is already managing the fabric. Make sure that you assign the required resource pools such as ASNs and loopback IP addresses for the blueprint.

2. Install a CN2 Cluster.

Install and configure a CN2 cluster that contains Kubernetes worker nodes. See the Install sections in the CN2 Installation Guide for Upstream Kubernetes or CN2 Installation Guide for OpenShift Container Platforms for instructions.

- **3.** Install the Plug-Ins.
 - a. Multus Plug-In:

This plug-in enables you to attach multiple network interfaces to pods. See the Multus CNI for Kubernetes or Multus CNI for OpenShift documentation for installation instructions.

b. SR-IOV Network Device Plug-In:

This plug-in discovers and advertises networking resources for SR-IOV virtual functions on a Kubernetes host. See the SR-IOV Network Device Plugin for Kubernetes or SR-IOV Network Device Plugin for OpenShift documentation for instructions.

c. CN2 Apstra Plug-In:

This plug-in is installed as part of the CN2 deployer. See "Install and Configure the CN2 Apstra Plug-In" on page 57 to install the plug-in.


d. CN2 IPAM Plug-In:

This plug-in allocates IP addresses for the pods. You install this plug-in on the SR-IOV nodes. See "Install the CN2 IPAM Plug-In" on page 61 to install the plug-in.

4. Onboard the IP Fabric in Apstra.

You onboard the fabric in Apstra from the Apstra Web GUI. For onboarding instructions, see the Juniper Apstra User Guide..

- Make sure that you assign the required resource pools such as ASNs and loopback IP addresses to the blueprint.
- Make sure that the hostnames of the generic systems (that is, servers) in your Apstra blueprint
 matches the hostnames of the corresponding CN2 nodes. You must also tag the SR-IOV link that
 connects the SRIOV-enabled NICs on the worker nodes to the fabric ports. You'll enter this same
 value in the sriov_link_tag in the CN2 Apstra plug-in CRD when you install the plug-in. The
 following diagram shows an example of a topology in an Apstra blueprint where the hostnames of
 the generic system were edited to match the corresponding hostnames of the CN2 worker nodes.
 The diagram also shows the SRIOV tags that were configured for the aforementioned SR-IOV
 links.



5. Verify Your Installation.

See "Verify Your Installation" on page 59 for instructions.

Install and Configure the CN2 Apstra Plug-In

IN THIS SECTION

Verify Your Installation | 59

This section describes how to install and configure the CN2 Apstra plug-in.

The CN2 Apstra plug-in is installed as part of the deployer. The CN2 Apstra plug-in extends the virtual network to the fabric, listens for CN2 Kubernetes events (such as NAD creation), and configures the fabric for the underlay through the Apstra SDK.

Depending on your installation, use the following files to install and configure the plug-in:

- For Kubernetes, use the single_cluster_deployer_example.yaml file.
- For OpenShift, copy all the files in the ocp/plugins directory to one level up in the directory structure.

To install and configure the CN2 Apstra plug-in:

- 1. Uncomment the apstra-plugin-secret and contrail-apstra-plugin in your single_cluster_deployer_example.yaml file.
- **2.** Enter your Apstra credentials (username and password) in the apstra-plugin-secret section in the corresponding deployer file. Make sure that your credentials are base64 encoded.

For example:

```
apiVersion: v1
data:
   password: YWRtaW4K
   username: YWRtaW4K
kind: Secret
metadata:
   name: apstra-plugin-secret
```

```
namespace: contrail
type: Opaque
```

3. Enter the parameters for blueprint name, server_ip, sriov_link tag in the contrail-apstra-plugin as shown in the following example. Make sure that the parameter for the sriov_link tag is the same parameter that you specified in the Apstra.

This example also shows the image URL from where it fetches the contrail-apstra-plugin image. You can edit the image URL, if needed. For example, you can change the value of the release_number in the image to 23.1.

```
apiVersion: plugins.juniper.net/v1alpha1
kind: ApstraPlugin
metadata:
name: contrail-apstra-plugin
namespace: contrail
spec:
blueprint: ""
common:
   containers:
      - image: enterprise-hub.juniper.net/contrail-container-prod/contrail-apstra-
plugin: release_number
      name: contrail-apstra-plugin
   server_ip: ""
```

For help in understanding what each field means, run the kubectl explain apstraplugin.spec command.

NOTE: The following example is only for informational purposes. You can run this command only after you deploy the CN2 Apstra plug-in.

kubectl explain apstraplugin.spec KIND: ApstraPlugin VERSION: plugins.juniper.net/v1alpha1

RESOURCE: spec <Object>

DESCRIPTION:

ApstraPluginSpec defines the desired state of ApstraPlugin

```
FIELDS:
  blueprint
                <string>
    The BluePrint in Apstra managing the Fabric which acts as underlay for this
     CN2 instance
             <Object>
  common
     Common configuration for k8s pods and containers
  log_level
                <string>
    The log level of Apstra plugin
  server_ip
                <string>
    The Apstra server IP address
  sriov_link_tag
                     <string>
     Contains the tag value(eg: SRIOV) for the SRIOV links in Apstra BluePrint
```

With the above steps, you have made the required changes in the deployer to install the CN2 Apstra plug-in. You can now proceed with the CN2 installation by following the instructions in the CN2 Installation Guide for Upstream Kubernetes or the CN2 Installation Guide for OpenShift Container Platforms.

NOTE: Even after you have completed the CN2 installation, you can still edit the CN2 Apstra plug-in parameters in the deployer YAML(s) as mentioned in the above steps and then reinstall CN2.

Verify Your Installation

Run the following kubect1 commands to verify that your installation is up and running. For example:

Check for the multus plug-in. kubectl get pods -A grep multus					
kube-system	kube-multus-ds-dn5j8	1/	/1 Running		
1	26d				
kube-system	kube-multus-ds-mnd4j	17	/1 Running		
1	26d				
kube-system	kube-multus-ds-xvt5v	1/	/1 Running		

2 26d------Check for the sriov-device-plugin. kubectl get pods -A | grep sriov-device-plugin kube-system kube-sriov-device-plugin-amd64-21792 1/1 Running 0 6d8h kube-system kube-sriov-device-plugin-amd64-n2lxv 1/1Running 1 6d8h kube-system kube-sriov-device-plugin-amd64-v8tqx 1/1 Running 26d 1 _ _ _ _ _ _ _ _ _ _ _ _ _ _ _ _ _ _ _ Check if the virtual functions were discovered. kubectl describe node jfm-qnc-05.lab.juniper.net | grep -A8 Allocatable Allocatable: 64 cpu: ephemeral-storage: 189217404206 hugepages-1Gi: 0 hugepages-2Mi: 0 intel.com/intel_sriov_netdevice: 7 263710404Ki memory: 110 pods: System Info: Check for the Apstra plug-in CRDs. kubectl api-resources | grep apstra apstraplugins plugins.juniper.net/v1alpha1 true ApstraPlugin _ _ _ _ _ _ _ _ _ _ _ Check for the Apstra secret. kubectl get secrets -A | grep apstra contrail apstra-plugin-secret 0paque 2 20d -----Check for the contrail-apstra-plugin pod. kubectl get pods -A | grep apstra

Install the CN2 IPAM Plug-In

Follow this procedure to install the CN2 IPAM plug-in for both Kubernetes and OpenShift deployments. This procedure assumes that CN2 is already installed on a Kubernetes cluster. In this procedure, we show a single-cluster deployment.

To install and configure the CN2 IPAM plug-in:

- 1. Run the kubectl get nodes command to view the list of available nodes.
- 2. Add the label sriov: "true" for each worker node with SR-IOV-enabled NICs. For example:

```
kubectl edit nodes <node name>
labels:
    beta.kubernetes.io/arch: amd64
    beta.kubernetes.io/os: linux
    kubernetes.io/arch: amd64
    kubernetes.io/hostname: jfm-qnc-02.englab.juniper.net
    kubernetes.io/os: linux
    server: jfm-qnc-02
    sriov: "true"
```

3. Add the sriovLabelSelector on the contrail-vrouters-nodes CRD.

kubectl edit Vrouters/contrail-vrouter-nodes -n contrail

In the CRD, under the spec field, add the following information:

```
sriovLabelSelector:
   matchLabels:
        sriov: "true"
```

4. Verify the plug-in installation.

Wait for the vRouter pod to restart on the master node. Verify that the cn2-ipamand sriov binaries are installed, as shown in the following example:

ls /opt/cni/bin/ archive bandwidth bridge cn2-ipam contrail-k8s-cni dhcp firewall host-device hostlocal ipvlan loopback macvlan multus portmap ptp sbr sriov static tuning vlan vrf

NOTE: The default location of the binary files depends on whether you use Kubernetes or OpenShift:

- For Kubernetes, the binaries reside in the /opt/cni/bin/ directory.
- For OpenShift, the binaries reside in the /var/lib/cni/bin/ directory.

Intra-VN and Inter-VN Approaches

IN THIS SECTION

- Intra-VN Approach | 62
- Inter-VN Approach | 65

This section shows the two approaches to configuring communication between SR-IOV pods, non-SR-IOV pods, and BMS: Intra-VN and Inter-VN.

You can use the Intra-VN approach or the Inter-VN approach depending on your requirement. If you want to see a summary of the configuration workflow for each approach, see Table 4 on page 68 or Table 5 on page 78.

Intra-VN Approach

In the Intra-VN approach, pods are attached to the same virtual network. By default, pods on the same virtual network can communicate with one another, regardless of whether:


The pods are spawned on the same worker nodes or on different worker nodes.

The worker nodes are connected to the same leaf device or to a different leaf.

Intra-VN Approach: Communication Between SR-IOV Pods

Figure 2 on page 63 shows an example of an Intra-VN topology where SR-IOV pods are attached to the same virtual network. This spine-and-leaf topology shows two SR-IOV worker nodes. Each node has a physical NIC with SR-IOV enabled. These physical NICs (ens801f2 and ens801f3) can be split into virtual functions and attached to the pods for direct I/O. When packets travel these virtual functions, the packets are tagged with the appropriate VLAN. In this approach, the packets do not pass through the vRouter but go directly to the IP fabric underlay provisioned by Apstra.

Figure 2: Intra-VN: Communication Between SR-IOV Pods



Intra-VN Approach: Communication Between SR-IOV Pods, Non-SR-IOV Pods, and BMS


Figure 3 on page 64 shows an example of SR-IOV pods, non-SR-IOV pods, and BMS attached to the same virtual network. The pods and BMS in this example use the same VNI and subnet.

Or

In this approach, an EVPN session is set up between the CN2 control node and the IP fabric to mutually exchange EVPN Type-2 routes used by the VXLAN protocol. The VTEP interface for the SR-IOV pods and BMS is on the fabric. The VTEP interface for the non-SR-IOV pods resides on the vRouter.

In the following figure, BMS is attached to the same virtual network as the SR-IOV and non-SR-IOV pods, but is not part of the CN2 cluster.

Figure 3: Intra-VN Communication Between SR-IOV Pods, Non-SR-IOV Pods, and BMS



NOTE: For information on configuring Intra-VN communication, see "Introduction to Configuring Intra-VN Communication" on page 66.


Inter-VN Approach

In the Inter-VN approach, CN2 pods and BMS workloads are attached to different virtual networks. The following sections shows the configuration required for configuring communication between pods and BMS.-

Inter-VN Approach: Communication Between SR-IOV Pods

The following figure shows an example of an Inter-VN topology between SR-IOV pods.

Figure 4: Inter-VN: Communication Between SR-IOV Pods



Inter-VN Approach: Communication Between SR-IOV Pods, Non-SR-IOV Pods, and BMS

In the Inter-VN approach, the pods and BMS belong to different virtual networks. To enable this communication, we are using EVPN Type-5 route exchanges between the CN2 control node and the fabric. For example:




Figure 5: Example: Inter-VN Communication Between SR-IOV Pods, Non-SR-IOV Pods, and BMS

NOTE: For information on configuring Inter-VN communication, see "Introduction to Configuring Inter-VN Communication" on page 77.

Introduction to Configuring Intra-VN Communication

 Table 2 on page 68 summarizes the procedures required to configure Intra-VN communication

 between:

- SR-IOV pods and other SR-IOV pods
- SR-IOV pods and non-SR-IOV pods
- SR-IOV pods, non-SR-IOV pods and BMS

Review "Prerequisites" on page 53 and "Intra-VN Approach" on page 62 before proceeding to the table.

	SR-IOV Pods	Non-SR-IOV Pods	Non-SR-IOV Pods and BMS
SR-IOV Pods	 Create an SR-IOV NAD (with the Asptra plug-in label) Create an SR-IOV pod and attach the pod to the SR-IOV NAD. For detailed information for each step, see "Configure Intra-VN Communication Between SR-IOV Pods" on page 70. 	 Pre-configuration setup (perform only once) 1. Change the encapsulation priority to vxlan in CN2. 2. Create a remote EVPN gateway in Apstra. 3. Configure a BGPRouter in CN2. Configuration steps 1. Create a common VirtualNetwork with the Apstra plug-in label. 2. Create an SR-IOV NAD and reference the common virtual network. 3. Create an SR-IOV pod and attach the pod to the SR-IOV NAD. 4. Create a non-SR-IOV NAD and reference the common VirtualNetwork . 5. Create a non-SR-IOV pod and attach the pod to the non-SR- IOV NAD. For detailed information for each step, see "Configure Intra-VN Communication Between 	 Complete the pre- configuration setup and follow the configuration steps in the previous column (SR-IOV pod to non- SR-IOV pods). In Apstra, assign the fabric port (connecting to the BMS) to the virtual network created in Apstra by CN2. For detailed information for each step, see "Configure Intra-VN Communication Between SR-IOV Pods, Non-SR- IOV Pods, and BMS" on page 77.

SR-IOV Pods	Non-SR-IOV Pods	Non-SR-IOV Pods and BMS
	SR-IOV Pods and Non- SR-IOV Pods" on page 71.	

Table 4: Summary of Intra-VN Configuration Workflows (Continued)

Configure Intra-VN Communication

IN THIS SECTION

- Before You Begin | 69
- Configure Intra-VN Communication Between SR-IOV Pods | 70
- Configure Intra-VN Communication Between SR-IOV Pods and Non-SR-IOV Pods | 71
- Configure Intra-VN Communication Between SR-IOV Pods, Non-SR-IOV Pods, and BMS | 77

Follow the procedures in this section to configure Intra-VN communication between SR-IOV pods, non-SR-IOV pods, and BMS.

Before You Begin

Read through this list of considerations before you begin your configuration:

• In the Intra-VN approach, you use the same subnet across the pods and BMS. When configuring IP addresses in BMS, it is important to use the unallocated IP addresses to avoid collision with the IPs allocated by CN2.

For example: If the subnet is 10.20.20.0/24, CN2 allocates IP addresses to the pod from the lower end, like 10.20.20.2, 10.20.20.3, and so on. For BMS, we suggest that you use IP addresses in the higher end, like 10.20.20.200, 10.20.20.201, 10.20.20.202 to avoid a collision.

Depending on whether you configure the IP on the physical interface or on the virtual interface, you must use use the appropriate connectivity template (untagged or tagged, respectively) in Apstra. The template is used to configure the ports that connect the BMS to the fabric. See the Juniper Apstra User Guide for more information.

To configure communication between SR-IOV pods and BMS or communication between non-SR-IOV pods and BMS, see "Configure Intra-VN Communication Between SR-IOV Pods, Non-SR-IOV Pods, and BMS" on page 77.

Configure Intra-VN Communication Between SR-IOV Pods

To configure Intra-VN communication between SR-IOV pods:

1. Create a NAD with the Apstra plug-in label, as shown in the following example:

```
apiVersion: "k8s.cni.cncf.io/v1"
kind: NetworkAttachmentDefinition
metadata:
  name: sriov-net20
  namespace: telco
  labels:
    juniper.net/plugin: apstra
  annotations:
    k8s.v1.cni.cncf.io/resourceName: intel.com/intel_sriov_netdevice
    juniper.net/networks: '{
      "vlanID": 20,
      "ipamV4Subnet": "10.20.20.0/24",
      "virtualNetworkNetworkId": 10020
    }'
spec:
  config: '{
  "type": "sriov",
  "cniVersion": "0.3.1",
  "name": "sriov-net20",
  "vlan": 20,
  "ipam": {
    "type": "cn2-ipam"
  }
}'
```

When you create this object, the CN2 Apstra plug-in listens to the NAD and extends the VirtualNetwork to the fabric through Apstra.

2. Issue the kubectl apply -f sriov_net20_nad.yaml command to create the NAD.

When the NAD is created, the CN2 Apstra plug-in listens for changes and provisions the fabric through the Apstra SDK.

3. Next, create an SR-IOV pod.

In the following example, we are referencing the NAD (sriov-net20) that we created in Step 1, in addition to the resource name (intel.com/intel_sriov_netdevice) for the virtual function.

```
apiVersion: v1
kind: Pod
metadata:
  name: sriov-pod-20-1
  namespace: telco
  annotations:
    k8s.v1.cni.cncf.io/networks: sriov-net20
spec:
  containers:
  - name: sriov-pod-20-1
    image: gcr.io/cos-cloud/toolbox
    imagePullPolicy: IfNotPresent
    command: [ "/bin/bash", "-c", "--" ]
    args: [ "while true; do sleep 300000; done;" ]
    securityContext:
      capabilities:
        add:
        - NET_ADMIN
      privileged: true
    resources:
      requests:
        intel.com/intel_sriov_netdevice: '1'
      limits:
        intel.com/intel_sriov_netdevice: '1'
  nodeSelector:
    server: jfm-qnc-esxi-2
```

When you create the pod, the CN2 Apstra plug-in listens to the pod-creation event and provisions the fabric to assign the relevant fabric ports to the VirtualNetwork.

You have now configured Intra-VN communication between SR-IOV pods.

Configure Intra-VN Communication Between SR-IOV Pods and Non-SR-IOV Pods

Configuring Intra-VN communication between SR-IOV pods and non-SR-IOV pods involves two sets of steps: pre-configuration setup and configuration. You perform the pre-configuration setup only once, no matter how many virtual networks and pods you configure.

To complete the pre-configuration setup:

- **1.** Change the encapsulation priority to vxlan in CN2 using the kubectl edit GlobalVrouterConfig defaultglobal-vrouter-config command.
- **2.** Create a remote EVPN gateway in Apstra. See the "Remote EVPN Gateways (virtual)" chapter in the Juniper Apstra User Guide for instructions.
- **3.** In CN2, configure a BGPRouter.

In the following example, we are referencing the fabric's loopback IP address: (10.1.1.3), ASN number (65003), and family (- e-vpn) used to exchange EVPN Type-2 routes.

```
apiVersion: core.contrail.juniper.net/v3
kind: BGPRouter
metadata:
  namespace: contrail
  name: bgprouter-qfx
  annotations:
    core.juniper.net/display-name: Sample BGP Router
    core.juniper.net/description:
      Represents configuration of BGP peers. All the BGP peers involved in
      Contrail system are under default Routing Instance of the default
      Virtual Network.
spec:
  parent:
    apiVersion: core.contrail.juniper.net/v3
    kind: RoutingInstance
    namespace: contrail
    name: default
  bgpRouterParameters:
    vendor: Juniper
    routerType: router
    address: 10.1.1.3
    identifier: 10.1.1.3
    autonomousSystem: 65003
    addressFamilies:
      family:
        - e-vpn
  bgpRouterReferences:
    - apiVersion: core.contrail.juniper.net/v3
      kind: BGPRouter
      namespace: contrail
      name: jfm-qnc-06.englab.juniper.net
```

To configure Intra-VN communication between SR-IOV pods and non-SR-IOV pods:

1. Create a common VirtualNetwork (with Apstra plug-in label) to extend the virtual network to the fabric. In the following example, we are creating a Subnet and a VirtualNetwork that references that subnet.

```
apiVersion: core.contrail.juniper.net/v3
kind: Subnet
metadata:
  namespace: telco
  name: net20-v4
spec:
  cidr: 10.20.20.0/24
---
apiVersion: "core.contrail.juniper.net/v3"
kind: VirtualNetwork
metadata:
    name: net20
    namespace: telco
    labels:
     juniper.net/plugin: apstra
spec:
    vlanID: 20
    virtualNetworkNetworkId: 10020
    routeTargetList:
    - target:10020:1
    v4SubnetReference:
        apiVersion: core.contrail.juniper.net/v3
        kind: Subnet
        name: net20-v4
        namespace: telco
```

2. Create a NAD for the SR-IOV pod (with Apstra plug-in label).

In the following example, we are referencing the VirtualNetwork (net20) that we created in Step 1.

```
apiVersion: "k8s.cni.cncf.io/v1"
kind: NetworkAttachmentDefinition
metadata:
   name: sriov-net20
   namespace: telco
   labels:
```

```
vn: web
    juniper.net/plugin: apstra
  annotations:
    k8s.v1.cni.cncf.io/resourceName: intel.com/intel_sriov_netdevice
    juniper.net/networks: '{
      "vlanID": 20,
      "virtualNetworkNetworkId": 10020,
      "virtualNetworkReference": {
         "apiVersion": "core.contrail.juniper.net/v3",
         "kind": "VirtualNetwork",
         "name": "net20",
         "namespace": "telco"
     },
      "routeTargetList": ["target:10020:1"]
    }'
spec:
  config: '{
  "type": "sriov",
  "cniVersion": "0.3.1",
  "name": "net20",
  "vlan": 20,
  "ipam": {
    "type": "cn2-ipam"
  }
}'
```

3. Create an SR-IOV pod.

In the following example, we are referencing the NAD (sriov-net20) that we created in Step 2.

```
apiVersion: v1
kind: Pod
metadata:
   name: sriov-pod-20-1
   namespace: telco
   annotations:
        k8s.v1.cni.cncf.io/networks: sriov-net20
spec:
   containers:
        name: sriov-pod-20
        image: gcr.io/cos-cloud/toolbox
        imagePullPolicy: IfNotPresent
```

```
command: [ "/bin/bash", "-c", "--" ]
args: [ "while true; do sleep 300000; done;" ]
securityContext:
   capabilities:
    add:
        - NET_ADMIN
   privileged: true
   resources:
      requests:
        intel.com/intel_sriov_netdevice: '1'
   limits:
        intel.com/intel_sriov_netdevice: '1'
nodeSelector:
   server: jfm-qnc-05
```

When you create the pod, the CN2 Apstra plug-in listens to the pod-creation event and provisions the fabric to assign the relevant fabric ports to the VirtualNetwork.

4. Create a NAD for the non-SR-IOV pod.

In the following example, we are referencing the same virtual network (net20) that we created Step 1.

```
apiVersion: "k8s.cni.cncf.io/v1"
kind: NetworkAttachmentDefinition
metadata:
 name: non-sriov-net20
 namespace: telco
 labels:
    vn: web
  annotations:
    juniper.net/networks: '{
      "virtualNetworkNetworkId": 10020,
      "virtualNetworkReference": {
         "apiVersion": "core.contrail.juniper.net/v3",
         "kind": "VirtualNetwork",
         "name": "net20",
         "namespace": "telco"
     },
      "routeTargetList": ["target:10020:1"]
   }'
spec:
  config: '{
  "type": "contrail-k8s-cni",
  "cniVersion": "0.3.1",
```

```
"name": "net20"
}'
```

5. Create a non-SR-IOV pod.

In the following example, were are referencing the NAD (non-sriov-net20) we created in Step 4.

```
apiVersion: v1
kind: Pod
metadata:
  name: non-sriov-pod-20-1
  namespace: telco
  annotations:
    k8s.v1.cni.cncf.io/networks: non-sriov-net20
spec:
  containers:
  - name: non-sriov-pod-20-1
    image: gcr.io/cos-cloud/toolbox
    imagePullPolicy: IfNotPresent
    command: [ "/bin/bash", "-c", "--" ]
    args: [ "while true; do sleep 300000; done;" ]
    securityContext:
      capabilities:
        add:
        - NET_ADMIN
      privileged: true
  nodeSelector:
    server: jfm-qnc-06
```

NOTE: If you are configuring communication between the pods and BMS, proceed with Step 2 in "Configure Intra-VN Communication Between SR-IOV Pods, Non-SR-IOV Pods, and BMS" on page 77 to complete the configuration.

You have now configured Intra-VN communication between SR-IOV pods and non-SR-IOV pods.

Configure Intra-VN Communication Between SR-IOV Pods, Non-SR-IOV Pods, and BMS

NOTE: This procedure describes how to configure Intra-VN communication between SR-IOV pods, non-SR-IOV pods, and BMS.

- For communication between SR-IOV pods and BMS, follow these steps but do not create a non-SR-IOV NAD and non-SR-IOV pod.
- For communication between non-SR-IOV pods and BMS, follow these steps but do not create an SR-IOV NAD and SR-IOV pod.

To configure Intra-VN communication between SR-IOV pods, non-SR-IOV pods, and BMS:

- **1.** Complete the pre-configuration setup and configuration steps in the the procedure "Configure Intra-VN Communication Between SR-IOV Pods and Non-SR-IOV Pods" on page 71.
- 2. In Apstra, identify the VirtualNetwork that was created by CN2 based on the VNI.
- 3. Assign the relevant fabric ports (that connect to the BMS) in Apstra to this virtual network.

Make sure that you use the appropriate connectivity template (untagged or tagged) to assign the ports to the virtual network. See the Juniper Apstra User Guide for instructions.

You have now configured Intra-VN communication between SR-IOV pods, non-SR-IOV pods, and BMS.

Introduction to Configuring Inter-VN Communication

Table 3 on page 78 summarizes the procedures required to configure Inter-VN communication between:

- SR-IOV pods and other SR-IOV pods
- SR-IOV pods and non-SR-IOV pods
- SR-IOV pods, non-SR-IOV pods, and BMS

Review the "Prerequisites" on page 53 and "Inter-VN Approach" on page 65 before proceeding to the table.

Table 5: Summary of Inter-VN Co	Configuration Workflows
---------------------------------	-------------------------

SR-IOV Pods	Non-SR-IOV Pods	Non-SR-IOV Pods and BMS
 Create an SR-IOV NAD (with Asptra plug-in label and vnr label). Create an SR-IOV pod and attach the pod to the NAD. Create a VNR. Configure the required routes in the pods. For detailed information for each step, see "Configure Inter-VN Communication Between SR-IOV Pods" on page 80. 	 Pre-configuration setup (perform only once) 1. Change the encapsulation priority to vxlan in CN2. 2. Create a remote EVPN gateway in Apstra. 3. Create a BGPRouter in CN2. Configuration steps 1. Create an SR-IOV NAD (with Apstra plug-in label and vnr label). 2. Create an SR-IOV pod and attach the pod to the SR-IOV NAD. 3. Create a non-SR-IOV NAD (with vnr label). 4. Create a non-SR-IOV pod and attach the pod to the non-SR- IOV NAD. 5. Create a VNR and specify the routing type as routingType:evpn. 6. Configure the required routes in the pods. For detailed information for each step, see "Configure Inter-VN 	 Complete the pre- configuration setup and follow the configuration steps (1 through 5) in the previous column (SR- IOV pod to non-SR- IOV pods). Manually create a virtual network for the BMS in Apstra. In CN2, create a reference NAD (with vnr label) to the virtual network that was created in Step 2 above. Configure the required routes in the BMS and also in the CN2 pods. For detailed information for each step, see "Configure Inter-VN Communication Between SR-IOV Pods, Non-SRIOV Pods and BMS" on page 87.

SR-IOV Pods	Non-SR-IOV Pods	Non-SR-IOV Pods and BMS
	Communication Between SR-IOV Pods and Non- SR-IOV Pods" on page 82.	

Table 5: Summary of Inter-VN Configuration Workflows (Continued)

Configure Inter-VN Communication

IN THIS SECTION

Before You Begin | 79

Follow the procedures in this section to configure Inter-VN communication between SR-IOV pods, non-SR-IOV pods, and BMS.

Before You Begin

Read through the this list of considerations before you begin your configuration:

- For Inter-VN routing, you must create a VirtualNetworkRouter in CN2.
- In the Inter-VN approach, you must manually configure the routes on the pods. For example: you can use the command ip route add 10.30.30.0/8 via 10.20.20.1 to reach the 10.30.30.0/8 subnet.
- The QFX5200 switch does not support EVPN Type-5 routing and edge-routing bridging (ERB). See Edge-Routing Bridging for QFX Series Switches for more information.

For a list of supported Juniper devices for use in an Inter-VN topology, see Layer 3 connectivity in an EVPN-VXLAN topology. Also, make sure that the QFX devices are running Junos OS version 20.2R2.11 or above.

Configure Inter-VN Communication Between SR-IOV Pods

To configure Inter-VN communication between SR-IOV pods:

1. Create an SR-IOV NAD (with vn label and Apstra plug-in label), as shown in the following example:

```
apiVersion: "k8s.cni.cncf.io/v1"
kind: NetworkAttachmentDefinition
metadata:
  name: net30
 namespace: telco
 labels:
    vn: web
    juniper.net/plugin: apstra
  annotations:
    k8s.v1.cni.cncf.io/resourceName: intel.com/intel_sriov_netdevice
    juniper.net/networks: '{
      "vlanID": 30,
      "ipamV4Subnet": "10.30.30.0/24",
      "virtualNetworkNetworkId": 10030
   }'
spec:
 config: '{
  "type": "sriov",
  "cniVersion": "0.3.1",
  "name": "net30",
  "vlan": 30,
  "ipam": {
    "type": "cn2-ipam"
 }
}'
```

2. Issue the kubectl apply -f sriov_net30_nad.yaml command to create the NAD.

The CN2 Apstra plug-in listens to the NAD event and extends the virtual network to the fabric through Apstra. You can create additional NADs as needed, following the same pattern.

3. Create an SR-IOV pod and attach the pod to the SR-IOV NAD.

In the following example, we are referencing the NAD (sriov-net30) that we created in Step 1 in addition to the resource name (intel.com/intel_sriov_netdevice) for the virtual function.

```
apiVersion: v1
kind: Pod
metadata:
  name: sriov-pod-30-1
  namespace: telco
  annotations:
    k8s.v1.cni.cncf.io/networks: net30
spec:
  containers:
  - name: sriov-pod-30-1
    image: gcr.io/cos-cloud/toolbox
    imagePullPolicy: IfNotPresent
    command: [ "/bin/bash", "-c", "--" ]
    args: [ "while true; do sleep 300000; done;" ]
    securityContext:
      capabilities:
        add:
        - NET_ADMIN
      privileged: true
    resources:
      requests:
        intel.com/intel_sriov_netdevice: '1'
      limits:
        intel.com/intel_sriov_netdevice: '1'
  nodeSelector:
    server: jfm-qnc-05
```

4. Run the kubectl apply -f pod.yaml command to create the pod.

The CN2 Apstra plug-in listens to the pod-creation event and provisions the fabric to assign the relevant fabric ports to the virtual network.

5. Create a VNR to route the different virtual networks with a common label.

In the following example, the common label is: vn: web.

```
apiVersion: core.contrail.juniper.net/v3
kind: VirtualNetworkRouter
metadata:
    namespace: telco
```

```
name: vnr-web
annotations:
    core.juniper.net/display-name: vnr-web
labels:
    vnr: web
    ns: telco
spec:
    type: mesh
    routingType: evpn
l3vxlanNetworkIdentifier: 50000
virtualNetworkSelector:
    matchLabels:
    vn: web
```

6. Configure the required routes in the pods to reach the other subnet. For example:

ip route add 10.30.30.0/24 via 10.20.20.1

You have now configured Inter-VN communication between SR-IOV pods.

Configure Inter-VN Communication Between SR-IOV Pods and Non-SR-IOV Pods

Configuring Inter-VN communication between SR-IOV pods and non-SR-IOV pods involves two sets of steps: pre-configuration setup and configuration. You perform the pre-configuration setup only once, no matter how many virtual networks and pods you configure.

To complete the pre-configuration setup:

- **1.** Change the encapsulation priority to vxlan in CN2 using the kubectl edit GlobalVrouterConfig defaultglobal-vrouter-config command.
- **2.** Create a remote EVPN gateway in Apstra. See the "Remote EVPN Gateways (virtual)" chapter in the Juniper Apstra User Guide for instructions.
- **3.** In CN2, configure a BGPRouter.

In the following example, we are referencing the fabric's loopback IP address: (10.1.1.3), ASN number (65003), and family (- e-vpn) used to exchange EVPN Type-2 routes.

apiVersion: core.contrail.juniper.net/v3
kind: BGPRouter

```
metadata:
  namespace: contrail
  name: bgprouter-qfx
  annotations:
    core.juniper.net/display-name: Sample BGP Router
    core.juniper.net/description:
      Represents configuration of BGP peers. All the BGP peers involved in
      Contrail system are under default Routing Instance of the default
      Virtual Network.
spec:
  parent:
    apiVersion: core.contrail.juniper.net/v3
    kind: RoutingInstance
    namespace: contrail
    name: default
  bgpRouterParameters:
    vendor: Juniper
    routerType: router
    address: 10.1.1.3
    identifier: 10.1.1.3
    autonomousSystem: 65003
    addressFamilies:
      family:
        - e-vpn
  bgpRouterReferences:
    - apiVersion: core.contrail.juniper.net/v3
      kind: BGPRouter
      namespace: contrail
      name: jfm-qnc-06.englab.juniper.net
```

To configure Inter-VN communication between SR-IOV pods and non-SR-IOV pods:

1. Create an SR-IOV NAD (with vn label and Apstra plug-in label), as shown in the following example:

```
apiVersion: "k8s.cni.cncf.io/v1"
kind: NetworkAttachmentDefinition
metadata:
   name: net30
   namespace: telco
   labels:
    vn: web
    juniper.net/plugin: apstra
```

```
annotations:
   k8s.v1.cni.cncf.io/resourceName: intel.com/intel_sriov_netdevice
   juniper.net/networks: '{
      "vlanID": 30,
      "ipamV4Subnet": "10.30.30.0/24",
      "virtualNetworkNetworkId": 10030
   }'
spec:
 config: '{
 "type": "sriov",
 "cniVersion": "0.3.1",
 "name": "net30",
  "vlan": 30,
  "ipam": {
    "type": "cn2-ipam"
 }
```

```
}'
```

2. Create an SR-IOV pod and attach the pod to the SR-IOV NAD.

In this example we are referencing the NAD (net30) that we created in Step 1 and the resource name for the SR-IOV pod (intel.com/intel_sriov_netdevice) for the virtual function.

```
apiVersion: v1
kind: Pod
metadata:
  name: sriov-pod-30-1
  namespace: telco
  annotations:
    k8s.v1.cni.cncf.io/networks: net30
spec:
  containers:
  - name: sriov-pod-30-1
                                      imagePullPolicy: IfNotPresent
    image: gcr.io/cos-cloud/toolbox
    command: [ "/bin/bash", "-c", "--" ]
    args: [ "while true; do sleep 300000; done;" ]
    securityContext:
      capabilities:
        add:
        - NET_ADMIN
      privileged: true
```

```
resources:
    requests:
    intel.com/intel_sriov_netdevice: '1'
    limits:
        intel.com/intel_sriov_netdevice: '1'
nodeSelector:
    server: jfm-qnc-05
```

When you create the pod, the CN2 apstra plug-in listens to the pod-creation event and provisions the fabric to assign the relevant fabric ports to the VirtualNetwork.

3. Create a non-SR-IOV NAD (with vn label), as shown in the following example:

```
apiVersion: "k8s.cni.cncf.io/v1"
kind: NetworkAttachmentDefinition
metadata:
  name: non-sriov-net20
  namespace: telco
  labels:
    vn: web
    juniper.net/plugin: apstra
  annotations:
    juniper.net/networks: '{
      "virtualNetworkNetworkId": 10020,
      "ipamV4Subnet": "10.20.20.0/24",
      "routeTargetList": ["target:10020:1"]
    }'
spec:
  config: '{
  "type": "contrail-k8s-cni",
  "cniVersion": "0.3.1",
  "name": "net20"
}'
```

4. Create a non-SR-IOV pod and attach the pod to the non-SR-IOV NAD.

Note that we are referencing the NAD (net20) that we created in Step 3.

```
apiVersion: v1
kind: Pod
metadata:
  name: non-sriov-pod-20-1
  namespace: telco
```

```
annotations:
    k8s.v1.cni.cncf.io/networks: net20
spec:
 containers:
 - name: non-sriov-pod-20-1
   image: gcr.io/cos-cloud/toolbox
    imagePullPolicy: IfNotPresent
    command: [ "/bin/bash", "-c", "--" ]
   args: [ "while true; do sleep 300000; done;" ]
   securityContext:
      capabilities:
        add:
        - NET_ADMIN
      privileged: true
  nodeSelector:
    server: jfm-qnc-06
```

5. Create a VNR to route the different virtual networks with a common label. In the following example, the common label is: vn: web.

```
apiVersion: core.contrail.juniper.net/v3
kind: VirtualNetworkRouter
metadata:
  namespace: telco
  name: vnr-web
  annotations:
    core.juniper.net/display-name: vnr-web
  labels:
    vnr: web
    ns: telco
spec:
  type: mesh
  routingType: evpn
  13vxlanNetworkIdentifier: 50000
  virtualNetworkSelector:
    matchLabels:
      vn: web
```

NOTE: If you are configuring communication between the pods and BMS, can now proceed to Step 2 in "Configure Inter-VN Communication Between SR-IOV Pods, Non-SRIOV Pods and BMS" on page 87 to complete the configuration.

6. Configure the required routes in the pods. For example:

ip route add 10.30.30.0/24 via 10.20.20.1

You have now configured Inter-VN communication between SR-IOV pods and non-SR-IOV pods.

Configure Inter-VN Communication Between SR-IOV Pods, Non-SRIOV Pods and BMS

To configure Inter-VN communication between SR-IOV pods, non-SR-IOV pods, and BMS:

- Complete the pre-configuration setup and follow Steps 1 though 5 in the procedure "Configure Inter-VN Communication Between SR-IOV Pods and Non-SR-IOV Pods" on page 82.
- **2.** Manually create a virtual network for the BMS in Apstra. See the Juniper Apstra User Guide for instructions.

NOTE: Although the required VirtualNetwork can be created in Apstra using CN2, we are also addressing the use case where the VirtualNetwork needed for BMS has already been created in Apstra.

3. In CN2, create a reference NAD (with vn label) with the same name as the BMS virtual network in Apstra. Also, add the label juniper.net/ssor: apstra to sync this NAD from Apstra into CN2. For example:

```
apiVersion: "k8s.cni.cncf.io/v1"
kind: NetworkAttachmentDefinition
metadata:
  name: bms-net40-vn
  namespace: telco
  labels:
    vn: web
    juniper.net/plugin: apstra
    juniper.net/ssor: apstra
```

```
annotations:
   juniper.net/networks: '{
   }'
```

4. Configure the required routes in the BMS and also in the CN2 pods. For example:

```
ip route add 10.30.30.0/24 via 10.40.40.1
```

You have now configured Inter-VN communication between SR-IOV pods, non-SR-IOV pods, and BMS.



CN2 Security

Kubernetes Network Policies | 90

Namespace Security Policies | 96

Encrypt Secret Data at Rest | 101

Configure Management and Control Plane Authentication with TLS Encryption | 101

Routing Policies | 106

Global Security Policy | 116

Enable Namespace Isolation by Default | 120

Kubernetes Network Policies

SUMMARY

Juniper Cloud-Native Contrail[®] Networking[™] (CN2) lets you deploy Kubernetes network policies within the Contrail firewall security policy framework. You must use a Container Network Interface (CNI) that supports NetworkPolicy, like Contrail, to deploy a network policy. This topic provides information about how to deploy a Kubernetes network policy in environments running CN2.

IN THIS SECTION

- Kubernetes Network Policy Overview | 90
- Deploy a Kubernetes Network Policy in Cloud-Native Contrail Networking | **92**
- Kubernetes Network Policy matchExpressions

Kubernetes Network Policy Overview

Kubernetes network policies let you specify how pods communicate with other pods and network endpoints. A Kubernetes NetworkPolicy resource enables a pod to communicate with:

- Other pods in the allowlist (a pod cannot block access to itself).
- Namespaces in the allowlist.
- IP blocks, or Classless Inter-Domain Routing (CIDR).

Kubernetes network policies apply only to pods within a namespace and define ingress (source) and egress (destination) rules. Kubernetes network policies have the following characteristics when applied to a pod:

- Pod specific and apply to a single pod or a group of pods. Network policy rules dictate the traffic to that pod.
- Define traffic rules for a pod for ingress traffic, egress traffic, or both. If you don't specify a direction explicitly, the policy applies to the ingress direction by default.
- Must contain explicit rules that specify traffic from the allowlist in the ingress and egress directions. Traffic that does not match the allowlist rules is denied.
- Permitted traffic includes traffic matching any of the network policies applied to a pod.

Kubernetes network policies have the following additional characteristics:

• When not applied to a pod, that pod accepts traffic from all sources.

• Act on connections rather than individual packets. For example, if traffic from pod A to pod B is allowed by the configured policy, then the packets from pod B to pod A are also allowed, even if the policy in place does not allow pod B to initiate a connection to pod A.

A Kubernetes network policy comprises the following sections:

- spec: Describes the desired state of a Kubernetes object. For a network policy, the podSelector and policyTypes fields within the spec specify the rules for that policy.
- podSelector: Selects the groups of pods to which the policy applies. An empty podSelector selects all pods in the namespace.
- policyTypes: Specifies whether the policy applies to ingress traffic from selected pods or egress traffic to selected pods. If no policyTypes are specified, the ingress direction is selected by default.
- ingress: Allows ingress traffic that matches the from and ports sections. In the following example, the ingress rule allows connections to all pods in the dev namespace with the label app: webserver-dev on TCP port 80 from:
 - Any pod in the default namespace with the label app: client1-dev.
 - All IP addresses within the 10.169.25.20/32 range.
 - Any pod in the default namespace with the label project: jtac.
- egress: Allows egress traffic that matches the to and portssections. In Example 1, the egress rule allows connections from any pod in the default namespace with the label app: dbserver-dev to port TCP 80.
- ipBlock: Selects IP CIDR ranges to allow as ingress sources or egress destinations. The ipBlock section of a network policy contains the following two fields:
 - cidr (ipBlock.cidr): The network policy allows egress traffic to, or ingress traffic from, the specified IP range.
 - except (ipBlock.except): Kubernetes expects traffic in the specified IP range not to match the policy. The network policy denies ingress traffic to, or egress traffic from, the IP range specified in except.

The following NetworkPolicy resource example shows ingress and egress rules:

```
apiVersion: networking.k8s.io/v1
kind: NetworkPolicy
metadata:
   name: policy1
   namespace: dev
spec:
```

```
podSelector:
  matchLabels:
    app: webserver-dev
policyTypes:
- Ingress
- Egress
ingress:
- from:
  - ipBlock:
      cidr: 10.169.25.20/32
  - namespaceSelector:
      matchLabels:
        project: jtac
  - podSelector:
      matchLabels:
        app: client1-dev
  ports:
  - protocol: TCP
    port: 80
egress:
- to:
  - podSelector:
      matchLabels:
        app: dbserver-dev
  ports:
  - protocol: TCP
```

In this example, ingress TCP traffic from IPs within CIDR 10.169.25.20/32 from port: 80 is allowed. Egress traffic to pods with matchLabels app: dbserver-dev to TCP port: 80 is allowed.

Deploy a Kubernetes Network Policy in Cloud-Native Contrail Networking

In CN2, after you configure and deploy a Kubernetes network policy, that policy is created automatically in Contrail. Here's an example of a Kubernetes network policy:

```
apiVersion: networking.k8s.io/v1
kind: NetworkPolicy
```

port: 80

```
metadata:
 name: test-network-policy
 namespace: default
spec:
 podSelector:
   matchLabels:
      role: db
 policyTypes:
  - Ingress
 - Egress
 ingress:
  - from:
    - ipBlock:
       cidr: 172.17.0.0/16
       except:
        - 172.17.1.0/24
    - namespaceSelector:
       matchLabels:
          project: myproject
    - podSelector:
       matchLabels:
          role: frontend
   ports:
    - protocol: TCP
      port: 6379
 egress:
  - to:
    - ipBlock:
       cidr: 10.0.0.0/24
   ports:
```

```
- protocol: TCP
port: 5978
```

This policy results in the following objects being created in CN2:

Tags on page 94 Address Groups on page 94 Firewall Rules on page 94

Firewall Policy on page 95

Table 6: Tags

Кеу	Value
role	db
namespace	default
project	myproject
role	frontend

Table 7: Address Groups

Name	Prefix
test-network-policy-except	172.17.1.0/24
test-network-policy	172.17.0.0/16
test-network-policy-egress	10.0.0/24

Table 8: Firewall Rules

Rule Name	Action	Service	Endpoint1	Direction	Endpoint2
default-ingress- test-network- policy-0- ipBlock-0-17x.x x.1.0/24-0	deny	tcp:6379	role=db && namespace=def ault	ingress	Address Group: 172.17.1.0/24
default-ingress- test-network- policy-0- ipBlock-0- cidr-17x.xx.0.0/ 16-0	pass	tcp:6379	role=db && namespace=def ault	ingress	Address Group: 172.17.0.0/16

Table 8: Firewall Rules (Continued)

Rule Name	Action	Service	Endpoint1	Direction	Endpoint2
default-ingress- test-network- policy-0- namespaceSelec tor-1-0	pass	tcp:6379	role=db && namespace=def ault	ingress	project=myproje ct
default-ingress- test-network- policy-0- podSelector-2-0	pass	tcp:6379	role=db && namespace=def ault	ingress	namespace=def ault && role=frontend
default-egress- test-network- policy- ipBlock-0- cidr-10.0.0.0/24 -0	pass	tcp:5978	role=db && namespace=def ault	egress	Address Group: 10.0.0.0/24

Table 9: Firewall Policy

Name	Rules
default-test-network-policy	default-ingress-test-network-policy-0- ipBlock-0-172.17.1.0/24-0, default-ingress-test- network-policy-0-ipBlock-0-cidr-172.17.0.0/16-0 default-ingress-test-network-policy-0- namespaceSelector-1-0 default-ingress-test-network-policy-0- podSelector-2-0, default-egress-test-network-policy- ipBlock-0-cidr-10.0.0.0/24-0

Kubernetes Network Policy matchExpressions

Starting in Cloud-Native Contrail Networking (CN2) version 22.3, CN2 supports Kubernetes Network Policy with matchExpressions. For more information about matchExpressions, see "Resources that support setbased requirements" in the Kubernetes documentation.

Namespace Security Policies

SUMMARY

Starting in CN2 Release 23.1, CN2 supports Namespace Security Polices. Namespace policies allows you to define security polices from endpoints within a namespace, or to an external IP address.

Overview

IN THIS SECTION

- Policy Priority: Namespace Security Polices and Kubernetes Network Policies | 98
- Example of a Namespace Security Policy | 99

Although Kubernetes network policies are useful in restricting the communication between pods in a namespace, you can only control ingress and egress traffic from a selected set of pods. As an administrator, these policies can be complex to use, specifically if you are interested in end-to-end traffic flow based on application or security requirements.

For end-to-end traffic flow, CN2 supports namespace security policies. Namespace security policies are administrative-centric policies. These policies allows you to define polices from a source endpoint to a destination endpoint within a namespace. With Namespace security policies, you can allow or deny traffic between pods in a namespace or to an external IP address.

Namespace security policies have the following characteristics:

IN THIS SECTION

Overview | 96

- You can only define security polices within a namespace. By default, security policies can only manage traffic within its own namespace.
- When you define a security policy, the policy is applied on all pods in a namespace.
- By default, if a pod does not match any user-defined policies, traffic is denied.
- You define security policies within a namespace using rules. Each rule has a source endpoint and destination endpoint. For ease of use, the security polices use the same endpoints as Kubernetes network policies (namespace, podselector, IPblock).
- Namespace security polices can contain one or multiple rules. For example:

```
Rule:
    Allow
    Src:
        (174.16.10.0/16 except 174.16.10.40/28)
        (174.16.10.40/24 except 174.16.10.70/32})
    Dst:
        (175.16.10.0/24 except 175.16.10.40/32)
        (175.16.10.0/24 except 175.16.10.70/32))
    port:[9000:9010])
```

- Namespace security policies support two actions: pass and deny. The default action is deny. Actions are per-policy, not per rule. This means that any rules you define follows the same action.
- For each rule, you can define the destination ports or destination port range (combination of source, destination, and port). For example, let's say you want particular IP address or source to access the server on a specified destination port or range of ports.

A Namespace security policy consists of the following sections. See: "Example of a Namespace Security Policy" on page 99.

• Spec

The spec field contains the rules and actions you need to define a security policy. The rules contain a list of user defined source and destination matches.

The rules are categorized, as follows:

- SrcEP: List of source endpoints for a rule match criteria (podSelector or ipBlock).
- DstEP: List of destination endpoints for a rule match criteria (podSelector or ipBlock).

- **Ports**: List of destination ports to be matched for this rule (contains a combination of ports and protocol).
- Action: Action to be taken if any policy rule matches (pass or deny). The default action is deny.
- .

Policy Priority: Namespace Security Polices and Kubernetes Network Policies

Because CN2 uses both Kubernetes network polices and namespace security policies, we use a sequence to determine how rules are processed between the two different policies.


Figure 1 on page 99 shows how Kubernetes network policies along with namespace security policies are prioritized. The rules for namespace security polices are prioritized first, followed by Kubernetes network policies.

NOTE: All Namespace security policies are user-defined.

Each policy is prioritized, as follows:

- 1. Namespace Security Policies (Deny): By default, if a pod does not match any policies in CN2, traffic is denied. The **deny** policies are given a higher priority over the **allow** policies.
- **2.** Namespace Security Policies (Allow): If you do not define a policy in CN2, traffic is allowed between all pods in the corresponding namespace.
- 3. Kubernetes Network Polices: By default, a Kubernetes network policy allows traffic from all sources.
- 4. Default (Deny): If a pod does not match any Kubernetes network policies, traffic is denied.

Figure 6: Policy Priority: Namespace Security Polices and Kubernetes Network Policies



Example of a Namespace Security Policy

Here is an example of a namespace security policy:

```
NOTE: When you create a namespace security policy, you only need to provide the namespace
and the source and destination endpoints (namespace, podSelector, ipBlock).
apiVersion: core.contrail.juniper.net/v3
            kind: NamespaceSecurityPolicy
            metadata:
              name: allow-hr11-to-fac12
              namespace: ns-svl
            spec:
              rules:
               - srcEP:
                   endPoints:
                     - podSelector:
                         matchLabels:
                           dept: hr
                         matchExpressions:
                           - {key: tier, operator: In, values: [one]}
                     - ipBlock:
```

```
cidr: 174.19.12.11/32
dstEP:
    endPoints:
        - podSelector:
            matchLabels:
                dept: fac
                ipBlock:
                cidr: 174.19.12.12/32
ports:
                - protocol: TCP
                port: 3300
                endPort: 3400
action: pass
```

In this example, we defined a security policy in namespace: ns-svl. In this policy, we've created a combination of rules for the source and destination endpoints. Table 1 on page 100 describes the different combinations.

For example, any traffic generated from the source (podSelector or iBlock) to the destination (podSelector or ipBlock) is allowed. The remaining traffic in the namespace is denied.

We've also specified the destination ports 3300 and 3400. This allows TCP traffic between the destination ports and between the source and destination endpoints.

Table 10: Example: Source and Destination Combinations

Source	Destination
Pod with label dept:hr to:	 Pod with label dept: fac or destination (dstEP). Or, ipBlock cidr: 174.19.12.12/32.
ipBlock174.19.12.11/32 to:	 Pod with label dept:fac or destination (dstEP). Or, ipBlock: cidr:174.19.12.12/32.

Kubernetes Network Policies

Encrypt Secret Data at Rest

Starting in CN2 Release 22.1, Juniper supports encryption of secret data at rest. CN2 automatically encrypts secret data at rest in your Kubernetes cluster and encrypts any password that you configure. A secret is an object that contains a small amount of sensitive data such as a password, a token, or a key. Data at rest encryption is a cybersecurity practice of encrypting stored data to prevent unauthorized access.

Refer to the Kubernetes documentation titled Encrypting Secret Data at Rest for instructions on how to enable and configure this feature.

Configure Management and Control Plane Authentication with TLS Encryption

SUMMARY

This topic describes how to configure management and control plane authentication with TLS Encryption in CN2 Release 22.4 or later in a Kubernetes-orchestrated environment.

IN THIS SECTION

Overview | 101

Configure TLS Encryption for Contrail Control
 Plane and vRouter | **102**

Overview

IN THIS SECTION

Considerations | 102

CN2 supports management and control plane authentication with TLS encryption. The TLS protocol is used for certificate exchange, mutual authentication, and negotiating ciphers to secure the stream from potential tampering and eavesdropping.

Certificates are part of the deployment used to bring up CN2. In Kubernetes all certificates are translated to secrets. By default, the certificate and secrets for the Contrail control plane and vRouter are automatically generated in the ContrailCertificateManager CRD. If desired, you can also create certificates for other components, such as Sandesh and the Contrail API server.

You can generate certificates using one of the following tools:

- cert-manager (default): The cert-manager tool adds certificates as resource types in Kubernetes clusters and simplifies the process of obtaining, renewing and using those certificates. By default, the certificate is valid for 10 years and automatically renews 15 days before its expiration date.
- go-crypto: go-crypto is a cryptographic package you can use to generate certificates. This package is a lightweight generator that does not use containers. By default, the certificate is valid for 10 years, but is not automatically renewed.

Considerations

Read through this list of considerations before you begin the configuration:

- When a certificate is renewed, you must restart the pod.
- You must enable TLS encryption for the Contrail control plane and vRouter, even if a certificate is provided.
- If you are creating your own certificate authority (CA), the secret must contain the keys tls.crt and tls.key.

Configure TLS Encryption for Contrail Control Plane and vRouter

Follow the steps in this procedure to easily configure TLS encryption for the Contrail control plane and vRouter.

NOTE: By default, TLS encryption is enabled for XMPP and introspect for control and vRouter. TLS-based XMPP is used to secure all XMPP communication that occurs in the networking environment. If you prefer, you can disable TLS encryption by specifying the *false* variable under the spec field in your control and vRouter YAML files. For example: xmppAuthEnable: false
introspectSslEnable: false

To configure TLS encryption for the Contrail control plane and vRouter:

1. Specify the generatortype, either cert-manager or go-crypto in ContrailCertificateManager. The default generator is cert-manager.

In Kubernetes all certificates are translated to secrets. When you generate the certificate, the secrets are automatically created when you apply your deployment.yaml file.

The following examples show certificates created in cert-manager and go-crypto for control and vRouter: Example using cert-manager:

```
apiVersion: configplane.juniper.net/v1alpha1
kind: ContrailCertificateManager
metadata:
  name: contrail-certificate-manager
  namespace: contrail
spec:
  common:
    containers:
    - image: REGISTRY/contrail-k8s-cert-manager:TAG
      name: contrail-k8s-cm
    - name: cert-manager
      image: REGISTRY/cert-manager:TAG
    - name: cert-manager-webhook
      image: REGISTRY/cert-manager-webhook:TAG
    - name: cert-manager-cainjector
      image: REGISTRY/cert-manager-cainjector:TAG
  generatortype: cert-manager
  casecret:
    name: contrail-ca
    namespace: contrail
  secrets:
    - name: xmpp-tls-vrouter-agent
      namespace: contrail
      components:
      - vrouter-xmpp
```

duration: 87600 [also default and value in hours] renewBefore: 360 [also default and value in hours]

Example using gocrypto:

```
apiVersion: configplane.juniper.net/v1alpha1
kind: ContrailCertificateManager
metadata:
  name: contrail-go-crypto
  namespace: contrail
spec:
  common:
    containers:
    - image: REGISTRY/contrail-k8s-gocrypto:TAG
      name: contrail-k8s-cm
  generatortype: gocrypto
  secrets:
    - name: xmpp-tls-vrouter-agent
      namespace: contrail
      components:
      - vrouter-xmpp
      duration: 87600 [also default and value in hours]
    - name: xmpp-tls-control
      namespace: contrail
      components:
      - control-xmpp
    - name: contrail-api-tls
      namespace: contrail
      dnsNames:
      - contrail-api.contrail-system.svc
      components:
      - control-sandesh
```

- 2. Apply your deployment.yaml file to generate the certificate.
- **3.** Verify your configuration.

Run the following kubect1 commands to verify that the certificate and secrets were successfully generated.

All contrail secrets created by cert-generator in deployer are labeled with contrail=default and certificate info NotAfter and NotBefore are added in annotation to view secret validity.

```
list secrets
kubectl get secret -l contrail=default -A
list secrets with more info
kubectl get secret -l contrail=default -A | tail +2 | awk '{print "kubectl describe secret
"$2" -n "$1}' | while read line; do $line; done | grep -e "Name:" -e "Namespace:" -e
"NotAfter:" -e "NotBefore:"
Download certificate from secret: [install jq]
kubectl get secret -n contrail contrail-api-tls -o json | jq -r '.data."tls.key"' | base64 -d
> tls.key
View certificate:
openssl x509 -noout -text -in tls.crt
```

By default, certificates and secrets are automatically generated in ContrailCertificateManager. You can also create secrets for other components or create your own CA.

To create secrets for other components, specify the component(s) you want to use in either certmanager or gocrypto. You can use one secret for multiple components. The available components are:

- control-xmpp
- vrouter-sandesh
- control-sandesh
- contrail-api-server
- vrouter-xmpp

If you did not enter a casecret in ContrailCertificateManager, a self-signed certificate is automatically created. This self-signed certificate is valid for 10 years.

If desired, you can specify your own CA certificate as shown in the following example. The secret must contain the keys tls.crt and tls.key.

```
apiVersion: v1
kind: Secret
metadata:
   name: ca-key-pair
   namespace: contrail
data:
   tls.crt:
```

```
<output of cat cacert.pem | base64 -w0>
tls.key:
<output of cat cakey.pem | base64 -w0>
```

Run the kubect1 apply -f ca-key-pair.yaml command to apply the secret.

SEE ALSO

Configuring Transport Layer Security Based XMPP in Contrail

Routing Policies

SUMMARY

Juniper Cloud-Native Contrail Networking (CN2) release 23.3 supports routing policies. Routing Policies modify a route's path and attributes dynamically. With release 23.3, the manipulation and filtering of routes is more granular.

IN THIS SECTION

- Routing Policies Overview | 106
- Routing Policy List Terms | **107**
- Apply a Routing Policy | **108**
- Create a Routing Policy | 109
- Routing Policies and BGP Extended Communities | 110
- Create a Routing Policy With BGP Extended
 Communities | 111
- Policy Actions | 114

Routing Policies Overview

Contrail uses routing policies to control the flow of network traffic between virtual networks (VNs). Routing policies enable you to define how traffic is forwarded, filtered, and controlled based on certain conditions. Routing policies define conditions (source or destination IP address, packet attributes, routing protocols) packets must meet for the policy to apply.

For more information about routing policies, see Routing Policy.

Routing Policy List Terms

Routing policies contain a set of list terms. List terms are conditions and actions that determine how routing policies handle traffic. Each routing policy can consist of one or more terms. Each terms specifies a set of conditions (match conditions) to be met and the corresponding actions to take if those conditions are fulfilled. A term can be a terminal rule, meaning that upon a match on the specified term, no further terms are evaluated and the route is dropped or accepted, based on the action in that term.

If the term is not a terminal rule, subsequent terms are evaluated for the given route. The following example shows the structure of list terms:

```
Policy {
    Term-1
    Term-2
}
```

The following example shows the structure of a term's match conditions and actions:

```
from {
    match-condition-1
    match-condition-2
    ..
    ..
}
then {
    action
    update-action-1
    update-action-2
    ..
}
```

A term cannot contain an any match condition. For example, an empty from cannot be present.

If an any match condition is present, all routes are considered as matching the term. In contrast, the then condition can be empty or the action can be unspecified.

Apply a Routing Policy

A routing policy evaluation has the following key points:

- If the term of a routing policy consists of multiple match conditions, a route must satisfy all match conditions to apply the action specified in the term.
- If a term in the policy does not specify a match condition, all routes are evaluated against the match.
- If a match occurs but the policy does not specify an accept, reject, or next term action, one of the following occurs:
 - The next term, if present, is evaluated.
 - If no other terms are present, the next policy is evaluated.
 - If no other policies are present, the route is accepted. The default routing policy action is "accept".
- If a match does not occur with a term in a policy, and subsequent terms in the same policy exist, the next term is evaluated.
- If a match does not occur with any terms in a policy, and subsequent policies exist, the next policy is evaluated.
- If a match does not occur by the end of a policy or all policies, the route is accepted.

A routing policy consists of multiple terms. Each term consists of match conditions and actions to apply to matching routes.

Each route is evaluated against the policy as follows:

- **1.** The route is evaluated against the first term. If it matches, the specified action is taken. If the action is to accept or reject the route, that action is taken and the evaluation of the route ends. If the next term action is specified or if no action is specified, or if the route does not match, the evaluation continues as described above to subsequent terms.
- **2.** Upon hitting the last non-terminal term of the given routing policy, the route is evaluated against the next policy, if present, in the same manner as described in step 1.

Create a Routing Policy

The following is an exampe virtual network with a routing policy referenced in the routingPolicyReferences field.

```
apiVersion: core.contrail.juniper.net/v5
kind: VirtualNetwork
metadata:
  creationTimestamp: "2023-08-24T16:52:41Z"
  finalizers:
  - virtual-network-id-deallocation.finalizers.core.juniper.net
  - route-target.finalizers.core.juniper.net
  - vn-routinginstance-delete.finalizers.core.juniper.net
  generation: 4
  labels:
    back-reference.core.juniper.net/4b55d55948465b8794a75b29ea02b2d4b7cb6f0130c52ae127815c9e:
Subnet_rptest-ns_rptest-subnet-1
    back-reference.core.juniper.net/626783989131f732c144823b1b51ea67fd949c537f8c775e25e530d5:
RoutingPolicy_rptest-ns_rptest
    back-reference.core.juniper.net/dd5f04a405320d130c348a4e6d02cabef25d0633cc1ff4813a3576f9:
RoutingPolicy_rptest-ns_rptestCommunityReject
    core.juniper.net/virtualnetwork: custom-default-podnetwork
    custom-default-podnetwork-uid: 4761b2bc-7ae0-4c33-8b51-894b665e3ebd
  name: rptest-vn-1
  namespace: rptest-ns
  resourceVersion: "6342"
  uid: 4761b2bc-7ae0-4c33-8b51-894b665e3ebd
spec:
  fabricSNAT: true
  fgName:
  - default-domain
  - rptest-ns
  - rptest-vn-1
  podNetwork: true
  routingPolicyReferences:
  - apiVersion: core.contrail.juniper.net/v5
    fgName:
    - default-domain
    - rptest-ns
    - rptest
    kind: RoutingPolicy
```

```
name: rptest
   namespace: rptest-ns
    uid: 8a142d00-f7fb-4872-85b6-11d6a576d7fe
  - apiVersion: core.contrail.juniper.net/v5
    fgName:
    - default-domain
    - rptest-ns
    - rptestCommunityExample
    kind: RoutingPolicy
    name: rptestCommunityExample
   namespace: rptest-ns
   uid: 7a142d00-f7fb-4872-85b6-11d6a576d7fe
  v4SubnetReference:
    apiVersion: core.contrail.juniper.net/v5
    fqName:
    - default-domain
    - rptest-ns
    - rptest-subnet-1
   kind: Subnet
   name: rptest-subnet-1
   namespace: rptest-ns
    uid: 4dd9c840-4e72-4125-97a2-f9eb5bfb756a
 virtualNetworkProperties:
    forwardingMode: 12_13
    rpf: enable
status:
 observation: ""
 state: Success
 virtualNetworkNetworkId: 4100
```

NOTE: The virtualNetworkProperties.forwardingMode field must be set to 12_13 or 13. The routing policy feature does not apply to intra-VN connections when the forwarding mode of the VN is L2.

Routing Policies and BGP Extended Communities

Border Gateway Protocol (BGP) extended communities are additional attributes for BGP routes. BGP extended communities provide a method of associating additional information like route target or encapsulation protocol with routes. Creating a routing policy with extended communities makes the

policy more granular, enabling you to distribute routes and manage traffic effectively. This makes BGP extended communities ideal for complex, dynamic routes.

CN2 offers extended community support with the import routing policy feature. This feature allows for the use of import routing policy terms to identify extended communities and execute import routing policy actions, such as the addition, adjustment, or removal of these extended communities.

CN2 supports the following extended communities:

- Route Target
- Encapsulation
- Security Group
- Origin VN
- MAC Mobility
- Load Balance
- Tag
- Color

For information about these extended communities, see BGP Extended Communities.

Create a Routing Policy With BGP Extended Communities

The following is an example of a routing policy that matches with a BGP extended community. The following example matches for a prefix specified in the termMatchCondition field and attaches the BGP color community (color:0:100) when the prefix is matched.

```
expand: {}
   community:
      add: {}
      remove: {}
      set: {}
   extcommunity:
      add:
        community:
          - color:0:100
      remove: {}
      set: {}
    service:
      add: {}
      remove: {}
      set: {}
termMatchCondition:
 asPath:
 community:
 communityList:
 communityMatchAll:
  extcommunityList:
 extcommunityMatchAll:
 external:
 family:
 localPref:
 nlriRouteType:
 prefix:
    - prefix: 172.100.70.5/32
      prefixType: exact
 prefixList:
```

Note the following fields:

- term: Represents a defined condition and associated actions to execute if term conditons are met.
- extcommunity: add:: Specifies an extended community to add to the route.

community: Contains the extended community string color:0:100.

- termMatchCondition: Specifies the conditions that must be satisfied for the actions in the term to take effect.
- asPath, community, localPref: Specifies additional term match conditions to match with the route.

• prefix: A match condition that specifies that the term will match with routes with the exact prefix 172.100.70.5/32.

The following table provides addition information about the fields of a routing policy.

Field	Guidelines
Name	Enter a name for the routing policy.
Term(s)	
Community	Select the community string to match for the routing policy. The community string is represented with accept-own , no-advertise , no-export , no-export-subconfed , no-reoriginate
Match All	Select the check box to match all the community strings.
Extended Community	Select the extended community string to match for the routing policy.
Match All	Select the check box to match the extended community strings.
Protocol	Select the protocol for the routing policy which is an array of path source or path protocol to match. The protocols are interface , aggregate , bgp , BGPaaS , interface -static, service-chain, service-interface, static, and xmpp . A path is considered as matching this condition if the path protocol is one of protocols in the list.

Table 11: Create a Routing Policy

Actions	Select the actions to be performed on the matching routes. The supported actions and the
Then	
	Example: 10.1.0.0/16 or longer A route matches this condition if its prefix matches any of the prefixes in the list.
	• longer
	• orlonger
	• exact
	Each prefix in the list is represented as prefix and match type, where the prefix match type can be:
Prefixes	Select a list of prefixes to match.
Field	Guidelines

values are listed in the Table 12 on page 114.

Table 11: Create a Routing Policy (Continued)

Policy Actions

Table 12: Policy Actions

Action	Value
action	Reject-Reject the route that matches this term. No more terms are evaluated after hitting this term.
	Accept-Accept the route that matches this term. No more terms are evaluated after hitting this term.
	Next-This is the default action taken upon matching the policy term. The route is updated according to the update specified in the policy action. Next terms present in the routing policy are processed on the route. If there are no more terms in the policy, the next routing policy is processed, if present.

Table 12: Policy Actions (Continued)

Action	Value
add community Add a list of community to the existing community.	The community is of type unsigned 32 bit integer:unsigned 32 bit integer. For example, 64512:55555.
add extended community Add a list of extended community to the existing community.	An eight octet string representation of value type:administrator:assigned- number where type is two octets, administrator is four octets, and assigned- number is two octets or it can be a hexadecimal representation of the community like: 0xFFffA101.
as-path Select different AS paths to control routing decisions	Unsigned 32-bit integer representing the as-path. For example, 444.
local-preference Select the local preference to distinguish routes and take further action.	Unsigned 32-bit integer representing local-preference. For example, 444.
med Select the MED of the BgpPath.	Unsigned 32-bit integer representing the MED. For example, 444.
remove community Remove a list of community (if present) from the existing community.	The community is of type unsigned 32 bit integer:unsigned 32 bit integer.
remove extended community Remove a list of extended community (if present) from the existing community.	An eight octet string representation of value type:administrator:assigned- number where type is two octets, administrator is four octets, and assigned- number is two octets or it can be a hexadecimal representation of the community like: 0xFFffA101.

Table 12: Policy Actions (Continued)

Action	Value
set community Set a list of community.	The community is of type unsigned 32 bit integer:unsigned 32 bit integer.
set extended community Set a list of extended community.	An eight octet string representation of value type:administrator:assigned- number where type is two octets, administrator is four octets, and assigned- number is two octets or it can be a hexadecimal representation of the community like: 0xFFffA101.

RELATED DOCUMENTATION

Routing Policy

Global Security Policy

SUMMARY

Juniper Cloud-Native Contrail Networking (CN2) release 23.3 supports the selectors field for global Contrail security policies. The selectors field is a combination of the podSelector and namespaceSelector fields. Global Contrail security policies define allow and deny rules for ingress and egress traffic between workloads (pods) across clusters. A global policy with a defined podSelector applies to pods with the label specified in the podSelector field. A global policy with a defined namespaceSelector applies to pods with the namespace label specified in namespaceSelector field.

IN THIS SECTION

- Global Security Policy Overview | 117
- Policy Scoping With Generic Label
 Selectors | 118
- Policy Priority | **120**

Global Security Policy Overview

CN2 release 23.2 enhanced security policies by introducing a global security policy. Unlike namespace security policies, global Contrail security policies address multiple worker clusters within the same CN2 deployment and their traffic use-cases. A multi-cluster deployment benefits from a global policy because it provides consistent, centralized policy management across multiple clusters and an efficient way to control traffic across clusters. Apply a global policy and all matching ingress and egress traffic is controlled by defined rules cluster-wide.

The following is an example of a GlobalContrailSecurityPolicy.

```
apiVersion: core.contrail.juniper.net/v3
kind: GlobalContrailSecurityPolicy
metadata:
  name: example-policy
spec:
  rules:
    - srcEP:
        endPoints:
          - podSelector:
              matchLabels:
                app: frontend
      dstEP:
        endPoints:
          - podSelector:
              matchLabels:
                app: backend
          - ipBlock:
              cidr: 174.16.10.50/24
      ports:
        - protocol: TCP
          port: 80
        - protocol: UDP
          port: 81
  action: pass
```

Note the kind field, and the lack of the namespace field in this policy's metadata. This policy is global because it is not associated with a namespace.

Policy Scoping With Generic Label Selectors

Along with global policies, CN2 release 23.2 introduced Contrail security policy. Global policies and Contrail security policies enable you to apply a policy that affects traffic from its source endpoint to the destination endpoint. By default, these policies do not contain a pod selector. This means that if you define any of these policies, those policies apply to all the pods across clusters. Use the PodSelector feature to apply a policy to a specific set of pods.

Starting in release 23.3, you can apply a policy to a specific pod with the selectors field. Selectors enable you to apply a policy to a set of pods within the same namespace or across namespaces.

The following is an example of a GlobalContrailSecurityPolicy. Note that this policy (example-policy) does not contain selectors. This policy applies to srcEP pods with the label dept: hr and dstEP pods with the label dept: fc.

```
apiVersion: core.contrail.juniper.net/v5
 kind: GlobalContrailSecurityPolicy
 metadata:
    name: example-policy
 spec:
    rules:
      - srcEP:
          endPoints:
            - podSelector:
                matchLabels:
                  dept: hr
                matchExpressions:
                  - {key: tier, operator: In, values: [one]}
            - ipBlock:
                cidr: 174.19.12.11/32
        dstEP:
          endPoints:
            - podSelector:
                matchLabels:
                  dept: fac
            - ipBlock:
                cidr: 174.19.12.12/32
        ports:
          - protocol: TCP
            port: 3300
```

```
endPort: 3400 action: pass
```

The following GlobalContrailSecurityPolicy example applies to pods with the label site: svl within namespaces with the label ns: ns-svl.

```
apiVersion: core.contrail.juniper.net/v5
 kind: GlobalContrailSecurityPolicy
 metadata:
    name: example-policy
 spec:
   selectors:
     - podSelector:
          matchLabels:
            site: svl
      - namespaceSelector:
          matchLabels:
            ns: ns-svl
    rules:
     - srcEP:
          endPoints:
            - podSelector:
                matchLabels:
                  dept: hr
                matchExpressions:
                  - {key: tier, operator: In, values: [one]}
            - ipBlock:
                cidr: 174.19.12.11/32
       dstEP:
          endPoints:
            - podSelector:
                matchLabels:
                  dept: fac
            - ipBlock:
                cidr: 174.19.12.12/32
       ports:
          - protocol: TCP
            port: 3300
            endPort: 3400
    action: pass
```

In the case of global policies, you must at least define the namespaceSelector field.

Policy Priority

Because CN2 uses both Kubernetes network polices and namespace security policies, a sequence is required to determine how rules are processed between the two different policies.

The rules for namespace security polices are prioritized first, followed by Kubernetes network policies.

Each policy is prioritized as follows:

- 1. Global Security Policies (Deny)
- 2. Global Security Policies (Pass)
- **3.** Namespace Security Policies (Deny): By default, if a pod does not match any policies in CN2, traffic is denied. The **deny** policies are given a higher priority over the **pass** policies.
- **4.** Namespace Security Policies (Pass): If you do not define a policy in CN2, traffic is allowed between all pods in the corresponding namespace.
- 5. Kubernetes Network Polices: By default, a Kubernetes network policy allows traffic from all sources.

RELATED DOCUMENTATION

Kubernetes Network Policy

Enable Namespace Isolation by Default

SUMMARY

Juniper Cloud-Native Contrail Networking (CN2) release 23.3 supports a default tag for isolated namespaces. With CN2, you can enable a cluster to create isolated namespaces by default.

IN THIS SECTION

- Namespaces Overview | 121
- Namespaces | 121
- Isolated Namespaces | 121

Default Namespace Isolation | 122

Namespaces Overview

Namespaces

Network communication between namespaces is allowed by default. The default namespace behavior is siffucient for several uses cases. For example, a single team or single application using a given cluster, and when all namespaces are within the same administrative and security boundary. For various teams across multiple applications however, isolated namespaces might be ideal.

For instance, you can have separate namespaces for databases, or monitoring. Resource names must be unique within a namespace, but they can be the same across different namespaces. Pods in a standard namespace exhibit the following network behavior:

- Pods in standard namespaces can communicate with other pods in the cluster without using NAT.
- Pods and services in standard namespaces share the same default-podnetwork and default-servicenetwork.

Isolated Namespaces

An isolated namespace enables you to segment resources at a network layer to prevent communication with other namespaces. This is helpful to introduce security mechanisms and reduce lateral movement within a cluster. You can create an isolated namespace to isolate a pod from all other pods outside of its namespace, without the added complexity of explicitly configuring a network policy. Each isolated namespace has its own pod network and service network. This means that pods in isolated namespace cannot reach pods or services in other isolated or standard namespaces. Pods in isolated namespace can only communicate with pods in the same namespace. The only exception is when a pod in an isolated namespace needs access to a Kubernetes service, such as Core DNS. In this case, the pod uses the cluster's default-servicenetwork to access the services.

Pods in an isolated namespace exhibit the following network behavior:

- Pods in isolated namespaces can only communicate with pods in the same namespace.
- Pods in isolated namespaces can reach services in non-isolated namespaces.

- The IP addresses and service IP addresses of pods in isolated namespaces are allocated from the same subnet as the cluster's pod and service subnet.
- Pods in an isolated namespace can access the underlay network, or IP fabric network, though IP fabric forwarding and fabric source NAT.

Default Namespace Isolation

CN2 release 23.3 lets you enable namespace isolation by default via an enhanced kubemanager. In 23.3, the following changes enhance the kubemanager spec:

- IsolateNamespaces: Set the enable field in this object to ensure that all namespaces created within the assiocated cluster are isolated. You can toggle this field at any time but it doesn't affect existing namespaces.
- Enable: Set to true to activate the IsolateNamespace field.
- ExceptionList: Enter a list of namespaces that won't be affected by the IsolateNamespaces feature. When you enable IsolateNamespaces and a namespace must be non-isolated, the name of that namespace must be added to the ExceptionList before you create the namespace.
- DefaultForwardingMode: Specify the forwarding mode to be used by all isolated namespaces within this cluster. The available options are:
 - fabric-snat (Fabric SNAT)
 - ip-fabric (IP Fabric Forwarding)

Leave this field blank if you don't require any forwarding for the isolated namespaces. Any forwarding mode specified as an explicit label on the namespace itself takes priority over the DefaultForwardingMode setting. Any namespace explicitly created as an isolated namespace will take priority over the state of the enable field or presence of the name in the exception list.

NOTE: These fields only exist for CN2 release 23.3 or later. Release 23.3 has a new apiVersion (v1) for the configplane.juniper.net group. These fields are not present for v1alpha1.

The following is an example kubemanager configuration.

```
apiVersion: configplane.juniper.net/v1
kind: Kubemanager
metadata:
   name: contrail-k8s-kubemanager
   namespace: contrail
```

spec:

isolateNamespaces:

enable: true

defaultForwardingMode: fabric-snat

exceptionList:

- non-isolated-ns-1
- non-isolated-ns-2

RELATED DOCUMENTATION

Create an Isolated Namespace



Advanced Virtual Networking

Create an Isolated Namespace | 126 Configure Allowed Address Pairs | 137 Enable Packet-Based Forwarding on Virtual Interfaces | 139 Configure Reverse Path Forwarding on Virtual Interfaces | 142 Configure Fast Convergence | 144 Configure Graceful Restart and Long-Lived Graceful Restart | 150 vRouter Interface Health Check | 156 Kubernetes Ingress Support | 162 Deploy VirtualNetworkRouter in Cloud-Native Contrail Networking | 166 Configure Inter-Virtual Network Routing Through Route Targets | 186 Configure IPAM for Pod Networking | 191 Enable VLAN Subinterface Support on Virtual Interfaces | 195 Subinterface Support with Multus | 202 EVPN Networking Support | 211 Customize Virtual Networks for Pod Deployments, Services, and Namespaces 215 Deploy Kubevirt DPDK Dataplane Support for VMs | 222 Pull Kubevirt Images and Deploy Kubevirt Using a Local Registry | 232 Static Routes | 235 VPC to CN2 Communication in AWS EKS | 251

Stickiness for Load-Balanced Flows | 259

Configure BFD Health Check for BGPaaS Sessions | 261

Configure a Service Account to Assume an IAM role | 265

Create an Isolated Namespace

SUMMARY

This topic describes how to create an isolated namespace in CN2 Release 22.1 or later in a Kubernetes-orchestrated environment.

IN THIS SECTION

Namespace Overview | 126
Example: Isolated Namespace Configuration | 127
Isolated Namespace Objects | 130
Create an Isolated Namespace | 131
Optional Configuration: IP Fabric Forwarding and Fabric Source NAT | 133
Enable IP Fabric Forwarding | 133
Enable Fabric Source NAT | 135

Namespace Overview

NOTE: In this document, we use the term "isolated" and "non-isolated" in the context of Contrail networking only.

Non-isolated Namespaces.

Namespaces, or non-isolated namespaces, provide a mechanism for isolating a group of resources within a single cluster. By default, namespaces are not isolated.

Non-isolated namespaces are intended for use in environments with many users spread across multiple teams, or projects. Non-isolated namespaces enable each team to exist in their own virtual cluster without impacting each other's work. Let's say you created all your resources in the default namespace that Kubernetes provides. If you have a complex application with multiple deployments, the default namespace can be hard to maintain. An easier way to manage this deployment is to group all your resources into different namespaces within the cluster. For example, the cluster can contain separate namespaces, such as a database namespace or a monitoring database. Names of resources must be unique within a namespace, but not across namespaces.

Pods in a non-isolated namespace exhibit the following network behavior:

- Pods in non-isolated namespaces can communicate with other pods in the cluster without using NAT.
- Pods and services in non-isolated namespaces share the same default-podnetwork and defaultservicenetwork.

Isolated Namespaces.

An isolated namespace enables you to run customer-specific applications that you want to keep private. You can create an isolated namespace to isolate a pod from other pods, without explicitly configuring a network policy.

Isolated namespaces are similar to non-isolated namespaces, except that each isolated namespace has its own pod network and service network. This means that pods in isolated namespaces cannot reach pods or services in other isolated or non isolated namespaces.

Pods in isolated namespace can only communicate with pods in the same namespace. The only exception is when a pod in an isolated namespace needs access to a Kubernetes service, such as Core DNS. In this case, the pod uses the cluster's default-servicenetwork to access the services.

Pods in an isolated namespace exhibit the following network behavior:


- Pods in isolated namespaces can only communicate with pods in the same namespace.
- Pods in isolated namespaces can reach services in non-isolated namespaces.
- The IP addresses and service IP addresses of pods in isolated namespaces are allocated from the same subnet as the cluster's pod and service subnet.
- Pods in an isolated namespace can access the underlay network, or IP fabric network, though IP fabric forwarding and fabric source NAT.

NOTE: You cannot covert a non-isolated namespace to an isolated namespace, and vice versa.

Example: Isolated Namespace Configuration

This sample configuration demonstrates an isolated namespace configuration in CN2.

Figure 7: Isolated Namespace Configuration



In the isolated namespace configuration:

- Pod-1 (non-isolated-1) is in a non-isolated namespace created by the user.
- Pod-2 (kube-system) and Pod-3 (contrail) are in non-isolated namespaces created by the controller.
- Pod-4 (isolated-1) and Pod-5 (isolated-2) are in isolated namespaces created by the user.
- The interfaces for Pod-1, Pod-2, Pod-3 are created from the cluster's default-podnetwork and defaultservicenetwork.
- The interfaces for Pod-4 and Pod-5 are created on the default-podnetwork and default-servicenetwork in their own isolated namespaces. Both Pod-4 and Pod-5 interfaces share the same subnet as the cluster's default-podnetwork and default-servicenetwork.

- Pods in isolated namespaces cannot communicate with pods in non-isolated namespaces. In this example, Pod-4 and Pod-5 in isolated namespaces cannot communicate with Pod-1, Pod-2, Pod-3 in non-isolated namespaces.
- Pods in isolated namespaces (Pod-4, Pod 5) can access any service through the cluster's defaultservicenetwork.
- Pods in all namespaces (non-isolated and isolated) are able to connect to the fabric through the cluster's ip-fabric-network.

Notes

- Isolated namespaces affect only the pod's default interface. This is because the default interface of
 pods in an isolated namespace are created on the default-podnetwork of the isolated namespace.
 However, interfaces from user-defined VirtualNetworks behave the same way in both isolated and nonisolated namespaces.
- You can create network policies on isolated namespaces to adjust the isolation of pods. The network policy behaves the same for both isolated and non-isolated namespaces.
- Two or more isolated namespaces can be interconnected through the VirtualNetworkRouter (VNR). See "VirtualNetworkRouter Overview" on page 167.

Here is an example of a VNR configuration used to interconnect the default-podnetworks of two isolated namespaces (ns-isolated-1 and ns-isolated-2). In this configuration, the VirtualNetworkRouter connects to ns-isolated-1 and ns-isolated-2. This means that pods in these isolated namespaces can communicate with each other.

```
apiVersion: core.contrail.juniper.net/v3
kind: VirtualNetworkRouter
metadata:
 namespace: ns-isolated-1
 name: vnr-1
  annotations:
    core.juniper.net/display-name: vnr-1
 labels:
      vnr: vnr-1
spec:
 type: mesh
 virtualNetworkSelector:
    matchExpressions:
    - key: core.juniper.net/virtualnetwork
      operator: In
      values:
```

```
- isolated-namespace-pod-virtualnetwork
 import:
   virtualNetworkRouters:
      - virtualNetworkRouterSelector:
          matchLabels:
            vnr: vnr-2
       namespaceSelector:
          matchLabels:
            kubernetes.io/metadata.name: ns-isolated-2
---
apiVersion: core.contrail.juniper.net/v3
kind: VirtualNetworkRouter
metadata:
 namespace: ns-isolated-2
 name: vnr-2
 annotations:
    core.juniper.net/display-name: vnr-2
 labels:
      vnr: vnr-2
spec:
 type: mesh
 virtualNetworkSelector:
   matchExpressions:
    - key: core.juniper.net/virtualnetwork
     operator: In
      values:
      - isolated-namespace-pod-virtualnetwork
 import:
   virtualNetworkRouters:
      - virtualNetworkRouterSelector:
          matchLabels:
            vnr: vnr-1
        namespaceSelector:
          matchLabels:
            kubernetes.io/metadata.name: ns-isolated-1
```

Isolated Namespace Objects

This table describes the namespace objects (API resources) the controller creates when you create an isolated namespace.

Table 13: Isolated Namespace Objects

Isolated Namespace Object	Description
default-podnetwork (VirtualNetwork)	The default interfaces of pods in an isolated namespace are created in this default-podnetwork, instead of the cluster's default-network.
default-servicenetwork (VirtualNetwork)	The cluster IP of services in isolated namespaces are created in this default-servicenetwork, instead of the cluster's default-servicenetwork.
IsolatedNamespacePodServiceNetwork (VirtualNetworkRouter)	This object establishes connectivity between the isolated namespace's default-podnetwork and default-servicenetwork.
IsolatedNamespaceIPFabricNetwork (VirtualNetworkRouter)	This object establishes connectivity between the isolated namespace's default-podnetwork and default-servicenetworkto the cluster's ip-fabricnetwork.
IsolatedNamespacePodToDefaultService (VirtualNetworkRouter)	This object establishes connectivity between the isolated namespace's default-podnetwork to the cluster's default-servicenetwork.

Create an Isolated Namespace

Follow these steps to create an isolated namespace:

- 1. Create a YAML file called ns-isolated.yaml.
- 2. Add the label core.juniper.net/isolated-namespace to the namespace metadata and set the variable to "true".

```
apiVersion: v1
kind: Namespace
metadata:
   name: ns-isolated
   labels:
        core.juniper.net/isolated-namespace: "true"
```

3. Issue the kubect1 apply command to apply the configuration.

kubectl apply -f ns.yaml

4. To verify your configuration, issue the kubectl get ns ns-isolated -o yaml command.

```
apiVersion: v1
kind: Namespace
metadata: `\
  annotations:
    core.juniper.net/forwarding-mode: "false"
    kubectl.kubernetes.io/last-applied-configuration: |
      {"apiVersion":"v1","kind":"Namespace","metadata":{"annotations":{"core.juniper.net/
forwarding-mode":"false"},"labels":{"core.juniper.net/isolated-namespace":"true"},"name":"ns-
isolated"}}
  creationTimestamp: "2021-10-04T21:47:40Z"
  finalizers:
  - finalizers.core.juniper.net/isns-virtualnetworks-delete
  - finalizers.core.juniper.net/isns-virtualnetworkrouters-delete
  labels:
    core.juniper.net/isolated-namespace: "true"
  managedFields:
  - apiVersion: v1
    fieldsType: FieldsV1
    •••
    ....
  name: ns-isolated
  resourceVersion: "4183"
  uid: d25d2b71-2051-4ac5-a738-e9b344235818
spec:
  finalizers:
  - kubernetes
status:
  phase: Active
```

Success! You created an isolated namespace.

Optional Configuration: IP Fabric Forwarding and Fabric Source NAT

Optionally, you can enable IP fabric forwarding and fabric source NAT on an isolated namespace.

IP fabric forwarding enables virtual networks to be created as part of the underlay network and eliminates the need for encapsulation and de-encapsulation of data. Fabric source NAT allows pods in the overlay to reach the Internet without floating IPs or a logical system.

When you create an isolated namespace, two virtual networks are created, a default-podnetwork and a default-servicenetwork. By default, IP fabric forwarding and fabric source NAT in these two virtual networks are disabled. You enable IP fabric forwarding or fabric source NAT in the virtual networks by adding "forwarding-mode" annotations for each feature in your isolated namespace YAML file.

Here is an example of the default-podnetwork for an isolated namespace with forwarding-mode set to fabricSNAT.

```
apiVersion: core.contrail.juniper.net/v3
kind: VirtualNetwork
metadata:
    annotations:
        core.juniper.net/description: Default Pod Network for IsolatedNamespace (ns-isolated)
        core.juniper.net/display-name: default-podnetwork
        ...
spec:
        ...
        fabricSNAT: true
        ...
```

Enable IP Fabric Forwarding

Follow these steps to enable IP fabric forwarding on an isolated namespace:

- **1.** Add the annotation core.juniper.net/forwarding-mode: "ip-fabric" to the namespace metadata.
- 2. Set the label for the isolated namespace to "true".

apiVersion: v1 kind: Namespace metadata: name: ns-isolated annotations: core.juniper.net/forwarding-mode: "ip-fabric" labels: "core.juniper.net/isolated-namespace": "true"

3. Issue the kubect1 apply command to enable IP fabric forwarding.

kubectl apply -f ns-isolated.yaml

4. Verify your configuration.

get vn -n ns-isolated default-podnetwork -o yaml

```
spec:
```

```
fabricForwarding: true
fabricSNAT: false
fgName:
- default-domain
- ns-isolated
- default-podnetwork
providerNetworkReference:
  apiVersion: core.contrail.juniper.net/v3
  fqName:
  - default-domain
  - contrail
  - ip-fabric
  kind: VirtualNetwork
  name: ip-fabric
  namespace: contrail
  resourceVersion: "5629"
  uid: bdb0ae55-d5e5-49b2-803d-d93eea206df0
v4SubnetReference:
  apiVersion: core.contrail.juniper.net/v3
  fqName:
  - default-domain
  - contrail-k8s-kubemanager-mycluster-contrail
  - default-podnetwork-pod-v4-subnet
  kind: Subnet
  name: default-podnetwork-pod-v4-subnet
  namespace: contrail-k8s-kubemanager-mycluster-contrail
```

```
resourceVersion: "4999"
uid: fc9b9471-3b3e-4a57-80ac-5b9ed806fe94
virtualNetworkProperties:
   forwardingMode: l3
   rpf: enable
status:
   observation: ""
   state: Success
   virtualNetworkNetworkId: 5
```

Success! You enabled IP fabric forwarding on the isolated namespace.

Enable Fabric Source NAT

NOTE: You can only enable fabric source NAT on the default-podnetwork.

Follow these steps to enable fabric source NAT on an isolated namespace:

- 1. Add the annotation core.juniper.net/forwarding-mode: "fabric-snat" to the namespace metadata.
- 2. Set the label for the isolated namespace to "true".

```
apiVersion: v1
kind: Namespace
metadata:
name: ns-isolated
annotations:
    core.juniper.net/forwarding-mode: "fabric-snat"
    labels:
        "core.juniper.net/isolated-namespace": "true"
```

3. Issue the kubect1 apply command to enable fabric source NAT.

kubectl apply -f ns-isolated.yaml

4. Verify your configuration.

kubectl get vn -n <isolated-namespace-name> default-podnetwork

Success! You enabled fabric source NAT on the isolated namespace.

spec:
fabricSNAT: true
fqName:
- default-domain
- ns-isolated-snat
- default-podnetwork
v4SubnetReference:
apiVersion: core.contrail.juniper.net/v3
fqName:
- default-domain
- contrail-k8s-kubemanager-mycluster-contrail
- default-podnetwork-pod-v4-subnet
kind: Subnet
name: default-podnetwork-pod-v4-subnet
namespace: contrail-k8s-kubemanager-mycluster-contrail
resourceVersion: "4999"
uid: fc9b9471-3b3e-4a57-80ac-5b9ed806fe94
virtualNetworkProperties:
forwardingMode: 13
rpf: enable
status:
observation: ""
state: Success
virtualNetworkNetworkId: 7

SEE ALSO

Enable IP Fabric Forwarding and Fabric Source NAT | 2

Configure Allowed Address Pairs

Starting in CN2 Release 22.1 or later, Juniper Networks supports allowed address pairs (AAPs). Allowed address pairs enables you to add IP/MAC (CIDR) addresses to the guest interface (VirtualMachineInterface) by using a secondary IP address.

When you create a pod in a cluster, each pod automatically obtains its IP address from the virtual machine (VM) interface. If your pod is *not* on the same virtual network, you can add an AAP to allow traffic to flow through the port regardless of the subnet. For example, let's say that your pod's IP address is 192.168.2.0. If you define an AAP with subnet 192.168.2.0/24, the AAP allows the pods to communicate with the guest interface. The vRouter then forwards the traffic and advertises reachability to the pod.

To configure an allowed address pair, insert the following attributes into your pod YAML file. For example:

```
kind: Pod
metadata:
  name: my-pod
  namespace: my-namespace
  annotations:
    k8s.v1.cni.cncf.op/networks: |
      Ε
        {
          "name": "net-a",
          "cni-args": {
               "net.juniper.contrail.allowedAddressPairs": [{
                 "ip": 192.168.2.0/24
                 "mac": "02:3f:66:ad:00:e9",
                 "addressMode": "active-active"
              }].}
          . . .
        },
        {
          "name": "net-b",
          . . .
        },
```

The AllowedAddressPairs attribute contains a list of allowed address pair definitions, as described in the following table:

Table 14: Allowed Address Pair Definitions

Definition	Description
ip	Specify the external pod IP address through which you want to allow traffic to pass.
mac	(Optional) Specify the MAC address of the external pod.
addressMode	(Optional) Specify a high availability (HA) address mode. Choose from <i>active/active</i> or <i>active/standby</i> . Active/standby is the default.
	The addressMode default value is an empty string. <i>Active/standby</i> is used for VRRP addresses. <i>Active/</i> <i>active</i> is used for ECMP.

In Kubemanager, the PodController watches for Pod events and reads the interface definitions for each new AAP. The controller then generates an AllowedAddressPair and adds it to the list of interfaces in the VirtualMachineInterface.

Alternative Configuration

Alternatively, you can configure AAP interfaces directly from the VirtualMachineInterface. For example:

```
kubectl patch --namespace project-kubemanager VirtualMachineInterface $VMINAME -p "$(cat ./
aap.yaml)"
```

The preceding command updates the existing VirtualMachineInterface with the AAP configuration, as follows:

```
spec:
allowedAddressPairs:
allowedAddressPair:
- ip:
ipPrefix: 192.0.2.0
ipPrefixLen: 24
```

Enable Packet-Based Forwarding on Virtual Interfaces

IN THIS SECTION

- Overview | 139
- Configure Packet Mode on a Virtual Interface | 139

Juniper Networks supports packet-based forwarding on virtual interfaces using CN2 Release 22.1 or later in a Kubernetes-orchestrated environment.

Overview

By default, Contrail compute nodes use flow mode for packet forwarding on a virtual interface. This means that every vRouter has a flow table to keep track of all flows that pass through it. In flow mode, the virtual interface processes all traffic by analyzing the state or session of traffic. However, in some instances you might want to switch from flow mode to packet mode. For example, you might want to achieve higher traffic-forwarding performance or get around certain limitations of flow mode.

In packet mode, the virtual interface processes the traffic on a per-packet basis and ignores all flow information. The main advantage of packet mode is that the processing type is stateless. Stateless mode means that the virtual interface does not keep track of session information or goes through traffic analysis to determine how a session is established.

NOTE: Features that require a network policy (such as ACLs, security groups, and floating IPs) are unable to work in packet mode.

Configure Packet Mode on a Virtual Interface

To configure packet mode on a virtual interface:

1. Verify that you are running flow mode. For example:

Generate some traffic by pinging another pod in the same network. In this example, the pod's IP address is 25.26.27.2.

```
root@pod-vn-1:/# ping -q -c5 25.26.27.2
PING 25.26.27.2 (25.26.27.2) 56(84) bytes of data.
--- 25.26.27.2 ping statistics ---
5 packets transmitted, 5 received, 0% packet loss, time 4057ms
rtt min/avg/max/mdev = 0.059/1.721/7.620/2.955 ms
```

2. Use the flow command-line tool to check for flows. The following example indicates that the virtualMachineInterface is in flow mode.

```
root@minikube:/# flow -1 --match 25.26.27.3
. . .
. . .
Listing flows matching ([25.26.27.3]:*)
   Index
                       Source:Port/Destination:Port
                                                                      Proto(V)
                     _____
                                                                       _ _ _ _ _ _ _ _ _
                       25.26.27.2:28
                                                                        1 (3)
  159692<=>400664
                       25.26.27.3:0
(Gen: 1, K(nh):39, Action:F, Flags:, QOS:-1, S(nh):39, Stats:5/490, SPort 64222,
TTL 0, UnderlayEcmpIdx:0, Sinfo 7.0.0.0)
  400664<=>159692
                       25.26.27.3:28
                                                                        1 (3)
                       25.26.27.2:0
(Gen: 1, K(nh):33, Action:F, Flags:, QOS:-1, S(nh):33, Stats:5/490, SPort 56567,
TTL 0, UnderlayEcmpIdx:0, Sinfo 5.0.0.0)
```

3. Enable packet mode on the virtualMachineInterface.

Create a patch file named packet-mode-patch.yaml, and set the VMI policy to true.

spec:

virtualMachineInterfaceDisablePolicy:true

4. Apply the patch.

```
[user@machine:~]$ kubectl -n vmi-disablepolicy patch vmi pod-vn-1-7d622c4d --patch "$(cat
packet-mode-patch.yaml)"
virtualmachineinterface.core.contrail.juniper.net/pod-vn-1-7d622c4d patched
```

After you apply the patch flow mode switches to packet mode, as shown in the following example:

```
[user@machine:~]$ kubectl -n vmi-disablepolicy get vmi pod-vn-1-7d622c4d -oyaml |
yq .spec.virtualMachineInterfaceDisablePolicy
true
```

5. Verify that packet mode is active.

Generate traffic by pinging another pod in the same network that you pinged in Step 1.

root@pod-vn-1:/# ping -q -c5 25.26.27.2
PING 25.26.27.2 (25.26.27.2) 56(84) bytes of data.
--- 25.26.27.2 ping statistics --5 packets transmitted, 5 received, 0% packet loss, time 4105ms
rtt min/avg/max/mdev = 0.051/2.725/13.388/5.331 ms

6. Use the flow command-line tool to check for flows.



Success! No flows exist, which indicates that you are in packet mode.

Configure Reverse Path Forwarding on Virtual Interfaces

IN THIS SECTION

- Overview | 142
- Enable RPF on a Virtual Interface | 143

Starting in CN2 Release 22.1 or later, Juniper Networks supports reverse path forwarding (RPF) on virtual interfaces in a Kubernetes-orchestrated environment.

Overview

Unicast reverse-path-forwarding (RPF) verifies that a packet is sent from a valid source address by performing an RPF check. RPF check is a validation tool that uses the IP routing table to verify whether the source IP address of an incoming packet is arriving from a valid path. RPF helps reduce forwarding of IP packets that might be spoofing an IP address.

When a packet arrives on an interface, RPF performs a forwarding table lookup on the packet's source IP address and checks the incoming interface. The incoming interface must match the interface on which the packet arrived. If the interface doesn't match, the vRouter drops the packet. If the packet is from a valid path, the vRouter forwards the packet to the destination address.

You can enable or disable source RPF on a per-virtual network basis. By default, RPF is disabled.

- RPF enable: Whenever a packet reaches the interface, RPF performs a check on the packet's source IP address. All packets are dropped if the route is not learned by the vRouter. Only packets received from the MAC/IP address allocated to the workload are permitted on an interface.
- RPF disable: Packets from any source are accepted on the interface. A forwarding table lookup is not performed on the incoming packet source IP address.

Enable RPF on a Virtual Interface

To enable RPF on a virtual interface, set the rpf variable under virtualNetworkProperties to enable. For example:

```
apiVersion: v1
kind: Namespace
metadata:
  name: rpf-ns
---
apiVersion: core.contrail.juniper.net/v3
kind: Subnet
metadata:
  namespace: rpf-ns
  name: rpf-subnet-1
  annotations:
    core.juniper.net/display-name: Sample Subnet
    core.juniper.net/description:
      Subnet represents a block of IP addresses and its configuration.
      IPAM allocates and releases IP address from that block on demand.
      It can be used by different VirtualNetwork in the mean time.
spec:
  cidr: "172.20.10.0/24"
---
apiVersion: core.contrail.juniper.net/v3
kind: VirtualNetwork
metadata:
  namespace: rpf-ns
  name: rpf-vn-1
  annotations:
    core.juniper.net/display-name: Sample Virtual Network
    core.juniper.net/description:
      VirtualNetwork is a collection of end points (interface or ip(s) or MAC(s))
      that can communicate with each other by default. It is a collection of
      subnets whose default gateways are connected by an implicit router
spec:
  v4SubnetReference:
    apiVersion: core.contrail.juniper.net/v3
    kind: Subnet
    namespace: rpf-ns
    name: rpf-subnet-1
```

fabricSNAT: true
virtualNetworkProperties:
 rpf: enable

RELATED DOCUMENTATION

Understanding How Unicast Reverse Path Forwarding Prevents Spoofed IP Packet Forwarding

Configure Fast Convergence

SUMMARY

This topic describes Fast Convergence in Juniper® Cloud-Native Contrail Networking (CN2) Release 23.2 and later in a Kubernetes-orchestrated environment.

IN THIS SECTION

- What Is Convergence | 144
- Fast Convergence in a Network Managed by CN2 | **145**
- Configure Fast Convergence | 148

What Is Convergence

Convergence or routing convergence is a state in which a set of routers share the same topological information. The routers collect the topology information through the routing protocol. Convergence happens when routers send this information to all routers in the network. Any change in the network (link failure, router failure, or change in the topology) affects convergence until the change is propagated to all routers in the network and convergence occurs again. The time taken by the routers in the network to reach convergence after a change is referred to as "convergence time".

Network convergence and fast failover are critical for high performance service provider networks that run sensitive applications. The speed of achieving convergence in a network depends on the following actions:

• Detection—A device detects a failure in the route. Corrective action, such as identifying a new forwarding path, is taken only after the identifying the device that failed.

In a virtual network, device reachability is established through keepalive messages. To achieve fast convergence, the detection time (the time it takes to detect a failure) is of high importance so you must keep the be kept within the acceptable limits.

- Local Repair—As soon as a device failure is detected in the primary route, traffic is diverted to the backup route. When this occurs, the failure or change in topology, is not propagated to all the devices in the network.
- Global Repair—Global repair (or network convergence) happens when the change in topology is propagated to all devices in the network though the routing protocols.

The availability of services depends on the time it takes to detect and correct any failures.

Fast Convergence in a Network Managed by CN2

CN2 provides an SDN solution that offers network virtualization at the compute node-level through overlay networking. In an SDN, failures can occur in the overlay or in the underlay. A failure in the overlay can be caused by a failed virtual machine or a failed pod. The vRouter detects, rectifies, and propagates any failure to the gateways by using health checks. Of the several possible types of failure in the underlay, the most critical failures are the SDN gateway and compute node failures.

Fast convergence improves the convergence time in case of failures in a cluster managed by CN2. In a typical Cloud-Native Contrail network, the customer endpoints connect to the vRouter through MPLSoUDP, GRE, or VXLAN overlay tunnels from the gateway device. The vRouters connect to the MPLS gateway through the fabric endpoints.

With fabric underlay routing, most fabric underlay failures such as those in the leaf or spine, can be addressed quickly without impacting the flow of traffic. However, two types of failures can lead to silent packet drop failures in the vRouter and failures in the gateway device. These failures are referred to as tunnel endpoint failures.

The control node maintains the overlay tunnels, which exchanges routes between the tunnel endpoints. The control node uses BGP to exchange routes with the gateway devices and XMPP to exchange routes with the vRouter. Because no keepalive messages are running on the overlay tunnels, the control node depends on the BGP hold time expiration to diagnose failures in northbound connectivity to the gateway, and on the XMPP timeout for failures for southbound connectivity to the vRouter. Any gateway failure in the gateway can lead to a silent packet drop for up to 90 seconds (the default value for BGP hold time expiration). This is because the control node detects the gateway failure only after the BGP hold time expires. Similarly, a failure in the vRouter can lead to a silent packet drop for up to 15 seconds (default value for XMPP timeout).

Example Scenarios

Figure 1 on page 146 shows what happens when the gateway router fails. In this example, the BGP hold time expires after 90 seconds as the destination is unreachable. This same hold time is propagated to the control node, which recognizes that the gateway router has failed. This scenario leads to a silent packet drop for 90 seconds until the routing table in the control node updates and convergence happens.





Figure 8: Tunnel Endpoint Failure: SDN Gateway

Figure 2 on page 147 shows a scenario where the vRouter fails. In this example, the control node recognizes the vRouter failure only after 15 seconds when the XMPP hold time expires. Traffic is dropped during these 15 seconds until convergence happens.

Figure 9: Tunnel Endpoint Failure: vRouter




Fast convergence reduces the convergence time if an overlay endpoint fails. The Contrail control plane responds to the changes in the underlay network and quickly reduces the convergence time. Typically, the spines learn of tunnel endpoint failures through BFD or from link down protocols. With fast convergence, the spine propagates failure information to the Contrail controller and removes the tunnel endpoint from the control node through a routing table update. The control node then recognizes this as a tunnel endpoint failure and initiates routing convergence.

- To achieve fast convergence if a gateway fails (northbound failure), the control node performs a nexthop reachability check. If a failure is detected, the control plane then initiates convergence.
- To achieve fast convergence if the vRouter fails (southbound failure), you must configure the XMPP hold time. The default hold time is 90 seconds, although the recommend timeout value is 9 seconds. A lower value (less than 9 seconds) is recommended only for smaller clusters. Whenever the XMPP hold time expires, the control node recognizes the failure and initiates convergence.

Figure 3 on page 148 shows how CN2 achieves fast convergence. Fast convergence is achieved by using the destination reachability information the spine gathers through the BFD or Linkdown protocols, and by using the XMPP timeout information sent to the control node to detect a failure in the vRouter.

Figure 10: Fast Convergence in a Contrail Managed Network



Configure Fast Convergence

By default, fast convergence is not enabled. To configure this feature, edit the global-system-config spec using the following command:

kubectl edit gsc default-global-system-config

To enable fast convergence:

Add the fastConvergenceParameters attribute under the spec field and set enable to true.

Alternatively, you can configure the following parameters:

• xmppHoldTime— XMPP hold time is used to detect vRouter failures. The timer expires when a vRouter fails. When the hold time is up, the control node again initiates convergence.

By default, the XMPP hold time is 90 seconds. You can enter a value in the range 1-90 seconds. The recommend timeout value is 9 seconds. A lower value (less than 9 seconds) is recommended only for smaller clusters.

 nhReachabilityCheck—Next-hop reachability determines the next-hop IP address for forwarding packets to a specific destination. To check next-hop reachability for the gateway and vRouter, set nhReachabilityCheck to true.

The following is an example of a fast convergence configuration:

```
apiVersion: v1
items:
- apiVersion: core.contrail.juniper.net/v4
  kind: GlobalSystemConfig
metadata:
  creationTimestamp: "2023-05-02T01:06:46Z" generation: 8
  labels:
    back-reference.core.juniper.net/e7868747b69fb26facc616309440afd4b538819946ee7b838dcc9632:
BGPRouter_contrail_5a11s30
  name: default-global-system-config
  resourceVersion: "4361491"
  uid: ad026e2c-1b9a-4bd7-b395-f90b92437a7f
spec:
  autonomousSystem: 64512
  bgpRouterReferences:
  - apiVersion: core.contrail.juniper.net/v2
    fgName:
    - default-domain
    - contrail
    - ip-fabric
    - default
    - 5a11s30
    kind: BGPRouter
    name: 5a11s30
    namespace: contrail
    uid: ac6d821c-bbd3-4973-bf26-a918cd664f82
  enable4bytesAS: false
  fastConvergenceParameters:
     enable: true
     nhReachabilityCheck: true
     xmppHoldTime: 9
  fgName:
  - default-global-system-config
  ibgpAutoMesh: true
status:
  observation: ""
```

```
state: Success
kind: List
metadata:
resourceVersion: ""
```

SEE ALSO

Fast Routing Convergence with Contrail Networking

Configure Graceful Restart and Long-Lived Graceful Restart

SUMMARY

This topic describes Graceful Restart and Long-Lived Graceful Restart (LLGR) Juniper® Cloud-Native Contrail Networking (CN2) Release 23.2 and later in a Kubernetes-orchestrated environment.

IN THIS SECTION

- Overview | 150
- Configure Graceful Restart and LLGR | 152

Overview

IN THIS SECTION

- BGP Helper Mode | 151
- XMPP Helper Mode | 151

In CN2, whenever a peer session is detected as down, the control node deletes all routes learned from the peer and immediately withdraws the routes from its advertised peers. This event causes instantaneous disruption of traffic among the worker nodes. To prevent this, you can configure graceful restart and long-lived graceful restart (LLGR). Enabling these features ensures that routes learnt are not immediately deleted and withdraw from the advertised peers. Instead, the routes are kept and marked as stale. Consequently, if sessions come back up and routes are relearned, the overall impact to the network is minimized.

Graceful restart allows a routing device undergoing a restart to inform its adjacent neighbors and peers of its condition. LLGR is a mechanism used to preserve routing details for a longer period of time in the event of a failed peer. LLGR retains stale routes for a much longer time than that allowed by graceful restart alone. With LLGR, route preference is retained and best paths are recomputed.

NOTE:

- Graceful restart and LLGR support IPv4, IPv6, and EVPN Type 2 routes.
- Neither graceful restart nor LLGR supports multicast traffic.

BGP Helper Mode

You can use BGP helper mode to minimize routing churn whenever a BGP session flaps. Or when the BGP peers restart, BGP helper mode can be used to minimize the impact to the network. This is especially helpful if the SDN gateway router goes down gracefully, as in an rpd crash or restart on a device. In that case, CN2 acts as a helper to the gateway, by retaining the routes learned from the gateway and advertises them to the rest of the network, as applicable. For this to work, the restarting router (the SDN gateway in this case) must support and be configured with graceful restart for all of the address families used.

BGP helper mode is also supported for BGP-as-a-Service (BGPaaS) clients. When configured, CN2 provides BGP helper mode to a restarting BGPaaS client.

XMPP Helper Mode

Contrail vRouter datapath agent supports route retention with its controller peer when LLGR with XMPP helper mode is enabled. This route retention allows the datapath agent to retain the last route path from the Contrail controller when an XMPP-based connection is lost. The route paths are held by the agent until a new XMPP-based connection is established to one of the Contrail controllers. Once the XMPP connection is up and is stable for a predefined duration, the route paths from the old XMPP connection are flushed. This route retention allows a controller to go down gracefully but with some forwarding interruption when connectivity to a controller is restored.

When enabling graceful restart and LLGR with XMPP helper mode, consider the following:

- You can enable graceful restart and LLGR with XMPP helper mode without enabling BGP helper mode and vica-versa.
- LLGR and XMPP subsecond timers for fast convergences should not be used simultaneously.

Configure Graceful Restart and LLGR

IN THIS SECTION

Verify Your Configuration | 153

By default, graceful restart and LLGR are not enabled. To enable these features, edit the global-systemconfig spec using the following command:

kubectl edit gsc default-global-system-config

NOTE: Whenever you enable or disable gracefulRestartParameters, the GlobalSystemConfigSpec gets updated and pushed down to all control nodes. Subsequently the configuration gets pushed down to the worker nodes as well. This results in session (BGP and XMPP) flap (session restart) since the peers are exchanging the new configuration. Because of this, you might observe a small drop in traffic while the peers restart.

The following is an example of how to enable graceful restart and LLGR and assign timer values.

```
Spec:
gracefulRestartParameters:
enable: true
longLivedRestartTime: 1800
restartTime: 60
xmppHelperEnable: true
bgpHelperEnable: true
endOfRibTimeout: 90
```

In the above example, enable is set to true to enable graceful restart and LLGR. The bgpHelperEnable and xmppHelperEnable modes are set to true to enable helper modes for BGP and XMPP peers.

See Table 1 on page 153 for descriptions of the timers and their associated behaviors.

Table 15: Graceful Restart Timers

Timer	Description
Restart time	The restartTime indicates how long the pod waits for a graceful restart capable neighbor to re- establish BGP peering. The default is 60 seconds.
	We recommend that you specify a nonzero value. A nonzero reset time advertise for graceful restart and long-lived graceful restart capabilities from peers.
	• bgpHelperEnable— Routes advertised by the BGP peer are kept for the duration of the restart time.
	• xmppHelperEnable—Routes advertised by XMPP peer are kept for the duration of the restart time.
LLGR restart time	The longLivedRestartTime indicates the amount of time LLGR retains stale routes.The default is 1800 seconds.
	• bgpHelperEnable— Routes advertised by BGP peers are kept for the duration of the LLGR timer.
	• xmppHelperEnable—Routes advertised by XMPP peers are kept for the duration of the LLGR timer.
	When graceful restart and LLGR are both configured, the duration of the LLGR timer is the sum of both timers.
End of RIB timer	The endOfRibTimeout timer specifies the amount of time a control node waits to remove stale routes from a vRouter agent's RIB. The default is 90 seconds.
	The EOR timer starts when this End of Config message is received by the vRouter agent. When the EOR timer expires, an EOR message is sent from the vRouter agent to the control node. The control node receives this EOR message then removes the stale routes which were previously advertised by the vRouter agent from it's RIB.

Verify Your Configuration

To verify your configuration, run the following command:

kubectl get gsc default-global-system-config -o yaml

The following output is an example of the GlobalSysemConfig.yaml file with graceful restart and LLGR configured:

```
kubectl get gsc default-global-system-config -o yaml
apiVersion: core.contrail.juniper.net/v4
kind: GlobalSystemConfig
metadata:
 annotations:
    conversion.globalsystemconfig.gracefulrestartparameters:
'{"BgpHelperEnable":true,"Enable":true,"EndOfRibTimeout":90,"LongLivedRestartTime":1800,"RestartT
ime":60,"XmppHelperEnable":true}'
    core.juniper.net/description: This cluster object defines all the global Contrail
      configurations. This object must be unique for a Contrail deployment.
    core.juniper.net/display-name: Default Global System Config
 creationTimestamp: "2023-05-02T19:01:23Z"
 generation: 25
 labels:
    back-reference.core.juniper.net/28c27a9ee0c01b57b940db85e38aef6526e506189cfa69d69b019349:
BGPRouter_contrail_tmallick-k8s-ctrl-2.englab.juniper.net
    back-reference.core.juniper.net/31b3717b8b83c3cedd435758e30860370ff90c20542563beb1fab793:
BGPRouter_contrail_tmallick-k8s-ctrl-1.englab.juniper.net
    back-reference.core.juniper.net/d2e220fd972a5acfc95a0cccaf8d973e97427606046a10f0b04297aa:
BGPRouter_contrail_tmallick-k8s-ctrl-3.englab.juniper.net
 name: default-global-system-config
  resourceVersion: "31673"
 uid: 3dfaefbc-a0e5-4e14-b6b3-73d03f09bf1b
spec:
 autonomousSystem: 64512
  bgpRouterReferences:
  - apiVersion: core.contrail.juniper.net/v2
    fgName:
    - default-domain
    - contrail
    - ip-fabric
    - default
    - jdoe-k8s-ctrl-1.englab.juniper.net
   kind: BGPRouter
   name: jdoe-k8s-ctrl-1.englab.juniper.net
    namespace: contrail
    uid: 698aa03c-6c5c-4e7a-bb75-b89baef75ea6
  - apiVersion: core.contrail.juniper.net/v2
    fqName:
```

```
- jdoe-k8s-ctrl-2.englab.juniper.net
 name: jdoe-k8s-ctrl-2.englab.juniper.net
 uid: 8afddddb-56ad-44fb-95a5-1cfe0fc10361
- apiVersion: core.contrail.juniper.net/v2
```

```
- default
- jdoe-k8s-ctrl-3.englab.juniper.net
kind: BGPRouter
name: jdoe-k8s-ctrl-3.englab.juniper.net
namespace: contrail
```

uid: af2f0faa-31f6-4869-8f16-ad2ba4d4c013

```
enable4bytesAS: true
```

- default-domain

kind: BGPRouter

fqName:

- contrail - ip-fabric

namespace: contrail

- default-domain

- contrail - ip-fabric - default

fqName:

```
- default-global-system-config
 gracefulRestartParameters:
   bgpHelperEnable: true
   enable: true
    endOfRibTimeout: 90
   longLivedRestartTime: 1800
   restartTime: 60
   xmppHelperEnable: true
 ibgpAutoMesh: true
status:
```

```
observation: ""
```

SEE ALSO

Configuring Graceful Restart and Long-Lived Graceful Restart in Contrail Networking Configuring Graceful Restart and Long-Lived Graceful Restart (Tungsten Fabric)

156

vRouter Interface Health Check

SUMMARY

In Juniper® Cloud-Native Contrail Networking (CN2) Release 22.3, a new health-check custom resource object is introduced that associates the virtual machine interface (VMI) to the pod creation and update workflow. The health-check resource is a namespace-scoped resource.

IN THIS SECTION

- vRouter Interface Health Check
 Overview | 156
- Create a Health-Check Object | 156
- Health-Check Process | 162

vRouter Interface Health Check Overview

The Contrail vRouter agent provides the health-check functionality. You can associate a ping or HTTP health check to an interface. If the health check fails, the interface is set as administratively down and associated routes are withdrawn. Those settings are based on the timers and intervals configured in the health-check object. Health check traffic continues to be transmitted in an administratively down state to allow for an interface to recover.

Create a Health-Check Object

NOTE: These two attributes (targetIpList and targetIpAll) related to VMI health check are not supported in CN2 Release 22.3. These two attributes will be supported in a future release.

To create a health-check object:

 In the deployment manifests from the Contrail Networking download page, use the hc.yaml file (shown below) for the YAML definition for health-check objects. The same folder also includes the hc_pod.yaml, which has the YAML definition to associate the health-check object with VMI by means of pod definitions. Sample hc.yaml file:

```
apiVersion: v1
kind: Namespace
metadata:
  name: healthcheck
---
apiVersion: core.contrail.juniper.net/v1alpha1
kind: ServiceHealthCheck
metadata:
  name: ping-hc
  namespace: healthcheck
spec:
  serviceHealthCheckProperties:
    delay: 2
    enabled: true
    healthCheckType: end-to-end
    maxRetries: 5
    monitorType: PING
    timeout: 5
---
apiVersion: core.contrail.juniper.net/v1alpha1
kind: ServiceHealthCheck
metadata:
  name: bfd-hc
  namespace: healthcheck
spec:
  serviceHealthCheckProperties:
    delay: 2
    enabled: true
    healthCheckType: link-local
    maxRetries: 5
    monitorType: BFD
    timeout: 5
apiVersion: core.contrail.juniper.net/v1alpha1
kind: ServiceHealthCheck
metadata:
  name: http-hc
  namespace: healthcheck
spec:
  serviceHealthCheckProperties:
```

```
delay: 2
enabled: true
healthCheckType: end-to-end
maxRetries: 5
monitorType: HTTP
timeout: 5
httpMethod: GET
expectedCodes: 200
urlPath: /health
```

2. Complete the parameters to define the health check. Table 16 on page 158 lists and explains the parameters.

Field	Description
Delay	The delay, in seconds, to repeat the health check.
DelayUsecs	Time in micro seconds at which the health check is repeated.
Enabled	Indicates that the health check is enabled. The default is False.
ExpectedCodes	When the monitor protocol is HTTP, the expected return code for HTTP operations must be in the range of 200-299.
HealthCheckType	Indicates the health-check type: link-local, end-to- end, segment, vn-ip-list, and end2end. The default is link-local.In both link-local and end-to-end modes, the health check is executed for the pod on the vRouter where the VMI is running.
HttpMethod	When the monitor protocol is HTTP, the type of HTTP method used is GET.
MaxRetries	The number of retries to attempt before declaring a health down instance .

Table 16: Health-Check Configurable Parameters

Field	Description
MonitorType	The protocol type to be used is PING, BFD, or TCP.
targetIpList	NOTE : Attribute is configurable but not supported in CN2 Release 22.3. This attribute will be supported in a future release.
targetIpAll	NOTE : Attribute is configurable but not supported in CN2 Release 22.3. This attribute will be supported in a future release.
Timeout	The number of seconds to wait for a response.
TimeoutUsecs	Time in micro seconds to wait for response.
UrlPath	Must be a valid URL, such as http://172.16.0.1/ < <i>path</i> >. The IP address can be a placeholder that will be replaced with the pod link-local IP address or metadata IP address.

Table 16: Health-Check Configurable Parameters (Continued)

Following is an abstract Golang schema for the health-check resource:

```
type ServiceHealthCheckProperties struct {
                      *int
   Delay
   DelayUsecs
                      *int
   Enabled
                      boolean
                      int // Only for http
   ExpectedCodes
   HealthCheckType
                       (link-local | end-to-end |segment | vn-ip-list) //end2end
   HttpMethod
                       *string
   MaxRetries
                       int
   MonitorType
                       (ping | BFD |TCP)
   Timeout
                       int
   TimeoutUsecs
                       int
}
type ServiceHealthCheckSpec struct {
    ServiceHealthCheckProperties *ServiceHealthCheckProperties
```

```
type ServiceHealthCheckStatus struct {
   uuid *string
type ServiceHealthCheck struct {
   <kube_specific_objetcs>
            ServiceHealthCheckSpec
   Spec
   Status ServiceHealthCheckStatus
```

}

}

}

The YML representation for the Golang schema is:

```
. . .
apiVersion: core.contrail.juniper.net/v1alpha1
kind: ServiceHealthCheck
metadata:
  name: ping-hc
  namespace: healthcheck
spec:
  serviceHealthCheckProperties:
    delay: 2
    enabled: true
    healthCheckType: end-to-end #valid values are link-local|end-to-end|segment|vn-ip-list
    maxRetries: 5
    monitorType: PING #valid are PING|HTTP|BFD
    timeout: 5
. . .
```

3. Link the health-check object to the VMI by means of the pod annotation reference value core.juniper.net/health-check. The default behavior is to associate the health check with the primary interface.

apiVersion: v1 kind: Pod metadata: name: hc_pod namespace: hc_ns

```
annotations:
    core.juniper.net/health-check: '[{"name": "ping-hc", "namespace": "healthcheck"}]'
spec:
    <>
```

4. (Optional) To link the health check with multiple interfaces, attached to a different Network Attachment Definition (NAD) or virtual network (VN), you can refer the health check object within the cni-args section. Following is an example of configured cni-args in annotations.

```
apiVersion: v1
kind: Pod
metadata:
  name: hc_pod
  namespace: hc_ns
  annotations:
          k8s.v1.cni.cncf.io/networks: |
      Ε
        {
          "name": "hc-vn",
          "namespace": "healthcheck",
          "cni-args": {
            "core.juniper.net/health-check": "[{\"name\": \"ping-hc\", \"namespace\":
\"healthcheck\"}]"
          }
        }
      ]
spec:
  <>
```

Existing VMI objects will have a new field to reference the HealthCheck object.

```
type VirtualMachineInterfaceStatus struct {
    <existing_vmi_status_attributes>
    ServiceHealthCheckReference *ResourceReference
}
type VirtualMachineInterface struct {
    <other VMI attributes>
    Status VirtualMachineInterfaceStatus
}
```

For the PING or HTTP monitoring-based health check, the minimum interval is **1second**. If you need a sub-second level health check for critical applications, you can opt for the BFD-based monitoring type.

Health-Check Process

The Contrail vRouter agent is responsible for providing the health-check service. The agent spawns a health-check probe process to monitor the status of a service hosted on the same compute node. Then the process updates the status to the vRouter agent.

The vRouter agent acts on the status provided by the script to withdraw or restore the exported interface routes. The agent is responsible for providing a link-local metadata IP address for allowing the script to communicate with the destination IP address from the underlay network, using appropriate NAT translations. In a running system, this information is displayed in the vRouter agent introspect at:

http://<compute-node-ip>:8085/Snh_HealthCheckSandeshReq?uuid=

Kubernetes Ingress Support

SUMMARY

Cloud-Native Contrail[®] Networking[™] supports the Container Network Interface (CNI) for integration with Kubernetes. This topic provides an overview of Kubernetes ingress service implementation in Cloud-Native Contrail Networking. This topic also contains a list of validated Kubernetes ingress controllers and their installation instructions.

IN THIS SECTION

- Ingress Controller Overview | 162
- Validated Ingress Controllers | 164
- NGINX Ingress Controller | 165
- HAProxy Ingress Controller | 165
- Contour Ingress Controller | 165

Ingress Controller Overview

You must have a Kubernetes ingress controller for an ingress to function properly. An ingress controller receives traffic from outside a Kubernetes cluster and routes and load-balances that traffic to containers

within a cluster. Ingress controllers also manage egress traffic between services within a cluster and external services. Controllers automatically route traffic to containers depending on service requirements.

Ingress controllers deploy ingress resources. Ingress resources comprise rules that specify which inbound traffic connections reach which services (pods). Ingress resources, combined with ingress controllers, route Layer 7 traffic to containers in a cluster.

Here's an example of an NGINX ingress resource:

```
apiVersion: apps/v1
kind: Deployment
metadata:
  name: apple-app-echo
  namespace: ingress-nginx-test
spec:
  selector:
    matchLabels:
      app: apple-echo
  replicas: 1
  template:
    metadata:
      labels:
        app: apple-echo
    spec:
      containers:
      - name: apple-echo
        image: svl-artifactory.juniper.net/atom-docker/cn2/http-echo:latest
        args:
          - "-text=apple-echo"
```

Ingress resources contain spec fields such as type: NodePort and type: LoadBalancer. These service types determine a controller's traffic routing and forwarding behavior. For example, if you enter a NodePort in the type field, the control plane allocates a port from a range (default 30000–32767) of ports to your service.

Consider the following example:

apiVersion: v1 kind: Service metadata: name: envoy

```
namespace: projectcontour
 annotations:
spec:
 #externalTrafficPolicy: Local
  ports:
  - port: 80
   name: http
   protocol: TCP
    nodePort: 30080
    targetPort: 8080
  - port: 443
   name: https
   protocol: TCP
   targetPort: 8443
   nodePort: 30443
  selector:
   app: envoy
  type: NodePort
```

Some highlights from the example above include:

- selector: The label selector that determines which set of pods this service targets. In this example, this service selects any pod with the label app: envoy.
- port: The service port (80).
- targetPort: The actual port used by the application in the container (8080).
- nodePort: The port on the host of each node in the cluster that your service is exposed to (30080).

Different ingress controllers require different configurations. Review the documentation of your ingress controller for annotation, specification, and configuration information.

Validated Ingress Controllers

Cloud-Native Contrail Networking supports many ingress controllers. We've validated the following three popular third-party controllers for use with Cloud-Native Contrail Networking:

- NGINX
- HAProxy
- Contour

NGINX Ingress Controller

NGINX is an open-source HTTP server that also functions as a reverse proxy, load balancer, and IMAP or POP3 proxy server. The NGINX ingress controller is a Kubernetes controller that deploys an NGINX configuration using a ConfigMap resource. Other than endpoint-only changes, you must reload NGINX after any change to the configuration file occurs. This reload mechanism is powered by a lua-nginx-module. NGINX requires Kubernetes v1.22 or later.

NOTE: We support the NGINX ingress controller in environments using Cloud-Native Contrail Networking as the software-defined networking (SND) solution starting in Contrail Networking Release 21.4.

See the NGINX Ingress Controller installation guide for installation instructions. This guide contains instructions for installing NGINX using several different methods (Docker, minikube, Helm).

HAProxy Ingress Controller

The HAProxy ingress controller provides TCP and HTTP routing and high availability (HA) load balancing. HAProxy offers features such as Runtime API, Data Plane API, and hitless reloads. These features excel in dynamic, high-traffic environments where users constantly deploy, configure, and terminate pods, services, and microservices. The HAProxy ingress controller v0.13 requires Kubernetes v1.19 or later.

NOTE: Starting in Contrail Networking Release 21.4, we support the HAProxy ingress controller in environments using Cloud-Native Contrail Networking as the SDN solution.

See the HAProxy Getting Started guide for installation instructions.

NOTE: You must use Helm to install and to configure the HAProxy ingress controller. See Installing Helm for more information.

Contour Ingress Controller

Contour ingress controller deploys an Envoy proxy as a reverse proxy and load balancer. Envoy is a Layer 7 bus network for proxy services and communication. Envoy is deployed as a self-contained proxy

instead of a library. As a result, any application can access Envoy's load-balancing features. This implementation is suitable for a distributed system such as a Kubernetes cluster. Other benefits of Contour include:

- Easy installation and integration of Envoy.
- Stable ingress support in multi-team Kubernetes clusters.
- Dynamic updates and ingress configuration without interruptions or dropped connections.

Contour requires Kubernetes 1.16 or later. You must enable role-based access control (RBAC) in your cluster for Contour to function properly.

NOTE: Starting in Contrail Networking Release 21.4, we support the Contour ingress controller in environments using Cloud-Native Contrail Networking as the SDN solution.

See the Getting Started guide for instructions about how to install the Contour ingress controller. This guide contains instructions about how to install and configure Contour with either kind or Docker. Install Contour after installing kind or Docker to run your ingress controller.

Deploy VirtualNetworkRouter in Cloud-Native Contrail Networking

SUMMARY

Cloud-Native Contrail[®] Networking[™] supports the VirtualNetworkRouter (VNR) construct. This construct provides connectivity between VirtualNetworks.

IN THIS SECTION

- VirtualNetworkRouter Overview | 167
- VirtualNetworkRouter Use Cases | 168
- Mesh Use Cases | 168
- Hub-spoke Use Cases | 168
- Mesh VNR That Connects Two or More Virtual Networks in the Same Namespace | 169

Namespace to an Existing Mesh-Type VNR | 170 Two Mesh VNRs in the Same Namespace | 171 Two Mesh VNRs with Different Namespaces | 172 Hub and Spoke VNRs in the Same Namespace | 173 Hub and Spoke VNRs in Different Namespaces | 174 Same Virtual Networks Under Multiple VNRs | 175 Use Case Explanation | 175 Standard Use Case: Single VNR Connecting Two Virtual Networks | 176 Update Use Case: Single VNR Connecting Two Additional Virtual Networks | 179 VirtualNetworkRouter Configuration | 183 API Type (Schema) | 183 Mesh VNR | 184 Spoke VNR | 185 Hub VNR | 185

Add New Virtual Networks Within the Same

VirtualNetworkRouter Overview

Typically, VirtualNetwork (VN) traffic is isolated to maintain tenant separation. In Cloud-Native Contrail Networking (CN2), VirtualNetworkRouter (VNR) performs route leaking. Route leaking establishes connectivity between VirtualNetworks by importing routing instances (RI) and the routing tables associated with these instances. As a result, devices in one routing table can access resources from devices in another routing table.

The VNR provides connectivity for the following two common network models:

• Mesh: Pods in all connected VirtualNetworks communicate with each other.

• Hub-spoke: VirtualNetworks connect to two different VNR types (spoke, hub). VirtualNetworks connected to spoke-type VNRs communicate with VirtualNetworks connected to hub-type VNRs and vice versa. VirtualNetworks connected to spoke VNRs cannot communicate with other VirtualNetworks attached to spoke VNRs.

VNR is a Kubernetes construct deployed within CN2.

VirtualNetworkRouter Use Cases

The following examples are common use cases that demonstrate the functionality of VNR in CN2.


Mesh Use Cases

- "Mesh VNR That Connects Two or More Virtual Networks in the Same Namespace" on page 169
- "Add New Virtual Networks Within the Same Namespace to an Existing Mesh-Type VNR" on page 170
- "Two Mesh VNRs in the Same Namespace" on page 171
- "Two Mesh VNRs with Different Namespaces" on page 172

Hub-spoke Use Cases

- "Hub and Spoke VNRs in the Same Namespace" on page 173
- "Hub and Spoke VNRs in Different Namespaces" on page 174
- "Same Virtual Networks Under Multiple VNRs" on page 175


Mesh VNR That Connects Two or More Virtual Networks in the Same Namespace



- **1.** Figure-1: The user creates VN1 and VN2 in namespace-1. Pods in VN1 cannot connect to pods in VN2. This is the default behavior of VirtualNetworks in CN2.
- **2.** Figure-2: The user defines a VNR of type mesh that selects VN1 and VN2. This VNR allows Pods in VN1 to communicate with Pods in VN2 and vice-versa.
- **3.** Figure-3: Pods in VN1 connect to Pods in VN2. The route-target of VNR is importExported to both VirtualNetworks.


"Back to VirtualNetworkRouter Use Cases" on page 168

Add New Virtual Networks Within the Same Namespace to an Existing Mesh-Type VNR



- 1. Figure-1: Two VirtualNetworks (VN1, VN2) connect to VNR in namespace-1.
- 2. Figure-2: The user creates two new VirtualNetworks (VN3, VN4).
- **3.** Figure-3: VN3 and VN4 connect to VNR. As a result, all VirtualNetworksconnected to the VNR receive connectivity.

"Back to VirtualNetworkRouter Use Cases" on page 168




Two Mesh VNRs in the Same Namespace

- **1.** Figure 1 and Figure 2: VNR-web and VNR-db of type mesh already exist in namespace-1. Only VNRs connected to respective VNRs communicate with each other.
- 2. Figure 1 and Figure 2: VNR-web and VNR-db communicate with each other.
- 3. Figure 3: All VirtualNetworks connected to both VNR-web and VNR-db communicate with each other.

"Back to VirtualNetworkRouter Use Cases" on page 168


Two Mesh VNRs with Different Namespaces




- **1.** Figure 1: VNR-web selects VN1 and VN2. Pods in VN1 and VN2 communicate with each other. VN1 and VN2 cannot communicate with VN3 or VN4.
- **2.** Figure 2: VNR-db selects VN3 and VN4. Pods in VN3 and VN4 communicate with each other. VN3 and VN4 cannot communicate with VN1 or VN2.
- **3.** Figure 3: The user updates VNR-web to select VNR-db.
- **4.** Figure 3: The user updates VNR-db to select VNR-web.
- **5.** Figure 3: Since two VNRs select each other, VNR-web's RT (route target) is added to VN3 and VN4. VNR-db's RT is added to VN1 and VN2. Pods in VN1, VN2, VN3, and VN4 communicate with each other.

NOTE: VNRs select VNs based on matchExpression labels in a virtualNetworkSelector spec. For example, in the illustration above, VNR-web in namespace-1 selects VN1 and VN2 based on the label vn: web from namespace-1. A virtualNetworkSelector only looks for matching labels within it's own namespace.

"Back to VirtualNetworkRouter Use Cases" on page 168






• Figure-1: Pods in VN1 cannot communicate with pods in VN2. VN1 and VN2 cannot communicate with VN3.

- Figure-2: The user creates a VNR of type "spoke" and "hub." VNR-spoke and VNR-hub import each other's RTs.
- Figure-3: VNR-spoke and VNR-hub's RTs are added to VN1, VN2, and VN3 because they import each others' RTs. As a result, pods in VN1 and VN2 communicate with VN3. Pods in VN1 and VN2 cannot communicate with each other.

"Back to VirtualNetworkRouter Use Cases" on page 168


Hub and Spoke VNRs in Different Namespaces



• Figure 1 through Figure 3 are the same as "Hub and Spoke VNRs in the Same Namespace" on page 173, except that VNR-spoke and VNR-hub operate in different namespaces.

"Back to VirtualNetworkRouter Use Cases" on page 168





- Figure 1: Pods in VN1 and VN2 cannot communicate with each other. Also resources on VN3, VN4 can communicate with each other.
- Figure 2: You create a VNR-spoke by selecting VN1 and VN2. You create a VNR-hub by selecting VN3 and VN4. You create a VNR-mesh by selecting VN3 and VN4.
- Figure 3: VNR-spoke ensures that VN1 and VN2 cannot communicate each other, VNR-hub lets VN1 and VN2 reach VN3 and VN4, and VNR-mesh enables communication between VN3 and VN4.

"Back to VirtualNetworkRouter Use Cases" on page 168

Use Case Explanation

This section comprises the following two VNR use cases along with end-to-end explanations of each use case:

- "Standard Use Case: Single VNR Connecting Two Virtual Networks" on page 176
- "Update Use Case: Single VNR Connecting Two Additional Virtual Networks" on page 179

Standard Use Case: Single VNR Connecting Two Virtual Networks

```
kind: Namespace
metadata:
  name: ns-single-mesh
 labels:
    ns: ns-single-mesh
spec:
  finalizers:
  - kubernetes
_ _ _
apiVersion: core.contrail.juniper.net/v1alpha1
kind: Subnet
metadata:
  namespace: ns-single-mesh
  name: subnet-1
  annotations:
    core.juniper.net/display-name: subnet_vn_1
spec:
 cidr: "10.10.1.0/24"
  defaultGateway: 10.10.1.254
---
apiVersion: core.contrail.juniper.net/v1alpha1
kind: Subnet
metadata:
  namespace: ns-single-mesh
  name: subnet-2
  annotations:
    core.juniper.net/display-name: subnet_vn_2
spec:
 cidr: "10.10.2.0/24"
 defaultGateway: 10.10.2.254
---
apiVersion: core.contrail.juniper.net/v1alpha1
kind: VirtualNetwork
metadata:
  namespace: ns-single-mesh
  name: vn-1
  annotations:
    core.juniper.net/display-name: vn-1
```

apiVersion: v1

```
labels:
    vn: web
spec:
 v4SubnetReference:
   apiVersion: core.contrail.juniper.net/v1alpha1
   kind: Subnet
   namespace: ns-single-mesh
   name: subnet-1
---
apiVersion: core.contrail.juniper.net/v1alpha1
kind: VirtualNetwork
metadata:
 namespace: ns-single-mesh
 name: vn-2
 annotations:
   core.juniper.net/display-name: vn-2
 labels:
    vn: web
spec:
 v4SubnetReference:
   apiVersion: core.contrail.juniper.net/v1alpha1
   kind: Subnet
   namespace: ns-single-mesh
   name: subnet-2
- -
apiVersion: core.contrail.juniper.net/v1alpha1
kind: VirtualNetworkRouter
metadata:
 namespace: ns-single-mesh
 name: vnr-1
 annotations:
   core.juniper.net/display-name: vnr-1
 labels:
     vnr: web
spec:
 type: mesh
 virtualNetworkSelector:
   matchExpressions:
      - key: vn
            operator: In
            values:
            - web
_ _ _
```

```
apiVersion: v1
kind: Pod
metadata:
 name: pod-vn-1
  namespace: ns-single-mesh
  annotations:
    k8s.v1.cni.cncf.io/networks: vn-1
spec:
  affinity:
    nodeAffinity:
      requiredDuringSchedulingIgnoredDuringExecution:
        nodeSelectorTerms:
        - matchExpressions:
          - key: agent-mode
            operator: NotIn
            values:
            - dpdk
  containers:
  - name: pod-vn-1
    image: svl-artifactory.juniper.net/atom-docker/cn2/bazel-build/dev/google-containers/toolbox
    command: ["bash","-c","while true; do sleep 60s; done"]
    securityContext:
      privileged: true
    imagePullPolicy: IfNotPresent
  restartPolicy: OnFailure
- - -
apiVersion: v1
kind: Pod
metadata:
 name: pod-vn-2
  namespace: ns-single-mesh
  annotations:
    k8s.v1.cni.cncf.io/networks: vn-2
spec:
  affinity:
    nodeAffinity:
      requiredDuringSchedulingIgnoredDuringExecution:
        nodeSelectorTerms:
        - matchExpressions:
          - key: agent-mode
            operator: NotIn
            values:
            - dpdk
```

```
containers:
- name: pod-vn-2
image: svl-artifactory.juniper.net/atom-docker/cn2/bazel-build/dev/google-containers/toolbox
command: ["bash","-c","while true; do sleep 60s; done"]
securityContext:
    privileged: true
imagePullPolicy: IfNotPresent
restartPolicy: OnFailure
```

This use case comprises the following:

- Two VirtualNetworks (vn-1 and vn-2) in namespace ns-single-mesh. Both virtual networks have the label vn: web. Each VirtualNetwork contains a single pod. The VirtualNetwork vn-1 contains pod-vn-1. The VirtualNetwork vn-2 contains pod-vn-2.
- A type: mesh VNR with the name vnr-1. This VNR establishes connectivity between the two VirtualNetworks using matchExpressions and vn: web. he VNR imports the RI and routing table of vn-1 to vn-2 and vice versa. Since vnr-1 is a mesh-type VNR, all pods in connected VirtualNetworks communicate with each other.

Update Use Case: Single VNR Connecting Two Additional Virtual Networks

```
apiVersion: v1
kind: Namespace
metadata:
   name: ns-single-mesh
   labels:
        ns: ns-single-mesh
spec:
    finalizers:
        kubernetes
----
apiVersion: core.contrail.juniper.net/v1alpha1
kind: Subnet
metadata:
   namespace: ns-single-mesh
   name: subnet-2
   annotations:
```

core.juniper.net/display-name: subnet_vn_1

```
spec:
 cidr: "10.10.3.0/24"
  defaultGateway: 10.10.3.254
---
apiVersion: core.contrail.juniper.net/v1alpha1
kind: Subnet
metadata:
  namespace: ns-single-mesh
  name: subnet-4
  annotations:
    core.juniper.net/display-name: subnet_vn_2
spec:
  cidr: "10.10.4.0/24"
 defaultGateway: 10.10.4.254
---
apiVersion: core.contrail.juniper.net/v1alpha1
kind: VirtualNetwork
metadata:
 namespace: ns-single-mesh
  name: vn-3
  annotations:
    core.juniper.net/display-name: vn-1
 labels:
    vn: db
spec:
  v4SubnetReference:
    apiVersion: core.contrail.juniper.net/v1alpha1
    kind: Subnet
    namespace: ns-single-mesh
    name: subnet-3
---
apiVersion: core.contrail.juniper.net/v1alpha1
kind: VirtualNetwork
metadata:
  namespace: ns-single-mesh
  name: vn-4
  annotations:
    core.juniper.net/display-name: vn-2
 labels:
    vn: middleware
spec:
  v4SubnetReference:
    apiVersion: core.contrail.juniper.net/v1alpha1
```

```
kind: Subnet
   namespace: ns-single-mesh
   name: subnet-4
apiVersion: core.contrail.juniper.net/v1alpha1
kind: VirtualNetworkRouter
metadata:
 namespace: ns-single-mesh
 name: vnr-2
 annotations:
   core.juniper.net/display-name: vnr-1
 labels:
     vnr: db
     vnr: middleware
spec:
 type: mesh
 virtualNetworkSelector:
   matchExpressions:
      - key: vn
            operator: In
            values:
            - db, middlware
---
apiVersion: v1
kind: Pod
metadata:
 name: pod-vn-3
 namespace: ns-single-mesh
 annotations:
   k8s.v1.cni.cncf.io/networks: vn-1
spec:
 affinity:
   nodeAffinity:
      requiredDuringSchedulingIgnoredDuringExecution:
        nodeSelectorTerms:
        - matchExpressions:
          - key: agent-mode
            operator: NotIn
            values:
            - dpdk
 containers:
  - name: pod-vn-3
```

image: svl-artifactory.juniper.net/atom-docker/cn2/bazel-build/dev/google-containers/toolbox

```
command: ["bash","-c","while true; do sleep 60s; done"]
    securityContext:
      privileged: true
    imagePullPolicy: IfNotPresent
  restartPolicy: OnFailure
- -
apiVersion: v1
kind: Pod
metadata:
 name: pod-vn-4
 namespace: ns-single-mesh
 annotations:
    k8s.v1.cni.cncf.io/networks: vn-2
spec:
 affinity:
   nodeAffinity:
      requiredDuringSchedulingIgnoredDuringExecution:
        nodeSelectorTerms:
        - matchExpressions:
          - key: agent-mode
            operator: NotIn
            values:
            - dpdk
 containers:
  - name: pod-vn-4
    image: svl-artifactory.juniper.net/atom-docker/cn2/bazel-build/dev/google-containers/toolbox
    command: ["bash","-c","while true; do sleep 60s; done"]
   securityContext:
      privileged: true
    imagePullPolicy: IfNotPresent
  restartPolicy: OnFailure
```

This use case is similar to the standard use case, except that in this use case the user updates the YAML file with an additional type: mesh VNR to connect two new VirtualNetworks (vn-3 and vn-4) in namespace ns-single-mesh. Note the following:

- The VNR shown has the name vnr-2 in namespace ns-single-mesh with matchExpressions: db, middlware.
- The VirtualNetwork vn-3 has the label vn: db, and vn-4 has the label vn: middleware.

As a result, vnr-2 imports the RI and routing table of vn-3 to vn-4 and vice versa.

VirtualNetworkRouter Configuration

The following section provides YAML configuration information for the following resources:

- "API Type (Schema)" on page 183
- "Mesh VNR" on page 184
- "Spoke VNR" on page 185
- "Hub VNR" on page 185

API Type (Schema)

```
type VirtualNetworkRouterSpec struct {
    // Common spec fields
    CommonSpec `json:",inline" protobuf:"bytes,1,opt,name=commonSpec"`
    // Type of VirtualNetworkRouter. valid types - mesh, spoke, hub
    Type VirtualNetworkRouterType `json:"type,omitempty" protobuf:"bytes,2,opt,name=type"`
    // Select VirtualNetworks to which this VNR's RT be shared
    VirtualNetworkSelector *metav1.LabelSelector `json:"virtualNetworkSelector,omitempty"
protobuf:"bytes,3,opt,name=virtualNetworkSelector"`
    // Import Router targets from other virtualnetworkrouters
    Import ImportVirtualNetworkRouter `json:"import,omitempty"
protobuf:"bytes,4,opt,name=import"`
}
type ImportVirtualNetworkRouter struct {
    VirtualNetworkRouters []VirtualNetworkRouterEntry `json:"virtualNetworkRouters,omitempty"
protobuf:"bytes,1,opt,name=virtualNetworkRouters"`
}
type VirtualNetworkRouterEntry struct {
    VirtualNetworkRouterSelector *metav1.LabelSelector
```

```
`json:"virtualNetworkRouterSelector,omitempty"
```

```
protobuf:"bytes,1,opt,name=virtualNetworkRouterSelector"`
```

```
NamespaceSelector *metav1.LabelSelector `json:"namespaceSelector,omitempty"
```

protobuf:"bytes,2,opt,name=namespaceSelector"`

}

Mesh VNR

```
apiVersion: core.contrail.juniper.net/v1alpha1
kind: VirtualNetworkRouter
metadata:
 namespace: frontend
 name: vnr-1
 annotations:
   core.juniper.net/display-name: vnr-1
 labels:
   vnr: web
   ns: frontend
spec:
 type: mesh
 virtualNetworkSelector:
   matchLabels:
     vn: web
 import:
   virtualNetworkRouters:
      - virtualNetworkRouterSelector:
          matchLabels:
            vnr: db
       namespaceSelector:
          matchLabels:
            ns: backend
```

The preceding YAML file is an example of a mesh VNR with the name vnr-1 in namespace frontend, with the labels vnr: web and ns: frontend. This VNR imports its route-target to any VNR in the namespace backend with matchLabel vnr: db.

Spoke VNR

```
kind: VirtualNetworkRouter
metadata:
 namespace: frontend
 name: vnr-1
 annotations:
   core.juniper.net/display-name: vnr-1
 labels:
    vnrgroup: spokes
   ns: frontend
spec:
 type: spoke
 virtualNetworkSelector:
   matchLabels:
     vngroup: spokes
 import:
   virtualNetworkRouters:
      - virtualNetworkRouterSelector:
          matchLabels:
            vnrgroup: hubs
        namespaceSelector:
          matchLabels:
            ns: backend
```

The preceding YAML file is an example of a spoke VNR with the name vnr-1 in namespace frontend with the labels vnrgroup: spokes and ns: frontend. This VNR imports its route-targets to any VNR in the namespace backend with matchLabel vnrgroup: hubs.

Hub VNR

```
apiVersion: core.contrail.juniper.net/v1alpha1
kind: VirtualNetworkRouter
metadata:
   namespace: backend
   name: vnr-2
   annotations:
      core.juniper.net/display-name: vnr-2
   labels:
```

```
vnrgroup: hubs
ns: backend
spec:
type: hub
virtualNetworkSelector:
matchLabels:
vngroup: hubs
import:
virtualNetworkRouters:
- virtualNetworkRouterSelector:
matchLabels:
vnrgroup: spokes
namespaceSelector:
matchLabels:
ns: frontend
```

The preceding YAML file is an example of a hub VNR with the name vnr-2 in the namespace backend with labels vnrgroup: hubs and ns: backend. This VNR imports its route-targets to any VNR in the namespace frontend with matchLabels vnrgroup: spokes.

Configure Inter-Virtual Network Routing Through Route Targets

SUMMARY

Cloud-Native Contrail® Networking[™] (CN2) supports inter-virtual network routing using route targets. Specify common route targets to route traffic between your virtual networks.

IN THIS SECTION

- Virtual Networks and Routing Instances Overview | **187**
- Route Target Overview | 187
- Enable Inter-Virtual Network Routing Through Route Targets with NAD | 188

Virtual Networks and Routing Instances Overview

A routing instance is a collection of routing tables, interfaces, and routing protocol parameters. The set of interfaces in a routing instance belongs to the routing tables, and the routing protocol parameters control the information in the routing tables. A single routing instance might have multiple routing tables —for example, unicast IPv4, unicast IPv6, and multicast IPv4 routing tables can exist in a single routing instance.

In virtual networking, a physical networking device might be split into multiple virtual routers, each with its own interfaces, routing instances, and associated virtual networks. Routing instances isolate traffic within a VirtualNetwork. If you want to route traffic between your virtual networks, you can define common route targets for those networks.

Route Target Overview

Route targets enable your virtual networks (namespaces) to exchange virtual routing and forwarding (VRF) routing tables in a Multiprotocol Label Switching (MPLS) configuration. A route target is a BGP Extended Communities Attribute that defines VPN membership. In other words, members of that VPN share all routes defined within an Extended Communities Attribute. You define the following two route targets in your VRF policy:

- Route-target import list: Defines a list of acceptable route targets for a VRF to import. When a
 provider edge (PE) router receives a route from another PE router, it compares the route targets to
 the route-target import list. Specifically, the PE router compares the route targets attached to each
 route against the route-target import list defined for each of its VRFs. If no new route target matches
 the route targets defined in the import list, the VRF rejects the route.
- Route-target export list: Defines a list of route targets attached to every route advertised to other PE routers in your VPN.

Depending on your network configuration, the import and export lists might be identical. Typically, you do the following:

- Allocate one route target extended-community value per VPN.
- Configure the import list and the export list to include the same information: the set of VPNs comprising the sites associated with the VRF.

For more complicated configurations like hub-and-spoke VPNs, the route-target import list and the route-target export list might not be identical.

Enable Inter-Virtual Network Routing Through Route Targets with NAD

Establish route-target communities by defining matching route targets in your VirtualNetwork resource. This enables you to route traffic between your virtual networks (namespaces). Add route targets to a VirtualNetwork resource object using the Network Attachment Definition (NAD).

The Network Attachment Definition (NAD) is a Custom Resource Definition (CRD) specified by the Kubernetes Network Plumbing Working Group. This CRD, NAD, defines how a pod attaches to a logical (virtual) or physical network that the NAD object refers to. In other words, the NAD object contains networking information (namespace, subnet, routing, interface) for a pod in relation to a network. You can define the following options for your VirtualNetwork resource in the annotations of a NAD YAML file:

- ipamV4Subnet (optional): Specifies an IPv4 CIDR subnet for your VirtualNetwork.
- ipamV6Subnet (optional): Specifies an IPv6 CIDR subnet for your VirtualNetwork.
- routeTargetList (optional): Lists import and export route targets.
- importRouteTargetList (optional): Lists route targets used as imports.
- exportRouteTargetList (optional): Lists route targets used as exports.
- fabricSNAT (optional): Toggles connectivity to the underlay network by port mapping. The default setting is false.

Additionally, the NAD-Controller monitors NAD object-creation events and creates and updates a VirtualNetwork accordingly. The juniper.net/networks-status annotation of the NAD updates success or error events during VirtualNetwork creation.

NOTE: If you do not specify a juniper.net/networks annotation, then Cloud-Native Contrail Networking treats the NAD resource as a third-party resource. Cloud-Native Contrail Networking does not create Contrail resources (such as VirtualNetwork and Subnet).

The following example shows a NAD YAML file with several annotations defined:

Example 1:

```
apiVersion: "k8s.cni.cncf.io/v1"
kind: NetworkAttachmentDefinition
metadata:
   name: nasa-network
   namespace: nm1
   annotations:
```

```
juniper.net/networks: '{
    "ipamV4Subnet": "172.16.10.0/24",
    "ipamV6Subnet": "2001:db8::/64",
    "routeTargetList": ["target:23:4561"],
    "importRouteTargetList": ["target:10.2.2.2:561"],
    "exportRouteTargetList": ["target:10.1.1.1:561"],
    "fabricSNAT": true
    }'
    juniper.net/networks-status: # should be updated by Kube-Manager to status of NAD object.
spec:
    config: '{
        "cniVersion": "0.3.1",
        "name": "nasa-network",
        "type": "contrail-k8s-cni"
}'
```

The NAD-Controller automatically updates the VirtualNetwork resource after you apply your NAD YAML file.

The following example shows a VirtualNetwork resource with several route-target options defined:

Example 2:

```
apiVersion: core.contrail.juniper.net/v1alpha1
kind: VirtualNetwork
metadata:
 namespace: project-sample
 name: virtualnetwork-sample
spec:
 routeTargetList:
   - target:23:4561
    - target:21L:7000
    - target:871:6540
  importRouteTargetList:
    - target:10.2.2.2:561
    - target:97:651
 exportRouteTargetList:
    - target:10.1.1.1:561
    - target:97:651
```

After establishing your desired network annotations, you can create a pod with custom interfaces that are attached to networks with shared route targets. These networks route traffic between one another as a result of the shared route targets defined in the NAD and VirtualNetwork objects.

The following example shows a pod YAML file with custom interfaces derived from the annotations in Example 1.

Example 3:

```
apiVersion: v1
 kind: Pod
 metadata:
    name: nasa-pod-1
    annotations:
      k8s.v1.cni.cncf.io/networks: |-
       Ε
         {
            "name": "nasa-network1",
            "namespace": "nasa-ns",
            "cni-args":null,
            "ips":["172.16.20.42"],
            "mac":"de:ad:00:00:be:ef",
            "interface": "tap1"
         },
         {
            "name": "nasa-network2",
            "namespace": "nasa-ns",
            "cni-args":null,
            "ips":["172.16.21.42"],
            "mac":"de:ad:00:00:be:ee",
            "interface":"tap2"
          }
        ]
```

Note that the two interfaces shown in the preceding code example (nasa-network1 and nasa-network2) attach to different networks. As a result of NAD functionality, you can route traffic between these networks.

RELATED DOCUMENTATION

Understanding Route Targets Routing Instances Overview

Virtual Routing Instances

Configure IPAM for Pod Networking

SUMMARY

Cloud-Native Contrail[®] Networking[™] release 22.1 supports IP address management (IPAM) for pods and services. Configure a Subnet resource to facilitate IP address allocation.

IN THIS SECTION

- IPAM in Cloud-Native Contrail
 Networking | 191
 SubnetPool Overview | 191
- Subnet Overview | 192
- VirtualNetwork Overview | 193
- BGP as a Service Session IP Addresses
 Overview | 194

IPAM in Cloud-Native Contrail Networking

Cloud-Native Contrail Networking introduces the Subnet and SubnetPool resources for the purpose of IPAM for pods and services. Each Subnet has an associated SubnetPool. These resources enable you to configure IPv4 and IPv6 address allocation in your cluster. A VirtualNetwork references a Subnet resource to determine available subnets for new pods and services. Multiple VirtualNetworks can reference the same Subnet. The Subnet resource is translated into IPAM and consumed by the control node and vRouter agent.

SubnetPool Overview

The SubnetPool manages a pool of addresses from which Subnets are allocated. When a request for an IP address occurs, that IP address is allocated from a virtual network's associated SubnetPool. CIDR parameters (prefix length, capacity, range) for IP address allocation are determined when a SubnetPool is created. You can allocate additional prefixes if you exhaust a SubnetPool.

Consider the following SubnetPool example:

kparmar-mbp:cn2 kparmar\$ kubectl get pool subnet-id-pool-Subnet-contrail-k8s-kubemanager-ocprdang-g8roaw-contrail-default-podnetwork-pod-v4-subnet -oyaml

apiVersion: idallocator.contrail.juniper.net/v1alpha1

```
capacity: 262144
count: 157
kind: Pool
max: 262143
metadata:
    creationTimestamp: null
    name: subnet-id-pool-Subnet-contrail-k8s-kubemanager-ocp-rdang-q8roaw-contrail-default-
podnetwork-pod-v4-subnet
reserved:
    q
    262143
    1
```

The capacity parameter denotes the total number of possible IDs in the pool. The count parameter denotes the number of used IDs in the pool. The max parameter denotes the maximum number of IDs available to be allocated from the pool. A given ID maps to an IP address in the Subnet pool.

Subnet Overview

The Subnet is a block of IP addresses and the configurations associated with those addresses. A Subnet is based on a single address family (IPv4, IPv6) at a time. You must create separate IPv4 and IPv6 Subnets. If you do not specify a SubnetPool, the Subnet functions as Contrail Classic IPAM. This means that the Subnet is isolated to a single namespace.

Consider the following Subnet spec example:

apiVersion: v13 kind: Subnet metadata:

```
name: default-servicenetwork-pod-v4-subnet
namespace: contrail-k8s-kubemanager-ocp
spec:
cidr: 10.128.0.0/16
defaultGateway: 10.128.0.1
ranges:
- ipRanges:
- from: 10.128.0.0
to: 10.128.0.255
key: contrail-k8s-kubemanager-ocp-user-4yu0qk-ocp-user-4yu0qk-ctrl-1
```

The cidr and defaultGateway parameters are the main parameters that define a Subnet resource. The cidr parameter determines the range of IPs available for allocation in that Subnet. The defaultGateway parameter defines the IP address of the defaultGateway for the Subnet. Specifying a defaultGateway address is optional. If you do not specify a defaultGateway address, it is automatically set as the first IP address in the Subnet.

A Kubernetes node configuration can have a podCIDR configuration parameter. The podCIDR is a subset of the default-podnetwork-subnet. When the podCIDR is present, the IP address of any pod created on that node will have an IP address allocated from the podCIDR. If no podCIDR is present, all of the IP addresses in the CIDR of the Subnet can be allocated for the node. The podCIDR can also reference a wildcard key. In the example, IP address allocation requests choose from IPs 10.128.0.0 to 10.128.0.255 as long as the requesting pod is created on the node with the key contrail-k8s-kubemanager-ocp-kparmar-4yu0qk-ocp-kparmar-4yu0qk-ctrl-1.

Alternatively, you can define a ranges parameter . The ranges parameter defines a list of IPs available for allocation. The ranges parameter overrides the CIDR parameter when it is present in a spec. The ranges parameter does not override the podCIDR parameter.

VirtualNetwork Overview

Cloud-Native Contrail Networking updates the VirtualNetwork resource to be compatible with IPAM implementation. Consider the following example:

```
apiVersion: v3
kind: VirtualNetwork
metadata:
   namespace: contrail
   name: virtualnetwork-sample
spec:
   v4SubnetReference:
```

```
apiVersion: core.contrail.juniper.net/v1
kind: Subnet
namespace: contrail
name: v4subnet
v6SubnetReference:
apiVersion: core.contrail.juniper.net/v1
kind: Subnet
namespace: contrail
name: v6subnet
```

Note the separate Subnet references for the IPv4 address family and the IPv6 address family. You cannot update the Subnet reference of a VirtualNetwork through the entire lifecycle of that VirtualNetwork.

BGP as a Service Session IP Addresses Overview

BGP as a Service (BGPaaS) enables the establishment of a BGP session between a control node to a workload or pod's IP address. You can create a Subnet with the DisableBGPaaSIPAutoAllocation flag set to **false** or **true**. When you set the DisableBGPaaSIPAutoAllocation to **false**, the following occurs:

- No IP address is allocated for BGPaaSPrimaryIP or BGPaaSSecondaryIP immediately. These IPs are only allocated (within Subnet CIDR range) when the first BGPAsAService is configured within the network of this Subnet.
- When you delete all of the BGPAsAService resources associated with a Subnet, the IP addresses assigned to BGPaaSPrimaryIP and BGPaaSSecondaryIP are released from the pool and set to empty values. These addresses are re-allocated from the pool when a BGPAsAService is configured again.

When you set the DisableBGPaaSIPAutoAllocation flag to **true**, the following occurs:

- You are able to use user-defined values for the BGPaaSPrimaryIP and BGPaaSSecondaryIP fields. These IP fields are mandatory and cannot be left empty. User-defined values for these fields are also reserved in the Subnet pool.
- The IP addresses used for BGPaaSPrimaryIP and BGPaaSSecondaryIP still remain reserved in the Subnet pool even if no BGPAsAService is configured or if all BGPAsAService resources are deleted.

When you change the DisableBGPaaSIPAutoAllocation field from **false** to **true**, BGPaaSPrimaryIP and BGPaaSSecondaryIP become mandatory fields. If the IPs were auto allocated before changing this flag from **false** to **true**, then those IPs are released from the pool and new user-provided IPs are reserved in the pool.

When you change DisableBGPaaSIPAutoAllocation from true to false the following occurs:

- If no BGPAsAService is configured within the Subnet, BGPaaSPrimaryIP and BGPaaSSecondaryIP values are released from the pool and these fields become empty.
- If at least one BGPAsAService is configured, no change happens to the existing values of BGPaaSPrimaryIP and BGPaaSSecondaryIP.

For more information about BGP as a Service (BGPaaS), see the "Enable BGP as a Service" on page 291 section.

Enable VLAN Subinterface Support on Virtual Interfaces

SUMMARY

Virtualized Network Function (VNF) and Containerized Network Function (CNF) workloads often require multiple virtual network services on a single interface. Cloud-Native Contrail[®] Networking[™] supports VLAN subinterfaces on virtual interfaces.

IN THIS SECTION

- VLAN Subinterface Overview | 195
- API Changes | **196**
- Network Definition Changes | 196
- Configuration Use Cases | 198
- Valid Configuration 1: One Parent, One Subinterface: | 198
- Valid Configuration 2: One Parent, Multiple Subinterfaces: | **199**
- Valid Configuration 3: Multiple Parents, Multiple Subinterfaces: | **200**
- Invalid Configuration 1: Multiple Interfaces on Same Network: | **201**
- Invalid Configuration 2: Two Interfaces with Same interfacegroup but no VLAN | 202

VLAN Subinterface Overview

A VLAN subinterface is a logical division of a virtual (or physical) interface at the network level. VLAN subinterfaces are Layer 3 interfaces that receive and forward 802.1Q VLAN tags. You can assign

multiple VLAN tags to a single virtual interface. When a packet arrives at that interface, the packet's associated VLAN tags designate which VLAN the packet routes to. You can use VLAN subinterfaces to route traffic to multiple VLANs for your services.

API Changes

This section provides information about API calls that occur when configuring a VLAN subinterface.

When configuring VLAN subinterfaces in Cloud-Native Contrail Networking, Kubernetes updates the VirtualMachineInterface field with new properties, or VLAN tags. After an update occurs, the VirtualMachineInterface object references other VirtualMachineInterface objects based on existing VLAN tags.

NOTE: Cloud-Native Contrail Networking defines the properties field from Contrail Classic as virtualMachineInterfaceProperties.

Network Definition Changes

This section provides information about the network definition enhancements necessary when creating a subinterface for a virtual interface within a pod.

In kube-manager, the PodController watching for pod events reads the network definition applied to it. Kubemanager parses each network selection element and creates an associated VMI (virtual machine interface). Parent VMIs are the network elements with only the net.juniper.contrail.interfacegroup tag attached in the YAML file. Subinterfaces are the network elements with the net.juniper.contrail.interfacegroup and net.juniper.contrail.vlan tags attached in the YAML file.

The following two tags enhance the network definition in the cni-args section:

- net.juniper.contrail.interfacegroup
 - Interface Group groups two or more interfaces.
 - The parent interface is the network selection element associated with only this tag.
 - The subinterface is the network selection element associated with this tag and a VLAN tag.
- net.juniper.contrail.vlan

Specifies the VLANID on the subinterface.

A VLAN subinterface belongs to its parent interface. Users must specify the namespace to which the subinterface attaches. Consider the following example:

Example

.

```
apiVersion: v1
kind: Pod
metadata:
 name: my-pod
 namespace: my-namespace
 annotations:
    k8s.v1.cni.cncf.io/networks: |
      Ε
        {
          "name": "parent-vn",
          "namespace": "vn-ns",
          "cni-args": {
            "net.juniper.contrail.interfacegroup": "eth1"}
          . . .
        },
        {
          "name": "subitf-vn",
          "namespace": "vn-ns",
          "cni-args": {
            "net.juniper.contrail.vlan": 100,
            "net.juniper.contrail.interfacegroup": "eth1"},
          . . .
        },
  . . .
```

The preceding example shows specified pod annotations for cni-args. This example configuration creates the following three VMIs and three interface IPs (IIPs) within the pod:

- VMI, IIP for eth0 on default pod network
- VMI, IIP for eth1 on parent-vn (parent interface)
- VMI, IIP for eth1.100 on subitf-vn (subinterface)

Configuration Use Cases

This section provides examples of different valid and invalid parent and subinterface configurations.

Valid Configurations

- "Valid Configuration 1: One Parent, One Subinterface:" on page 198
- "Valid Configuration 2: One Parent, Multiple Subinterfaces:" on page 199
- "Valid Configuration 3: Multiple Parents, Multiple Subinterfaces:" on page 200

Invalid Configurations

- "Invalid Configuration 1: Multiple Interfaces on Same Network:" on page 201
- "Invalid Configuration 2: Two Interfaces with Same interfacegroup but no VLAN" on page 202

Valid Configuration 1: One Parent, One Subinterface:

```
apiVersion: v1
kind: Pod
metadata:
 name: vlan100-0
 namespace: vlan-project
 annotations:
    k8s.v1.cni.cncf.io/networks: |
      Ε
        {
          "name": "vlan-parent-vn",
          "namespace": "vlan-project",
          "cni-args": {
              "net.juniper.contrail.interfacegroup": "eth1"
          }
       },
        {
          "name": "vlan-subintf-vn",
          "namespace": "vlan-project",
          "cni-args": {
              "net.juniper.contrail.vlan": "100",
              "net.juniper.contrail.interfacegroup": "eth1"
          }
```

Valid Configuration 2: One Parent, Multiple Subinterfaces:

```
apiVersion: v1
kind: Pod
metadata:
  name: vlan100-0
  namespace: vlan-project
  annotations:
    k8s.v1.cni.cncf.io/networks: |
      Ε
        {
          "name": "vlan-parent-vn",
          "namespace": "vlan-project",
          "cni-args": {
              "net.juniper.contrail.interfacegroup": "eth1"
          }
        },
        {
          "name": "vlan-subintf-vn2",
          "namespace": "vlan-project",
          "cni-args": {
              "net.juniper.contrail.vlan": "200",
              "net.juniper.contrail.interfacegroup": "eth1"
          }
        },
        {
          "name": "vlan-subintf-vn",
          "namespace": "vlan-project",
          "cni-args": {
              "net.juniper.contrail.vlan": "100",
              "net.juniper.contrail.interfacegroup": "eth1"
          }
        }
      ]
```

Valid Configuration 3: Multiple Parents, Multiple Subinterfaces:

```
apiVersion: v1
kind: Pod
metadata:
  name: vlan100-0
  namespace: vlan-project
  annotations:
    k8s.v1.cni.cncf.io/networks: |
      Ε
        {
          "name": "vlan-parent-vn",
          "namespace": "vlan-project",
          "cni-args": {
              "net.juniper.contrail.interfacegroup": "eth1"
          }
        },
        {
          "name": "vlan-subintf-vn2",
          "namespace": "vlan-project",
          "cni-args": {
              "net.juniper.contrail.vlan": "200",
              "net.juniper.contrail.interfacegroup": "eth1"
          }
        },
        {
          "name": "vlan-subintf-vn",
          "namespace": "vlan-project",
          "cni-args": {
              "net.juniper.contrail.vlan": "100",
              "net.juniper.contrail.interfacegroup": "eth1"
          }
        },
        {
          "name": "vlan-subintf-vn4",
          "namespace": "vlan-project",
          "cni-args": {
              "net.juniper.contrail.vlan": "100",
              "net.juniper.contrail.interfacegroup": "eth2"
          }
        },
```

```
{
    "name": "vlan-subintf-vn3",
    "namespace": "vlan-project",
    "cni-args": {
        "net.juniper.contrail.interfacegroup": "eth2"
    }
]
```

Invalid Configuration 1: Multiple Interfaces on Same Network:

```
apiVersion: v1
kind: Pod
metadata:
  name: vlan100-0
 namespace: vlan-project
  annotations:
    k8s.v1.cni.cncf.io/networks: |
      Ε
        {
          "name": "vn1",
          "namespace": "vlan-project",
          "cni-args": {
              "net.juniper.contrail.interfacegroup": "eth1"
          }
        },
        {
          "name": "vn1",
          "namespace": "vlan-project",
          "cni-args": {
              "net.juniper.contrail.vlan": "200",
              "net.juniper.contrail.interfacegroup": "eth1"
         }
        },
      ]
```

Invalid Configuration 2: Two Interfaces with Same interfacegroup but no VLAN

```
apiVersion: v1
kind: Pod
metadata:
  name: vlan100-0
  namespace: vlan-project
 annotations:
    k8s.v1.cni.cncf.io/networks: |
      Ε
        {
          "name": "vn1",
          "namespace": "vlan-project",
          "cni-args": {
              "net.juniper.contrail.interfacegroup": "eth1"
         }
        },
        {
          "name": "vn2",
          "namespace": "vlan-project",
          "cni-args": {
              "net.juniper.contrail.interfacegroup": "eth1"
         }
        },
      ]
```

Subinterface Support with Multus

IN THIS SECTION

- Prerequisites | 203
- VLAN Subinterface Overview | 203
- Configuring Subinterfaces on Pods | 203
- CN2 CNI with Multus | 204

- Pod Creation Flow Overview | 206
- API Calls and Output | 207
- Verify Subinterfaces | 209

Starting with Release 23.3, Cloud-Native Contrail® Networking[™] (CN2) supports multiple network subinterfaces using the Multus "meta" plugin. The "meta" references the Multus multi-vendor support.

Prerequisites

For Multus to process subinterfaces, the parent interface (physical or virtual) must be available.

VLAN Subinterface Overview

The following applies to the VLAN subinterface:

- A subinterface is always defined and associated with a parent interface.
- This subinterface is associated with a virtual network different from the parent interface.
- The subinterface should have a valid VLAN tag (1-4095).
- Subinterfaces, like regular interfaces, are created by CN2 for a pod based on the network annotations supplied.

For more information about how Multus works in a Cloud-Native Contrail environment, see Enable Pods with Multiple Network Interfaces and Enable VLAN Subinterface Support on Virtual interfaces.

Configuring Subinterfaces on Pods

To configure subinterfaces on pods use the network definition tags net.juniper.contrail.interfacegroup and net.juniper.contrail.vlan in the annotations cni-args section of the YAML.

- The net.juniper.contrail.interfacegroup tag does the following:
 - InterfaceGroup groups together two or more interfaces.

- The parent interface is the network selection element associated with only this tag.
- The subinterface is the network selection element associated with this tag and a VLAN tag.
- The net.juniper.contrail.vlan tag specifies the VLANID on the subinterface.

CN2 CNI with Multus

This section includes example YAMLs for configuring the CN2 CNI using Multus.

Example Network Attachment Definition for Subinterfaces

A VLAN subinterface belongs to its parent interface. You must specify the namespace to which the subinterface attaches. See the following example.

```
apiVersion: v1
kind: Namespace
metadata:
  name: multus-vlan
---
apiVersion: "k8s.cni.cncf.io/v1"
kind: NetworkAttachmentDefinition
metadata:
  name: multus-vn-1
  namespace: multus-vlan
  annotations:
    juniper.net/networks: '{
      "ipamV4Subnet": "172.16.1.0/24"
   }'
spec:
  config: '{
  "cniVersion": "0.3.1",
  "name": "multus-vn-1",
  "type": "contrail-k8s-cni"
}'
---
apiVersion: "k8s.cni.cncf.io/v1"
kind: NetworkAttachmentDefinition
metadata:
  name: multus-vn-2
```

```
namespace: multus-vlan
annotations:
    juniper.net/networks: '{
        "ipamV4Subnet": "172.16.2.0/24"
    }'
spec:
    config: '{
        "cniVersion": "0.3.1",
        "name": "multus-vn-2",
        "type": "contrail-k8s-cni"
}'
....
```

Example Pod YAML

The following example shows specified pod annotations for the cni-args. This example configuration creates the following three virtual machine interfaces (VMIs) and three interface IP addresses (IIPs) within the pod:

- VMI, IIP for eth0 on the default pod network
- VMI, IIP for eth1 on multus-vn-1 (parent interface)
- VMI, IIP for eth1.100 on multus-vn-2 (subinterface)

```
apiVersion: v1
kind: Pod
metadata:
 name: multus-pod-4
 namespace: multus-vlan
 annotations:
    k8s.v1.cni.cncf.io/networks: |
      Ε
        {
          "name": "multus-vn-1",
          "namespace": "multus-vlan",
          "cni-args": {
              "net.juniper.contrail.interfacegroup": "eth1"
          },
          "ips":["172.16.1.6"],
          "mac":"de:ad:00:00:be:01"
       },
```

```
{
          "name": "multus-vn-2",
          "namespace": "multus-vlan",
          "cni-args": {
              "net.juniper.contrail.vlan": "100",
              "net.juniper.contrail.interfacegroup": "eth1"
          },
          "ips":["172.16.2.6"],
          "mac":"ee:ad:00:00:be:02"
       }
      ]
spec:
 containers:
    - name: multus-pod-4
      image: <repository>:<tag>
      command: ["bash", "-c", "while true; do sleep 60s; done"]
      securityContext:
        capabilities:
          add:
            - NET_ADMIN
        privileged: true
 tolerations:
    - key: "key"
      operator: "Equal"
      value: "value"
      effect: "NoSchedule"
. . .
```

Pod Creation Flow Overview

Kubemanager listens to pod creation, deletion, and update events. When detecting new pod creation:

- Kubemanager parses the pod information and creates the corresponding VM (pod), VMI (pod interface), and IIP (pod interface IP).
- This information is passed to vRouter agent using the XMPP communication channel between the Contrail controller and vRouter agent.
- In parallel to this communication, the kubelet gets a setup pod event and evokes the CN2 CNI to configure the pod networking.

API Calls and Output

The following steps show the API calls and output when creating and configuring the subinterfaces.

 The CN2 CNI calls get vm-cfg (GET POD_CONFIG()) (sample get url [http:// 127.0.0.1:9091/vm-cfg/__multus-vlan__multus-pod-4](http://127.0.0.1:9091/vm-cfg/ __default__testpmd-pod)) API to get a list of all VMIs (virtual machine interfaces) configured using the Contrail controller.

Example output:

```
[{
    "id": "83fbe4ee-79ce-4d1a-972e-5420138eae7f",
    "vm-uuid": "68627577-c1c5-4dac-acf1-3f4547b795e0",
    "vn-id": "4b5f3770-d0e4-4c48-ad34-898cdd76d72d",
    "vn-name": "default-domain:contrail-k8s-kubemanager-kubernetes-contrail:default-
podnetwork",
    "mac-address": "02:83:fb:e4:ee:79",
    "sub-interface": false,
    "vlan-id": 65535,
    "annotations": [
        "{index:0/3}",
        "{interface:eth0}",
        "{network:default-podnetwork}",
        "{vmi-address-family:dualStack}"
    ]
},{
    "id": "9779ab13-acce-48a4-a0db-1a4d07133042",
    "vm-uuid": "68627577-c1c5-4dac-acf1-3f4547b795e0",
    "vn-id": "b173bcd1-bf86-436c-888f-af3c0699865c",
    "vn-name": "default-domain:multus-vlan:multus-vn-1",
    "mac-address": "de:ad:00:00:be:01",
    "sub-interface": false,
    "vlan-id": 65535,
    "annotations": [
        "{index:1/3}",
        "{interface:eth1}",
        "{network:multus-vn-1}",
        "{vmi-address-family:ipV4}"
    ]
},{
    "id": "b71a96e6-f936-477e-a072-9e61a4e16aa7",
```

```
"vm-uuid": "68627577-c1c5-4dac-acf1-3f4547b795e0",
"vn-id": "ceb0fc94-2848-47c6-8c08-7cc2af657517",
"vn-name": "default-domain:multus-vlan:multus-vn-2",
"mac-address": "ee:ad:00:00:be:02",
"sub-interface": true,
"vlan-id": 100,
"annotations": [
    "{index:2/3}",
    "{interface:eth1}",
    "{network:multus-vn-2}",
    "{vlan-id:100}",
    "{vlan-id:100}",
    "{vmi-address-family:ipV4}"
]
```

2. The CN2 CNI processes this information and calls the port add message (POST VMI) (sample post api http://127.0.0.1:9091/vm)

Example output:

```
{
    "time": "2023-07-04 08:31:44.276785096 +0000 UTC m=+15.080014967",
    "vm-id": "54b3ae3eefc4486bc826d595b1316210f9e445f7de1bcad71112037980e7c9a7",
    "vm-uuid": "68627577-c1c5-4dac-acf1-3f4547b795e0",
    "vm-name": "__multus-vlan__multus-pod-4",
    "host-ifname": "tapeth0-686275",
    "vm-ifname": "eth0",
    "vm-namespace": "/var/run/netns/85d564c8-a4a5-49ee-b040-0d43c5eaf883",
    "vn-uuid": "4b5f3770-d0e4-4c48-ad34-898cdd76d72d",
    "vmi-uuid": "83fbe4ee-79ce-4d1a-972e-5420138eae7f",
    "vhostuser-mode": 0,
    "vhostsocket-dir": "",
    "vhostsocket-filename": "",
    "vmi-type": "",
    "pod-uid": ""
}
. . .
```

3. Then the CN2 CNI does get result (GET VM IP) to vrouter-agent (sample api [http://127.0.0.1:9091/vm/68627577-c1c5-4dac-

acf1-3f4547b795e0/83fbe4ee-79ce-4d1a-972e-5420138eae7f] (http://127.0.0.1:9091/vm/68627577-c1c5-4dac-acf1-3f4547b795e0/83fbe4ee-79ce-4d1a-972e-5420138eae7f))

Example output:

```
[{
    "id": "83fbe4ee-79ce-4d1a-972e-5420138eae7f",
    "instance-id": "68627577-c1c5-4dac-acf1-3f4547b795e0",
    "vn-id": "4b5f3770-d0e4-4c48-ad34-898cdd76d72d",
    "vm-project-id": "0000000-0000-0000-0000-00000000000",
    "mac-address": "02:83:fb:e4:ee:79",
    "system-name": "tapeth0-686275",
    "rx-vlan-id": 65535,
    "tx-vlan-id": 65535,
    "vhostuser-mode": 0,
    "ip-address": "192.168.0.33",
    "plen": 24,
    "dns-server": "192.168.0.1",
    "gateway": "192.168.0.1",
    "v6-ip-address": "2001::21",
    "v6-plen": 64,
    "v6-dns-server": "2001::1",
    "v6-gateway": "2001::1",
    "author": "/contrail-vrouter-agent",
    "time": "469016:31:59.293170"
}]
. . .
```

- **4.** Now the CN2 CNI gets the IP address to configure in the pod, performs the configuration as needed, and returns results to the kubelet.
 - If configuration request is to add a subinterface, check if parent interface exists. If not, create the parent interface and then create the subinterface.
 - If configuration request is to delete the parent interface, delete the subinterfaces.

Verify Subinterfaces

To confirm the subinterfaces are created:

• Ping between two pods via subinterfaces.

- Create multiple subinterfaces on a single parent interface in a pod.
- Create multiple subinterfaces and multiple parent interfaces in a pod.

You can also run the kubectl exec command to access inside the pod. Then run the ip addr command to display the current networking.

\$ kubectl exec -it -n <namespace> <podname> -- /bin/bash
\$ ip addr

Example output:

1: lo: <LOOPBACK,UP,LOWER_UP> mtu 65536 qdisc noqueue state UNKNOWN group default qlen 1000 link/loopback 00:00:00:00:00:00 brd 00:00:00:00:00:00 inet 127.0.0.1/8 scope host lo valid_lft forever preferred_lft forever inet6 ::1/128 scope host valid_lft forever preferred_lft forever 2: eth1.100@eth1: <BROADCAST,MULTICAST,UP,LOWER_UP> mtu 1500 qdisc noqueue state UP group default link/ether ee:ad:00:00:be:02 brd ff:ff:ff:ff:ff inet 172.16.2.6/24 brd 172.16.2.255 scope global eth1.100 valid_lft forever preferred_lft forever inet6 fe80::dc91:bbff:feea:d676/64 scope link valid_lft forever preferred_lft forever 26: eth1@if27: <BROADCAST,MULTICAST,UP,LOWER_UP> mtu 1500 qdisc noqueue state UP group default link/ether de:ad:00:00:be:01 brd ff:ff:ff:ff:ff link-netnsid 0 inet 172.16.1.6/24 brd 172.16.1.255 scope global eth1 valid_lft forever preferred_lft forever inet6 fe80::dc91:bbff:feea:d676/64 scope link valid_lft forever preferred_lft forever 28: eth0@if29: <BROADCAST,MULTICAST,UP,LOWER_UP> mtu 1500 qdisc noqueue state UP group default link/ether 02:da:89:0d:69:be brd ff:ff:ff:ff:ff link-netnsid 0 inet 192.168.3.11/24 brd 192.168.3.255 scope global eth0 valid_lft forever preferred_lft forever

RELATED DOCUMENTATION

Enable Pods with Multiple Network Interfaces

Enable VLAN Subinterface Support on Virtual interfaces

EVPN Networking Support

SUMMARY

Juniper Cloud-Native Contrail Networking release R22.4 supports EVPN/VXLAN forwarding using Type2 prefixes with Virtual Networks utilizing forwarding mode L2 and L2_L3. With EVPN for Layer 2 connectivity and VXLAN for data encapsulation, CN2 enables you to establish connectivity between a CN2 virtual network and an EVPN-VXLAN-signalled service.

IN THIS SECTION

- EVPN Overview | 211
- VXLAN Overview | 211
- EVPN-VXLAN Overview | 212
- Configuring VXLAN Encapsulation Priority | **212**
- Manually Set a VXLAN VNI for Virtual Networks | 213

EVPN Overview

EVPN is an extension to Border Gateway Protocol (BGP) that allows the network to carry endpoint reachability information such as Layer 2 MAC addresses and Layer 3 IP addresses. This control plane technology uses Multiprotocol BP (MP-BGP) for MAC and IP address endpoint distribution, where MAC addresses are treated as routes.

EVPN also provides multipath forwarding and redundancy through an all-active multihoming model. An endpoint or device connects to two or more upstream devices and forwards traffic using all the links. If a link or device fails, traffic continues to flow using the remaining active links.

With EVPN, MAC learning is handled in the control plane. This avoids the data plane flooding of unknown IPs typical with Layer 2 networks. EVPN also supports different data-plane encapsulation technologies between EVPN-VXLAN-enabled switches. In EVPN-VXLAN architecture, VXLAN provides the overlay data-plane encapsulation.

VXLAN Overview

VXLAN is an overlay tunneling protocol. The VXLAN tunneling protocol encapsulates MAC frames into UDP headers at Layer 2. This means that VXLAN encapsulates Ethernet frames into UDP packets with the physical network headers (IP header, Ethernet header) as outer headers. As a result, VXLAN enables devices to route UDP packets across networks, independent of the physical underlay.

The entity that performs the encapsulation and de-encapsulation is called a VXLAN tunnel endpoint (VTEP). After CN2 establishes a VXLAN segment, a VTEP encapsulates VM or pod traffic into a VXLAN header and sends that traffic to another VTEP. The receiving VTEP removes or strips off the encapsulation and forwards the data. VMs or pods must belong to the same VXLAN segment to communicate using VXLAN.

EVPN-VXLAN Overview

In Juniper networks, EVPN performs control plane functionality and VXLAN performs data plane functionality. EVPN handles MAC address learning in the control plane. VXLAN defines a tunneling scheme to overlay Layer 2 networks on top of Layer 3 networks. This tunneling scheme allows for optimal forwarding of Ethernet frames with support for an all-active multipathing of unicast and multicast traffic with the use of UDP/IP encapsulation for tunneling.

Configuring VXLAN Encapsulation Priority

The default encapsulation protocol for EVPN is MPLS over UDP. In order to enable EVPN-VXLAN for your cluster, you must change the encapsulation priority order in the GlobalVrouterConfig of your cluster. Set VXLAN as the top encapsulation priority in the encapsulation section of encapsulationPriorities in the default-global-vrouter-config object of GlobalVrouterConfig.

The following example GlobalVrouterConfig shows VXLAN as the top encapsulation priority.

```
apiVersion: core.contrail.juniper.net/v1
kind: GlobalVrouterConfig
metadata:
    creationTimestamp: "2022-08-23T10:45:52Z"
    generation: 6
    labels:
        core.juniper.net/parent: 9b83eddfaaa5778ad6b99cb81c803529cf911d492b9e7ec6d63d029d
    name: default-global-vrouter-config
    resourceVersion: "35583"
    uid: b2b57f5c-8dd0-4cd1-848f-0ec23f2819df
spec:
    encapsulationPriorities:
    encapsulationPriorities:
    encapsulation:
        - VXLAN
        - MPLSoGRE
```

```
fqName:
- default-global-system-config
- default-global-vrouter-config
linklocalServices:
  linklocalServiceEntry:
  - ipFabricServiceIP:
    - 10.87.76.29
    - 10.87.76.31
    - 10.87.76.32
```

- MPLSoUDP

ipFabricServicePort: 6443

```
linklocalServiceIP: 10.200.0.1
```

linklocalServiceName: kubernetes

```
linklocalServicePort: 443
```

parent:

apiVersion: core.contrail.juniper.net/v1

kind: GlobalSystemConfig

```
name: default-global-system-config
```

uid: 2f9ff5cf-4d40-4e8f-b7d3-2e403624c572

portTranslationPools:

pools:

- portRange: endPort: 57023

startPort: 56000

protocol: tcp

- portRange:

endPort: 58047 startPort: 57024

protocol: udp

status:

```
observation: ""
state: Success
```

Manually Set a VXLAN VNI for Virtual Networks

A VXLAN network identifier (VNI) uniquely identifies the VXLAN segment. VNIs enable CN2 to use the same MAC frames across multiple VXLAN segments without traffic crossover. This means that CN2 can establish multiple VXLAN segments between the same VMs or pods with traffic isolation. VMs or pods on the same VNI communicate with each other and VMs or pods on separate VNIs need a router to communicate. VLAN tunnel endpoints (VTEPs) perform data encapsulation and reference VNI and MAC address information when looking up the forwarding table of another VM or pod. Once the VTEP determines a forwarding table, one VTEP endpoint sends a UDP packet to another endpoint over a network.

CN2 assigns a unique VNI to a virtual network (VN) upon VN creation. In CN2 release 22.4, you can manually set a VNI for your virtual networks. You can also define a VNI using a Network Attachment Definition (NAD).

The following YAML example shows a user-defined VNI in a VN.

```
apiVersion: core.contrail.juniper.net/v1alpha1
kind: VirtualNetwork
metadata:
   namespace: evpnl2test
   name: vn1
spec:
   v4SubnetReference:
    apiVersion: core.contrail.juniper.net/v1alpha1
    kind: Subnet
    namespace: evpnl2test
    name: sn1
   virtualNetworkProperties:
    forwardingMode: 12
   virtualNetworkNetworkId: 5000
```

The following YAML example shows a user-defined VNI in a NAD.

```
apiVersion: "k8s.cni.cncf.io/v1"
kind: NetworkAttachmentDefinition
metadata:
   name: evpnl2
   namespace: evpnl2test
   annotations:
     juniper.net/networks: '{
        "ipamV4Subnet": "172.26.10.0/24",
        "virtualNetworkNetworkID": 5000
     }'
spec:
   config: '{
        "cniVersion": "0.3.1",
        "name": "evpnl2",
```

```
"type": "contrail-k8s-cni"
}'
```

RELATED DOCUMENTATION

EVPN User Guide

Customize Virtual Networks for Pod Deployments, Services, and Namespaces

SUMMARY

Starting in release 23.1, Juniper Cloud-Native Contrail Networking (CN2) supports the ability to apply a custom default network for namespaces, Deployments, and Services. This feature also supports environments with Multus CNI enabled. With Multus as the CNI of your CN2 environment, you can deploy pods that have multiple interfaces for different use cases.

IN THIS SECTION

- Custom Namespace Network
 Overview | 215
- Apply a Custom Namespace Network to a Namespace | 216
- Apply a Custom Service Network to a Service | 217
- Designate a Virtual Network as a Custom
 Default Pod Network | 217
- Use a NAD to Create a Custom Default Pod Network | **218**
- Deploy a Custom Pod Network per Pod | 218
- Custom Default Namespace Network Interactions | 221
- Multi-NIC Pod | 221

Custom Namespace Network Overview

In traditional Kubernetes, the default pod network is a single CIDR used by all pods in the cluster, regardless of namespace. This approach doesn't allow for network layer segmentation between pods

because Kubernetes assigns IPs from a shared CIDR. CN2 addresses this drawback with isolated namespaces. CN2 isolated namespaces enable Kubernetes to create custom default namespace networks on a per-namespace basis. This means that when you configure a Deployment in a namespace with a custom namespace network, new pods and services use the custom network within an individual isolated namespace. Isolated namespaces ensure network isolation between pods and services without the need for a Kubernetes network policy.

CN2 improves on this feature by enabling Kubernetes to create pods that use custom namespace networks on a per-pod basis. Custom namespace networks provide their own VirtualNetworks (VNs) and Subnets. CN2 assigns pod IPs based on the Subnet parameters of a given custom namespace network. In other words, you can create pods with their own networks in a given namespace. This means that CN2 supports network isolation at the namespace level and pod level.

Apply a Custom Namespace Network to a Namespace

You can specify a custom default namespace network per namespace. Designate a custom namespace network on a per-namespace basis and all pods and services created within that namespace use that network as the pod or service network. The Namespace annotation net.juniper.contrail.podnetwork: network-namespace/network-name designates the desired network as the custom namespace network.

The following YAML shows an example of namespace with a custom namespace network annotation.

apiVersion: v1
kind: Namespace
metadata:
 name: custom-podnet
 annotations:
 net.juniper.contrail.podnetwork: custom-podnet/ns-level-custom-podnets

NOTE: The annotation of a namespace must be present when you create the namespace. You cannot update the annotation on a namespace to change its network. You must recreate the namespace to change its network. If kubemanager detects an update to the Custom Namespace Network annotation within a namespace, kubemanager flags that namespace and any pod created within that namespace after the update does not start. Reverting the update removes the flag and the pods launch normally.

Apply a Custom Service Network to a Service

You can specify a custom default network for services in the annotations of a Service object. As a result, the service can select pods that use the custom service network. Services that select pods with a custom network are isolated from other networks. The annotation format is: network-namespace/network-name.

The following is an example of a Service with a custom service network.

apiVersion: v1
kind: Service
metadata:
 name: custom-podnet-svc
 namespace: custom-podnet
 annotations:
 net.juniper.contrail.podnetwork: custom-podnet/pod-level-custom-podnet

Designate a Virtual Network as a Custom Default Pod Network

You can designate a VN as a custom default pod network. If you manually create a VirtualNetwork object, you must set the field "podNetwork: true" on the VirtualNetwork's spec. This field designates the new VN as the custom default pod network. CN2 assigns IPs to pods from this network.

The following is an example of a VirtualNetwork designated as a custom default pod network.

```
apiVersion: core.contrail.juniper.net/v2
kind: VirtualNetwork
metadata:
   namespace: custom-podnet
   name: vn-network
spec:
   podNetwork: true
   v4SubnetReference:
    apiVersion: core.contrail.juniper.net/v2
    kind: Subnet
    namespace: custom-podnet
    name: vn-network-subnet
```

Use a NAD to Create a Custom Default Pod Network

Install a Network Attachment Definiton (NAD) with podNetwork: true set at the juniper.net/networks annotation to create a custom default pod network. After you create this NAD, the NAD controller automatically creates a VN and sets the "podNetwork: true" field during VirtualNetwork creation.

The following is an example of a NAD designated as a custom default pod network.

```
apiVersion: "k8s.cni.cncf.io/v1"
kind: NetworkAttachmentDefinition
metadata:
  name: nad-network
  namespace: custom-podnet
  annotations:
    juniper.net/networks: '{
        "ipamV4Subnet": "5.5.5.0/24",
        "podNetwork": true
    }'
```

•

NOTE: You don't need to specify a NAD annotation for pods within a namespace if this namespace uses the same network as the primary interface (eth0). In other words, since the namespace specifies a network with an annotation, pods within that namespace don't need to specify that same network.

Deploy a Custom Pod Network per Pod

You can also specify a custom default pod network per pod. In order to designate a custom pod network on a per-pod basis, you must specify the following key value pair in the annotations of a pod: "net.juniper.contrail.podnetwork": network-namespace/network-name. This feature provides pod isolation because pods that use a custom pod network are isolated from other networks.

The following example shows a namespace, VirtualNetwork, and pod with custom default networks defined.

apiVersion: v1 kind: Namespace metadata:

```
name: cpn-intra-network-test-vn
 annotations:
    net.juniper.contrail.podnetwork: cpn-intra-network-test-vn/vn
---
apiVersion: core.contrail.juniper.net/v1
kind: Subnet
metadata:
 namespace: cpn-intra-network-test-vn
 name: vn-sn
spec:
 cidr: 15.15.15.0/24
---
apiVersion: core.contrail.juniper.net/v1
kind: VirtualNetwork
metadata:
 namespace: cpn-intra-network-test-vn
 name: vn
spec:
 podNetwork: true
 v4SubnetReference:
   apiVersion: core.contrail.juniper.net/v1
   kind: Subnet
   namespace: cpn-intra-network-test-vn
   name: vn-sn
- -
apiVersion: v1
kind: Pod
metadata:
 name: ns-level-cpn-pod
 namespace: cpn-intra-network-test-vn
spec:
 containers:
    - name: toolbox
      image: <repository>:<tag>
      imagePullPolicy: IfNotPresent
      command: ["bash", "-c", "while true; do sleep 60s; done"]
      securityContext:
        capabilities:
          add:
            - NET_ADMIN
       privileged: true
 tolerations:
    - key: "key"
```

```
operator: "Equal"
      value: "value"
      effect: "NoSchedule"
apiVersion: v1
kind: Pod
metadata:
 name: pod-level-cpn-pod
 namespace: cpn-intra-network-test-vn
 annotations:
   net.juniper.contrail.podnetwork: cpn-intra-network-test-vn/vn # namespace/name of the network
   net.juniper.contrail.podnetwork.ip: 15.15.15.3 # ip request for the interface
   net.juniper.contrail.podnetwork.cni-args: | # any cni-args needed for this interface
spec:
 containers:
    - name: toolbox
      image: <repository>:<tag>
      imagePullPolicy: IfNotPresent
      command: ["bash", "-c", "while true; do sleep 60s; done"]
      securityContext:
       capabilities:
          add:
            - NET_ADMIN
       privileged: true
 tolerations:
    - key: "key"
      operator: "Equal"
      value: "value"
      effect: "NoSchedule"
```

Note the following pod annotations:

```
annotations:
  net.juniper.contrail.podnetwork: cpn-mc-cc/cpn1 # namespace/name of the network
  net.juniper.contrail.podnetwork.ip: 100.100.100.3 # ip request for the interface
  net.juniper.contrail.podnetwork.cni-args: | # any cni-args needed for this interface
    {
        "net.juniper.contrail.interfacegroup": "eth0"
    }
```

You define a custom pod network in the annotations of both the pod (pod-level-cpn-pod) and namespace (cpn-intra-network-test-vn). As part of the 23.1 release, you must configure a pod to use a custom pod network in the annotations at the pod level. If you specify an annotation at both the pod and namespace level, the pod-level annotation takes priority.

Custom Default Namespace Network Interactions

See the following sections for information about common custom namespace network interactions.

Multi-NIC Pod

A pod with a custom default namespace network may still contain multiple interfaces. The following YAML is an example of a NetworkSelectionElement of a pod with a custom network and multiple interfaces.

```
apiVersion: v1
kind: Namespace
metadata:
 name: custom-podnet
 annotations:
    net.juniper.contrail.podnetwork: cpn-intra-network-test/vn
# Pod
 annotations:
    k8s.v1.cni.cncf.io/networks: |
      Γ
        {
          "name": "vn1",
          "namespace": "vn1-ns",
       },
        {
          "name": "vn2",
          "namespace": "vn2-ns",
       }
      ]
```

A pod with the annotations defined above would utilize eth0 from custom-podnet-vn, eth1 from vn1, and eth2 from vn2. You can also create a namespace with a custom namespace network and multiple interfaces. The following YAML shows the configuration above, replicated at the namespace level.

```
apiVersion: v1
kind: Namespace
metadata:
  name: vn0-ns
  annotations:
    net.juniper.contrail.podnetwork: vn0-ns/vn0
- -
# Pod
  annotations:
    k8s.v1.cni.cncf.io/networks: |
      [
        {
          "name": "vn1",
          "namespace": "vn1-ns",
        },
        {
          "name": "vn2",
          "namespace": "vn2-ns",
        }
      ]
```

Deploy Kubevirt DPDK Dataplane Support for VMs

SUMMARY

Cloud-Native Contrail[®] Networking[™] (CN2) supports the deployment of Kubevirt with vRouter DPDK dataplane for high-performance Virtual Machine (VM) and container networking in Kubernetes.

IN THIS SECTION

Kubevirt Overview 223
Kubevirt and the DPDK vRouter 223
Deploy Kubevirt 224
Prerequisites 224



Kubevirt Overview

Kubevirt is an open-source Kubernetes project that enables the management and scheduling of VM workloads alongside container workloads within a Kubernetes cluster. Kubevirt provides a method of running VMs in a Kubernetes-orchestrated environment.

Kubevirt provides the following additional functions to your Kubernetes cluster. These enhancements help support Kubevirt in a cloud networking environment:

- Other types of pods, or Custom Resource Definitions (CRDs), to the Kubernetes API server.
- Controllers for cluster-wide logic to support the new types of pods.
- Daemons for node-specific logic to support the new types of pods.

Kubevirt creates and manages VirtualMachineInstance (VMI) objects. A VMI is an instantiation of a VM. In other words, when you create a VM, the VMI associated with that VM represents the unique instance or state of that VM. VMIs enable you to terminate and initiate VMs at another time with no change in data or state. If a VM fails, the VMI helps restore it. Kubevirt provides a way for VMs to run in the Kubernetes-orchestrated environment.

Kubevirt and the DPDK vRouter

Kubevirt does not typically support user space networking for fast packet processing. In CN2, however, enhancements enable Kubevirt to support vhostuser interface types for VMs. A vhostuser interface type is a virtual network interface that enables high-performance communication between a VM and a user-space application. These interfaces perform user space networking with the Data Plane Development Kit (DPDK) vRouter and give pods and Kubevirt VMs access to the increased performance and packet processing the DPDK vRouter provides.

The following are some of the benefits of the DPDK vRouter application:

- Packet processing occurs in user space and bypasses kernel space. This bypass increases packetprocessing efficiency.
- Kernel interrupts and context switches do not occur because packets bypass kernel space. This bypass results in less CPU overhead and increased data throughput.
- DPDK enhances the forwarding plane of the vRouter in user space, increasing performance.
- DPDK Lcores run in poll mode. This mode enables the Lcores to receive and process packets immediately upon receiving them.

Kubevirt utilizes the DPDK vRouter as a high-performance networking solution for VMs running in Kubernetes. Instead of relying on default kernel-based networking, Kubevirt integrates with DPDK vRouter to achieve accelerated packet processing for the VMs.

Deploy Kubevirt

Prerequisites

You must have an active Kubernetes cluster and the ability to use the kubectl client in order to deploy Kubevirt.

Pull Kubevirt Images and Deploy Kubevirt Using a Local Registry

See the following topic for information about how to deploy Kubevirt: "Pull Kubevirt Images and Deploy Kubevirt Using a Local Registry" on page 232.

NOTE: These instructions are for the following Kubevirt releases:

- v0.58.0 (current)
- v0.48.0

Launch a VM Alongside a Container

With Kubevirt, launching and managing a VM in Kubernetes is similar to deploying a pod. You can create a VM object using kubect1. After creating a VM object, that VM is active and running in your cluster.

Use the following high-level steps to launch a VM alongside a container:

- 1. Create a VirtualNetwork.
- **2.** Launch a VM.

Create a Virtual Network

The following NetworkAttachmentDefinition object is an example of a virtual network:

```
apiVersion: "k8s.cni.cncf.io/v1"
kind: NetworkAttachmentDefinition
metadata:
  name: vn-blue
  namespace: contrail
  annotations:
    juniper.net/networks: '{
      "ipamV4Subnet": "19.1.1.0/24"
    }'
 labels:
    vn: vn-blue-vn-green
spec:
  config: '{
  "cniVersion": "0.3.1",
  "name": "nad-blue",
  "type": "contrail-k8s-cni"
}'
```


Launch a VM

The following VirtualMachine specs are examples of VirtualMachine instances with a varying number of interfaces:

NOTE: For the latest Kubevirt API version information, refer to the official Kubevirt documentation for the latest release: https://github.com/kubevirt/kubevirt.

• Single vhostuser interface VM:

```
apiVersion: kubevirt.io/v1
kind: VirtualMachine
metadata:
  name: vm-single-virtio
  namespace: contrail
spec:
  running: true
  template:
    metadata:
      labels:
        kubevirt.io/size: small
        kubevirt.io/domain: vm-single-virtio
        app: vm-single-virtio-app
    spec:
      nodeSelector:
        master: master
      terminationGracePeriodSeconds: 30
      domain:
        cpu:
          sockets: 1
          cores: 8
          threads: 2
          #dedicatedCpuPlacement: true
        memory:
          hugepages:
            pageSize: "2Mi"
        resources:
          requests:
            memory: "512Mi"
        devices:
          disks:
            - name: containerdisk
              disk:
                bus: virtio
            - name: cloudinitdisk
```



• Single vhostuser interface VM with CNI parameters:

Kubevirt also enables you to specify a network to use for a VM through the spec:network and domain:interfaces fields. This functionality is limited because Kubevirt typically doesn't allow you to specify additional network parameters like "ips" or "cni-args". With Kubevirt running in a CN2 environment however, you can define specific VM networks in a Kubevirt VM's annotations field.

Use key k8s.v1.cni.cncf.io/networks, define your custom networks, and specify additional desired parameters. The CN2 CNI resolves the custom network configuration by filling in missing fields.

For example, if you specify a "cni-args" parameter, the VM annotations, the CN2 CNI attempts to merge the default network of the Kubevirt VM with the user-specified network, including additional parameter fields.

Note the annotations field. In this example, cni-args enables the health-check feature. The custom networks vn-green and vn-blue are merged with the default VM's network.

apiVersion: kubevirt.io/v1
kind: VirtualMachine
metadata:
 annotations:

```
k8s.v1.cni.cncf.io/networks: |
          Ε
           {
             "name": "vn-green",
             "namespace": "kubevirttest",
             "cni-args": {
               "core.juniper.net/health-check": "[{\"name\": \"bfd-hc\", \"namespace\":
\"kubevirttest\"}]"
            }
           },
           {
              "name": "vn-blue",
              "namespace": "kubevirttest"
           }
          ]
 labels:
    special: vm-ubuntu
  name: vm-ubuntu-hc-1
 namespace: kubevirttest
spec:
  running: true
  template:
   metadata:
     labels:
        kubevirt.io/size: small
        kubevirt.io/domain: vm-single-virtio
        app: vm-single-virtio-app
   spec:
      nodeSelector:
        master: master
      terminationGracePeriodSeconds: 30
      domain:
        cpu:
          sockets: 1
          cores: 8
          threads: 2
          #dedicatedCpuPlacement: true
        memory:
          hugepages:
            pageSize: "2Mi"
```

resources: requests:

memory: "512Mi"

228

```
229
```

```
devices:
    disks:
      - name: containerdisk
        disk:
          bus: virtio
      - name: cloudinitdisk
        disk:
          bus: virtio
    interfaces:
    - name: default
      bridge: {}
    - name: vhost-user-vn-blue
      vhostuser: {}
    useVirtioTransitional: true
networks:
- name: default
  pod: {}
- name: vhost-user-vn-blue
  multus:
    networkName: vn-blue
volumes:
  - name: containerdisk
    containerDisk:
      image: <image>:<latest>
  - name: cloudinitdisk
    cloudInitNoCloud:
      userDataBase64: SGkuXG4=
```

• Multi vhostuser interface:

```
apiVersion: kubevirt.io/v1
kind: VirtualMachine
metadata:
   name: vm-multi-virtio
   namespace: contrail
spec:
   running: true
   template:
      metadata:
      labels:
      kubevirt.io/size: small
      kubevirt.io/domain: vm-multi-virtio
```

```
app: vm-multi-virtio-app
spec:
  nodeSelector:
    worker: worker
  terminationGracePeriodSeconds: 30
  domain:
    cpu:
      sockets: 1
      cores: 8
      threads: 2
      #dedicatedCpuPlacement: true
   memory:
      hugepages:
        pageSize: "2Mi"
    resources:
      requests:
        memory: "512Mi"
    devices:
      disks:
        - name: containerdisk
          disk:
            bus: virtio
        - name: cloudinitdisk
          disk:
            bus: virtio
      interfaces:
      - name: default
        bridge: {}
      - name: vhost-user-vn-blue
        vhostuser: {}
      - name: vhost-user-vn-green
        vhostuser: {}
      useVirtioTransitional: true
  networks:
  - name: default
    pod: {}
  - name: vhost-user-vn-blue
   multus:
      networkName: vn-blue
  - name: vhost-user-vn-green
    multus:
      networkName: vn-green
  volumes:
```

- name: containerdisk containerDisk: image: <image>:<latest>
 name: cloudinitdisk cloudInitNoCloud: userDataBase64: SGkuXG4=
- Bridge/vhostuser interface VM:

```
apiVersion: kubevirt.io/v1
kind: VirtualMachine
metadata:
 name: vm-virtio-veth
  namespace: contrail
spec:
  running: true
  template:
    metadata:
      labels:
        kubevirt.io/size: small
        kubevirt.io/domain: vm-virtio-veth
        app: vm-virtio-veth-app
    spec:
      nodeSelector:
        master: master
      terminationGracePeriodSeconds: 30
      domain:
        cpu:
          sockets: 1
          cores: 8
          threads: 2
          #dedicatedCpuPlacement: true
        memory:
          hugepages:
            pageSize: "2Mi"
        resources:
          requests:
            memory: "512Mi"
        devices:
          disks:
            - name: containerdisk
              disk:
```

```
bus: virtio
      - name: cloudinitdisk
        disk:
          bus: virtio
    interfaces:
    - name: default
      bridge: {}
    - name: vhost-user-vn-blue
      vhostuser: {}
    - name: vhost-user-vn-green
      bridge: {}
    useVirtioTransitional: true
networks:
- name: default
  pod: {}
- name: vhost-user-vn-blue
 multus:
    networkName: vn-blue
- name: vhost-user-vn-green
 multus:
    networkName: vn-green
volumes:
  - name: containerdisk
    containerDisk:
      image: <image>:<latest>
  - name: cloudinitdisk
    cloudInitNoCloud:
      userDataBase64: SGkuXG4=
```

Pull Kubevirt Images and Deploy Kubevirt Using a Local Registry

The current Kubevirt release (v0.58.0) doesn't support imagePullSecret. This field-located in a Kubernetes configuration file-tells Kubernetes where to pull credentials from in order to pull images from a secure registry (enterprise-hub.juniper.net/contrail-container-prod/). Juniper Cloud-Native Contrail® Networking[™] (CN2) release 22.4 addresses this issue with a workaround for the older Kubevirt release (v048.0) and current release (v0.58.0).

See the following information about how to perform this workaround to pull images and deploy Kubevirt using a local registry.

1. Install Docker.

sudo curl -fsSL https://get.docker.com -o /tmp/get-docker.sh sudo sh /tmp/get-docker.sh

2. Create a local registry.

sudo docker run -d -p 5000:5000 --restart=always --name registry registry:2

3. Edit /etc/docker/daemon.json to add your local registry's ip:port.

```
# add the following to /etc/docker/daemon.json
#
#
#{
# "local-registries" : ["your-computer-hostname:5000"]
#}
```

4. Restart Docker.

sudo service docker restart

5. Download the required containers. These containers are located at Release Userspace CNI - dpdk vhostuser interface support Juniper/kubevirt. The kubevirt-operator.yaml and kubevirt-cr.yaml are also located at this repository.

```
sudo wget -0 /tmp/virt-api_v0.58.0-jnpr.tar.gz https://github.com/Juniper/kubevirt/releases/
download/v0.58.0-jnpr/virt-api_v0.58.0-jnpr.tar.gz
sudo wget -0 /tmp/virt-controller_v0.58.0-jnpr.tar.gz https://github.com/Juniper/kubevirt/
releases/download/v0.58.0-jnpr/virt-controller_v0.58.0-jnpr.tar.gz
sudo wget -0 /tmp/virt-handler_v0.58.0-jnpr.tar.gz https://github.com/Juniper/kubevirt/
releases/download/v0.58.0-jnpr/virt-handler_v0.58.0-jnpr.tar.gz
sudo wget -0 /tmp/virt-launcher_v0.58.0-jnpr.tar.gz https://github.com/Juniper/kubevirt/
releases/download/v0.58.0-jnpr/virt-launcher_v0.58.0-jnpr.tar.gz
sudo wget -0 /tmp/virt-launcher_v0.58.0-jnpr.tar.gz
releases/download/v0.58.0-jnpr/virt-launcher_v0.58.0-jnpr.tar.gz
```

6. Load the required containers.

```
sudo docker load < /tmp/virt-api_v0.58.0-jnpr.tar.gz
sudo docker load < /tmp/virt-controller_v0.58.0-jnpr.tar.gz
sudo docker load < /tmp/virt-handler_v0.58.0-jnpr.tar.gz
sudo docker load < /tmp/virt-launcher_v0.58.0-jnpr.tar.gz
sudo docker load < /tmp/virt-operator_v0.58.0-jnpr.tar.gz</pre>
```

7. Tag and push the containers to your local registry.

Replace <LOCAL_REGISTRY> with your local registry. For example, if the containers are hosted at 10.84.13.52:5000/kubevirt, replace <LOCAL_REGISTRY> with 10.84.13.52:5000/kubevirt.

```
sudo docker tag svl-artifactory.juniper.net/atom-docker/kubevirt/virt-api:v0.58.0-jnpr
<LOCAL_REGISTRY>/virt-api:v0.58.0-jnpr
sudo docker push <LOCAL_REGISTRY>/virt-api:v0.58.0-jnpr
sudo docker tag svl-artifactory.juniper.net/atom-docker/kubevirt/virt-controller:v0.58.0-
jnpr <LOCAL_REGISTRY>/virt-controller:v0.58.0-jnpr
sudo docker push <LOCAL_REGISTRY>/virt-controller:v0.58.0-jnpr
sudo docker tag svl-artifactory.juniper.net/atom-docker/kubevirt/virt-handler:v0.58.0-jnpr
<LOCAL_REGISTRY>/virt-handler:v0.58.0-jnpr
sudo docker push <LOCAL_REGISTRY>/virt-handler:v0.58.0-jnpr
sudo docker tag svl-artifactory.juniper.net/atom-docker/kubevirt/virt-launcher:v0.58.0-jnpr
sudo docker tag svl-artifactory.juniper.net/atom-docker/kubevirt/virt-launcher:v0.58.0-jnpr
sudo docker tag svl-artifactory.juniper.net/atom-docker/kubevirt/virt-launcher:v0.58.0-jnpr
<LOCAL_REGISTRY>/virt-launcher:v0.58.0-jnpr
sudo docker push <LOCAL_REGISTRY>/virt-launcher:v0.58.0-jnpr
sudo docker tag svl-artifactory.juniper.net/atom-docker/kubevirt/virt-operator:v0.58.0-jnpr
sudo docker tag svl-artifactory.juniper.net/atom-docker/kubevirt/virt-operator:v0.58.0-jnpr
sudo docker push <LOCAL_REGISTRY>/virt-launcher:v0.58.0-jnpr
sudo docker tag svl-artifactory.juniper.net/atom-docker/kubevirt/virt-operator:v0.58.0-jnpr
sudo docker push <LOCAL_REGISTRY>/virt-operator:v0.58.0-jnpr
```

8. Download the kubevirt-operator.yaml and kubevirt-cr.yaml.

```
wget https://github.com/Juniper/kubevirt/releases/download/v0.58.0-jnpr/kubevirt-
operator.yaml
wget https://github.com/Juniper/kubevirt/releases/download/v0.58.0-jnpr/kubevirt-cr.yaml
```

9. Modify the kubevirt-operator.yaml.

Replace <LOCAL_REGISTRY> with your local registry. For example, if the containers are hosted at 10.84.13.52:5000/kubevirt, replace <LOCAL_REGISTRY> with 10.84.13.52:5000/kubevirt.

10. Modify /etc/crio/crio.conf in all Kubernetes nodes in the cluster. Add the following to the crio.conf in all of the Kubernetes nodes in the cluster. These commands allow cri-o (Container Runtime Interface-Open Container Initiative) to pull images from your local registry.

NOTE: The cri-o service is a version of the Kubernetes container runtime interface (CRI) that enables the use of Open Container Initiative (OCI) compatible runtimes.

Where 10.92.81.91 is the ip of <LOCAL_REGISTRY>

11. After modifying the crio.conf, restart the service.

service crio restart

RELATED DOCUMENTATION

Deploy Kubevirt DPDK Dataplane Support for VMs | 222

Static Routes

SUMMARY

Juniper Cloud-Native Contrail Networking (CN2) release 23.1 supports static routes for your cluster. This article provides information about how to configure static routes for your CN2 cluster.

IN THIS SECTION

- Understanding Static Routes | 236
- Static Routes in CN2 | 236
- Configure Static Routes for a Virtual Network | 238
- Configure Static Routes for a VMI | 238

- Configure Static Routes on Pod Interfaces | 244
- Configure Static Routes for a Virtual Network with a NAD | 246
- Multiple Static Routes on Pod Interfaces | 247
- Troubleshooting RouteTable and InterfaceRouteTable | **249**
- Dataplane Verification | 249
- Config Plane Verification | 250

Understanding Static Routes

You can use static routes when a network doesn't require the complexity of a dynamic routing protocol. Routes that are permanent fixtures in routing and forwarding tables are often configured as static routes.

The route consists of a destination prefix and a next-hop forwarding address. The static route is activated in the routing table and inserted into the forwarding table when the next-hop address is reachable. Traffic that matches the static route is forwarded to the specified next-hop address.

Static Routes in CN2

CN2 implements static routes through the following two custom resources (CRs):

• RouteTable: Contains a user-defined network destination prefix, along with an associated next hop (nextHop). The nextHop IP address must be an IP address of a VMI object. A prefix defines the destination network that is reachable via the next hop. A RouteTable lets you define a static route and next-hop pairing, which you can then associate with a RouteTable and a virtual network (VN). The following is an example of a RouteTable CR. Note that the namespace field is not required in this instance.

apiVersion: core.contrail.juniper.net/v3
kind: RouteTable
metadata:

Note that the field nextHopType must have the value ip-address. Any other value results in a user input error. The communityAttributes field allows you to set BGP communities on the route, which are advertised via BGP.

- InterfaceRouteTable: The InterfaceRouteTable configures static routing with the next hop of a virtual machine interface (VMI). An InterfaceRouteTable contains the destination prefix without the need for a statically-configured next hop entry. As with a RouteTable, the prefix defines the destination network. Unlike a RouteTable, you do not need to define a nextHop IP address because when you associate an InterfaceRouteTable with a VMI, the associated VMI acts as the next hop for this prefix.
- The following is an example of an InterfaceRouteTable CR. Note that the namespace field is not required in this instance.

Note that the field nextHopType must have the value ip-address. Any other value results in a user input error.

These CRs are scoped to their respective namespaces and enable you to configure required attributes for static routes.

Configure Static Routes for a Virtual Network

Configure the RouteTable CR to apply static routes to a virtual network (VN). A VN references a RouteTable in it's spec. As a result, when the RouteTable is associated with that VN, the static route is applied. The following is a VN object with an associated RouteTable:

```
apiVersion: core.contrail.juniper.net/v3
kind: VirtualNetwork
metadata:
 namespace: static-route
 name: vn-route
spec:
 v4SubnetReference:
    apiVersion: core.contrail.juniper.net/v1alpha1
   kind: Subnet
   namespace: static-route
   name: vn-subnet
  routeTableReferences:
    - apiVersion: core.contrail.juniper.net/v3
      kind: RouteTable
      namespace: static-route
      name: static-rt
```

Configure Static Routes for a VMI

Configure the interface-route-table annotation on a VMI in order to apply an InterfaceRouteTable to a VMI.

```
apiVersion: v3
kind: VirtualMachineInterface
metadata:
   name: static-route-pod
   namespace: static-route
   annotations:
```

```
core.juniper.net/interface-route-table: '[{"name": "static-rt", "namespace": "static-
route"}]'
spec:
    <VMI_SPEC>
status:
    interfaceRouteTableReferences:
        - apiVersion: core.contrail.juniper.net/v3
        kind: InterfaceRouteTable
        namespace: static-route
        name: static-rt
```

The following is an example kubectl describe vmi output:

```
forwarder-6dff5888fd-59c9l-da8f57ef
Name:
             static-route
Namespace:
Labels:
             back-reference.core.juniper.net/
28ffe95511d099080e315d0bb633ec5334f9250a40c8c9c61825d185=Tag_t2-kubernetes.io_metadata.name-
static-route
              back-reference.core.juniper.net/
5b136ca6d41e33dfb79a3f066e3db71186ade2514d1de62cf7d3a2b7=Tag_t1-core.juniper.net_clusterName-
contrail-k8s-kubemanager-ku
              back-reference.core.juniper.net/
83323440b6198bd1f37a71f0ad4afde199fffd2742ed93cdeea56d4f=InterfaceRouteTable_static-route_to-
zone-1
              back-reference.core.juniper.net/
84befcc656f5c3b04ece96e4d040cd168c3470825052cd9ef6903755=Tag_t1-core.juniper.net_namespace-
static-route
              back-reference.core.juniper.net/
92b2adff92e4dea99659da131af95ac5623ac10275e0a581fcab8c77=InterfaceRouteTable_static-route_to-
right
              back-reference.core.juniper.net/
9793fa23186c25d750b1a724d088a2cd46bff77cc54f819860847259=VirtualNetwork_static-route_left-vn
              back-reference.core.juniper.net/
bcaf7cc535f4f34dd8d9e4a425cebeea7c229e4efc8e2f8ba3821bc8=VirtualMachine_contrail-k8s-kubemanager-
kubernetes-forwarder-6d
              back-reference.core.juniper.net/
ec2031060f3699dd2f7dd888d858d0a51de65fc2e5e62100b85df999=RoutingInstance_static-route_left-vn
              back-reference.core.juniper.net/
f48f4e9c4f6c1dfccc439d752da4c9ee8eb7472a73d7bf5749a050af=Tag_t1-app-forwarder
              back-reference.core.juniper.net/
```

```
f6b670 baed 4845 c6640 bb4 db030 b0 d22 cb3165 a 5e3929 a ad3a 91 fff \texttt{ETag\_t1-pod-template-hash-6dff5888 fd additional template-hash-6dff5888 fd additional template-hash-6dff588 fd additional template-hash-
Annotations: core.juniper.net/interface-route-table: [{"Namespace":"static-route","Name":"to-
right"},{"Namespace":"static-route","Name":"to-zone-1"}]
                                   index: 1/5
                                   interface: eth1
                                   kube-manager.juniper.net/pod-cluster-name: contrail-k8s-kubemanager-kubernetes
                                    kube-manager.juniper.net/pod-name: forwarder-6dff5888fd-59c9l
                                   kube-manager.juniper.net/pod-namespace: static-route
                                   network: left-vn
                                   vmi-address-family: dualStack
API Version: core.contrail.juniper.net/v3
                                  VirtualMachineInterface
Kind:
Metadata:
    Creation Timestamp: 2023-05-04T06:05:15Z
    Finalizers:
          virtualmachineinterface.finalizers.core.juniper.net
    Generation: 2
    Managed Fields:
         API Version: core.contrail.juniper.net/v3
         Fields Type: FieldsV1
          fieldsV1:
              f:metadata:
                    f:finalizers:
                         .:
                         v:"virtualmachineinterface.finalizers.core.juniper.net":
                   f:labels:
                         f:back-reference.core.juniper.net/
ec2031060f3699dd2f7dd888d858d0a51de65fc2e5e62100b85df999:
               f:spec:
                    f:virtualMachineInterfaceMacAddresses:
                         f:macAddress:
         Manager:
                                            manager
         Operation:
                                            Update
                                            2023-05-04T06:05:15Z
         Time:
         API Version: core.contrail.juniper.net/v3
         Fields Type: FieldsV1
          fieldsV1:
               f:status:
                    f:interfaceRouteTableReferences:
                    f:observation:
                   f:routingInstanceReferences:
                   f:state:
```

```
Manager: manager
```

```
Operation:
                 Update
   Subresource: status
                 2023-05-04T06:05:16Z
   Time:
   API Version: core.contrail.juniper.net/v3
   Fields Type: FieldsV1
    fieldsV1:
      f:metadata:
        f:annotations:
          .:
          f:core.juniper.net/interface-route-table:
          f:index:
          f:interface:
          f:kube-manager.juniper.net/pod-cluster-name:
          f:kube-manager.juniper.net/pod-name:
          f:kube-manager.juniper.net/pod-namespace:
          f:network:
          f:vmi-address-family:
        f:ownerReferences:
          .:
          k:{"uid":"a48fb78d-710b-4d66-9c29-73b77d5db8c6"}:
      f:spec:
        f:portSecurityEnabled:
       f:tagReferences:
       f:virtualMachineReferences:
        f:virtualNetworkReference:
          .:
          f:apiVersion:
          f:kind:
          f:name:
          f:namespace:
          f:resourceVersion:
          f:uid:
    Manager:
                kubemanager
   Operation: Update
                2023-05-04T06:05:17Z
   Time:
 Owner References:
   API Version:
                           core.contrail.juniper.net/v3
   Block Owner Deletion: true
   Controller:
                           true
    Kind:
                           VirtualMachine
                           contrail-k8s-kubemanager-kubernetes-
   Name:
forwarder-6dff5888fd-59c91-65da579d
   UID:
                           a48fb78d-710b-4d66-9c29-73b77d5db8c6
```

```
43839
 Resource Version:
 UID:
                           bbe79a87-fda4-4a2d-be5f-52ecad9863e2
Spec:
 Allowed Address Pairs:
 Fg Name:
    default-domain
   static-route
    forwarder-6dff5888fd-59c9l-da8f57ef
  Parent:
 Port Security Enabled: true
 Properties:
 Tag References:
   API Version: core.contrail.juniper.net/v3
   Fq Name:
      t1-core.juniper.net_namespace-static-route
    Kind:
                      Tag
                       t1-core.juniper.net_namespace-static-route
   Name:
   Resource Version: 43153
   UID:
                      c6bc3209-03c0-4c42-92fe-a71bcf5d2268
   API Version:
                      core.contrail.juniper.net/v3
   Fq Name:
      t1-core.juniper.net_clusterName-contrail-k8s-kubemanager-kubernetes
   Kind:
                      Tag
                       t1-core.juniper.net_clusterName-contrail-k8s-kubemanager-kubernetes
   Name:
   Resource Version: 5169
                       72bf6479-90c2-4c57-97ca-214f0ddeec38
   UID:
                      core.contrail.juniper.net/v3
   API Version:
   Fq Name:
      t1-app-forwarder
   Kind:
                      Tag
                       t1-app-forwarder
   Name:
   Resource Version: 43297
   UID:
                       c31f28bb-efba-4793-bd2f-567fd3ff396d
   API Version:
                       core.contrail.juniper.net/v3
   Fq Name:
      t1-pod-template-hash-6dff5888fd
   Kind:
                      Tag
                       t1-pod-template-hash-6dff5888fd
   Name:
   Resource Version: 43298
   UID:
                       7add9d84-8db2-4ddc-b32a-6f2ba06182ee
   API Version:
                      core.contrail.juniper.net/v3
   Fq Name:
      t2-kubernetes.io_metadata.name-static-route
```

```
Kind:
                       Tag
    Name:
                       t2-kubernetes.io_metadata.name-static-route
   Resource Version: 43178
                       ed588b5a-bc07-4ab4-b163-016ab16924ee
   UID:
 Virtual Machine Interface Mac Addresses:
    Mac Address:
      02:bb:e7:9a:87:fd
 Virtual Machine References:
   API Version: core.contrail.juniper.net/v3
   Fq Name:
     contrail-k8s-kubemanager-kubernetes-forwarder-6dff5888fd-59c91-65da579d
   Kind:
                      VirtualMachine
   Name:
                       contrail-k8s-kubemanager-kubernetes-forwarder-6dff5888fd-59c91-65da579d
   Resource Version: 43434
                       a48fb78d-710b-4d66-9c29-73b77d5db8c6
   UID:
 Virtual Network Reference:
   API Version: core.contrail.juniper.net/v3
   Fq Name:
     default-domain
      static-route
     left-vn
   Kind:
                      VirtualNetwork
                      left-vn
   Name:
   Namespace:
                      static-route
   Resource Version: 42804
   UID:
                       41ab021d-0b55-4598-bc32-abf954708fd0
Status:
 Interface Route Table References:
   API Version: core.contrail.juniper.net/v3
   Fq Name:
     static-route
     to-right
   Kind:
                      InterfaceRouteTable
                       to-right
    Name:
   Namespace:
                      static-route
   Resource Version: 42473
   UID:
                      912aa23d-fb26-4181-8c42-880ebe9f1a9b
   API Version:
                      core.contrail.juniper.net/v3
   Fq Name:
      static-route
     to-zone-1
   Kind:
                      InterfaceRouteTable
                       to-zone-1
    Name:
```

Namespace: static-route Resource Version: 42475 UID: a2cfce5c-cb31-4a24-b432-16bdb8318bd6 Observation: Routing Instance References: API Version: core.contrail.juniper.net/v3 Attributes: Direction: both Fq Name: default-domain static-route left-vn left-vn Kind: RoutingInstance Name: left-vn Namespace: static-route UID: 300cda6a-a7fa-4f79-a815-dc3d7c0a46e7 Success State: Events: <none>]

Note the Interface Route Table References section. This section shows the association between the listed InterfaceRouteTables and VMIs.

Configure Static Routes on Pod Interfaces

You can use the annotation section of a pod's manifest to configure static routes for a pod's default or secondary interface. The pod reconciler processes the annotation section to create a VMI object with an associated InterfaceRouteTable. The reconciler looks for the string key: "core.juniper.net/interface-route-table" in the annotation section. The pod's VMI uses that string as a metadata label to associate with an InterfaceRouteTable.

The following is an example of a pod manifest with an InterfaceRouteTable defined for the default interface:

```
apiVersion: v1
kind: Pod
metadata:
   name: static-route-pod
   namespace: static-route
   annotations:
```

Note the securityContext fields. These fields are necessary because the pod must have permission to change it's routing table in order to utilize the configured route.

The following is an example of a pod manifest with an InterfaceRouteTable defined for the secondary interface:

```
apiVersion: v1
kind: Pod
metadata:
 name: static-route-pod
 namespace: static-route
 annotations:
    k8s.v1.cni.cncf.io/networks: |
      Ε
       {
          "name": "vn-route",
          "namespace": "static-route",
          "cni-args": {
            "core.juniper.net/interface-route-table": "[{\"name\": \"vmi-rt\", \"namespace\":
\"static-route\"}]"
          }
       }
     ]
spec:
 containers:
    - name: praqma
      image: <image-repository>:<tag>
      imagePullPolicy: Always
      securityContext:
        capabilities:
```

```
add:
- NET_ADMIN
privileged: true
```

Note that the name for the primary interface InterfaceRouteTable is vmi-rt and that the name for the secondary interface is vn-route. Defining two InterfaceRouteTables with different names in the same namespace automatically creates an InterfaceRouteTable for the primary and secondary interface of that pod.

Configure Static Routes for a Virtual Network with a NAD

You can also specify static route properties in a network attachment definition (NAD) object. After the NAD is reconciled or applied, a RouteTable is created and the resulting VN object references that RouteTable. The following is an example of a NAD with static route information defined:

```
apiVersion: "k8s.cni.cncf.io/v1"
kind: NetworkAttachmentDefinition
metadata:
  name: vn-route
  namespace: static-route
  labels:
    vn: vn-route
  annotations:
    juniper.net/networks: '{
      "ipamV4Subnet": "108.108.2.0/24"
      "routeTableReferences": '[{"name": "vn-rt", "namespace": "static-route"}]'
    }'
spec:
  config: '{
  "cniVersion": "0.3.1",
  "name": "vn-route",
  "type": "contrail-k8s-cni"
}'
```

Multiple Static Routes on Pod Interfaces

Using InterfaceRouteTable, you can associate multiple static routes to a single pod interface (VMI). This means that that VMI object has multiple next hop destinations, depending on the IP prefix. You can specify multiple InterfaceRouteTable references using cluster service version (CSV) syntax or JSON syntax annotations.

NOTE: You must reference an InterfaceRouteTable in a "namespace/name" format. In the following example, static-route is the namespace and to-right and to-zone-1 are the InterfaceRouteTable objects, or next hop destination for the left-vn VMI.

The following example is a Deployment with multiple InterfaceRouteTable references:

```
apiVersion: apps/v1
kind: Deployment
metadata:
  name: forwarder
  namespace: static-route
  labels:
    app: forwarder
spec:
  replicas: 3
  selector:
    matchLabels:
      app: forwarder
  template:
    metadata:
      labels:
        app: forwarder
      annotations:
        k8s.v1.cni.cncf.io/networks: |
          Ε
           {
             "name": "left-vn",
             "namespace": "static-route",
              "cni-args": {
               "core.juniper.net/interface-route-table": "static-route/to-right, static-route/to-
zone-1"
             }
           },
```

```
{
         "name": "right-vn",
         "namespace": "static-route",
         "cni-args": {
           "core.juniper.net/interface-route-table": "static-route/to-left"
         }
       },
       {
         "name": "zone-1",
         "namespace": "static-route",
         "cni-args": {
           "core.juniper.net/interface-route-table": "static-route/to-left"
         }
       },
       {
         "name": "zone-2",
         "namespace": "static-route",
          "cni-args": {
           "core.juniper.net/interface-route-table": "static-route/to-left"
         }
       }
      ]
spec:
  containers:
    - name: praqma
      image: <repository>:<tag>
      securityContext:
        capabilities:
          add:
            - NET_ADMIN
        privileged: true
```

The following example is a pod manifest with multiple InterfaceRouteTable references using JSON syntax:

```
apiVersion: v1
kind: Pod
metadata:
  name: irt-right
  namespace: static-route
  annotations:
     k8s.v1.cni.cncf.io/networks: |
     [{
```

```
"name": "right-vn",
          "namespace": "static-route",
          "cni-args": {
               "core.juniper.net/interface-route-table": "[{\"namespace\": \"static-route\",
"\name\": \"to-left\"}, {\"namespace\": \"static-route\", \"name\": \"to-zone-1\"}]"
            }
      }]
spec:
 containers:
    - name: praqma
      image: <image-repository>:<tag>
      securityContext:
        capabilities:
          add:
            - NET_ADMIN
        privileged: true
```

NOTE: You must use backward slashes in JSON syntax. Backward slashes are required to encode a JSON string inside another JSON string.

Troubleshooting RouteTable and InterfaceRouteTable

Dataplane Verification

- In the vRouter introspect, verify that the VRF of the VN shows a row with a matching static route prefix specified in the RT using the following steps:
 - Access vRouter introspect at https://<vrouter_ip>:8085/Snh_VrfListReq
 - Verify that the VRF is associated with the VN.
 - Navigate to the ucindex column in the VRF unicast RouteTable.
 - Verify that the table contains a row with the correct static route prefix.
- In the introspect, verify that the next hop properties of the VN are accurate and as desired. In the introspect, the next hop column for the prefix should contain the following:

- The next hop interface name must be a valid tap interface.
- The label must be a positive integer.
- The resolved value must be true.
- The route-type: value must be InterfaceStaticRoute.

Config Plane Verification

- Verify the state of the RouteTable and InterfaceRouteTable objects.
 - Check the status of the reconciler for the InterfaceRouteTable object.

kubectl get interfaceroutetable -n

• Check the status of the reconciler for the RouteTable object.

kubectl get routetable -n

- Verify the RouteTable reference in the associated VN. Verify the InterfaceRouteTable reference in the associated VMI.
 - Check the status of the reconciler for the VMI. You should see the InterfaceRouteTable in the VMI with an associated universally unique identifier (UUID) the Contrail FQ (meta info such as apiversion, kind, namespace, name) name.

kubectl get vmi -n -oyaml | grep -i interfaceRouteTable

kubectl get vn -n -oyaml | grep -i routeTable

VPC to CN2 Communication in AWS EKS

SUMMARY

Juniper Cloud-Native Contrail Networking (CN2) release 23.1 supports communication between AWS virtual private cloud (VPC) networks, external networks, and CN2 clusters. This feature only applies to AWS EKS environments using CN2 as the CNI. This article provides information about how CN2 implements this feature.

IN THIS SECTION

- Understanding Kubernetes and VPC Networks | 251
- Prerequisites | 252
- Gateway Service Instance Components | 252
- Custom Resource Implementation | 256
- Custom Controller Implementation | 258
- Troubleshooting | 258

Understanding Kubernetes and VPC Networks

Typically, you cannot access a Kubernetes workload in an overlay network running on Amazon Elastic Kubernetes Service (EKS) from a VPC. In order to achieve AWS VPC to Kubernetes communication, you must expose the host network of your Kubernetes cluster to the VPC. Although some public cloud Kubernetes distributions offer solutions that support this feature, these solutions are tailored for traditional VM workloads instead of Kubernetes workloads. As a result, these solutions have the following drawbacks:

- You must configure pod IPs as secondary IP addresses on node interfaces. This imposes resource constraints on the nodes, reducing the number of pods that can be supported.
- Services are exposed through public Load Balancers. Every time a service is created, the Load Balancer begins an instantiation process which might result in more time until service exposure

CN2 release 23.1 addresses this issue by introducing a Gateway Service Instance (GSI). A GSI is a collection of Amazon Web Service (AWS) and Kubernetes resources that work together to seamlessly interconnect CN2 with VPC and external networks. Apply a GSI manifest and CN2 facilitates communication between pods and services in an Amazon EKS cluster and workloads in the same VPC.

Prerequisites

The following are required to enable VPC to CN2 communication:

- A license for cRPD. To purchase a license, visit https://www.juniper.net/us/en/products/routers/ containerized-routing-protocol-daemon-crpd.html
 - You must install the license into the EKS cluster as a Secret within the contrail-gsi namespace.
 - The secret must contain the base64-encoded version of the license under the crpd-license key of .Data.
 - The following is an example Secret with a reference to a license:

```
apiVersion: v1
kind: Secret
metadata:
   name: crpd-license
   namespace: contrail-gsi
data:
   crpd-license: ***** # base64 encoded crpd license
```

- An EKS cluster running CN2 release 23.1 or later
- AWS Identity and Access Management (IAM) role access. See the following link for instructions about how to configure a service account to assume an IAM role: "Configure a Service Account to Assume an IAM role" on page 265
- Nodes within the EKS cluster must have the label: core.juniper.net/crpd-node: "".
 - The controller will only schedule the cRPD container on nodes with the following key: core.juniper.net/crpd-node. After this label is added onto a node, none of the CN2 controllers (including the vRouter) will run on this node. This ensures that the proper amount of nodes are reserved for cRPD containers.

Gateway Service Instance Components

The following is an example of a gateway service instance (GSI) manifest:

apiVersion: v1 kind: Namespace

```
metadata:
 name: contrail-gsi
---
apiVersion: v1
kind: ServiceAccount
metadata:
 name: contrail-gsi-serviceaccount
 namespace: contrail-gsi
---
apiVersion: rbac.authorization.k8s.io/v1
kind: ClusterRole
metadata:
 name: contrail-gsi-role
rules:
- apiGroups:
 - '*'
  resources:
  - '*'
 verbs:
  - '*'
---
apiVersion: rbac.authorization.k8s.io/v1
kind: ClusterRoleBinding
metadata:
 name: contrail-gsi-rolebinding
roleRef:
  apiGroup: rbac.authorization.k8s.io
  kind: ClusterRole
 name: contrail-gsi-role
subjects:
- kind: ServiceAccount
 name: contrail-gsi-serviceaccount
 namespace: contrail-gsi
---
apiVersion: plugins.juniper.net/v1alpha1
kind: GSIPlugin
metadata:
 name: contrail-gsi-plugin
 namespace: contrail-gsi
spec:
  awsRegion: "us-east-2"
  iamRoleARN: "arn:aws:iam::******"
  vpcID: "vpc-********"
```

common:
containers:
<pre>- image: <repository>/contrail-gsi-plugin:<tag></tag></repository></pre>
<pre>imagePullPolicy: Always</pre>
name: contrail-gsi-plugin
initContainers:
- command:
- kubectl
- apply
k
- /crd
<pre>image: <repository>/contrail-gsi-plugin-crdloader:<tag></tag></repository></pre>
imagePullPolicy: Always
name: contrail-gsi-plugin-crdloader
<pre>serviceAccountName: contrail-gsi-serviceaccount</pre>

Note that the awsRegion, iamRoleARN, and vpcID fields are user-defined. The iamRoleARN value is the Amazon Resource Name (ARN) of the IAM Role that you create as part of the prerequisites for this feature.

Applying a GSI manifest creates a custom controller that creates and manages the following:

AWS resources:

- Transit gateway: A transit gateway is a network transit hub that can interconnect VPCs. A transit gateway can have Attachments which are one or more VPCs.
- Connect attachment: A transit gateway connect attachment establishes a connection between a transit gateway and third-party virtual appliances (JCNRs) running in a VPC. After you create a connect attachment, one or more Generic Routing Encapsulation (GRE) tunnels, or Transit Gateway Connect peers, can be created on the Connect attachment to connect the transit gateway and the third-party appliance. A Transit Gateway Connect peer is comprised of two BGP peering sessions over the GRE tunnel which provide routing redundancy. After you install the transit gateway resource, CN2 performs this process automatically.
- VPC attachment: A VPC Attachment attaches to a transit gateway. When you attach a VPC to a transit gateway, resource and routing rules apply to that gateway.

Kubernetes resource:

• Connected peers: A transit gateway connect peer is a GRE tunnel that facilitates communication between a transit gateway and a third-party appliance or JCNR.

CN2 GSI resource:


• Juniper Cloud-Native Router (JCNR): JCNR is an extension of CN2 that acts as a gateway between EC2 instances and other AWS resources and the EKS cluster running CN2.

JCNRs do the following:

- Connect via Multiprotocol BGP (MP-BGP) to CN2 control nodes and use MPLSoUDP in the data plane
- Provide active/active L3 and L4 load balancing across the CN2 EKS nodes

You can scale JCNRs and their connected peers to a maximum of four instances. In this case, a transit gateway provides active/active L3 and L4 load balancing across the JCNRs. As an example of JCNR functionality, if you add a label onto a VN that you want to expose, the JCNR advertises that VN's subnet to the transit gateway. A next hop route between the VN's subnet and the transit gateway is added to the VPC's routing table. As a result, the VN is routed in the VPC's network and accessible via workloads within the VPC. This functionality is similar to a traditional physical SDN gateway, where the transit gateway and the JCNR act as a physical gateway between the EKS cluster and the rest of the AWS environment without the drawbacks of hostNetwork.

The following illustration depicts connectivity in a typical Amazon EKS cluster. Note that CN2 automatically generates the VPC Routing Table.



Custom Resource Implementation

CN2 implements this feature through the following custom resources (CRs):

• TransitGateway: Represents the AWS TransitGateway resource.

- Route: Represents an entry in a VPC routing table. A Route is an internally-created object that doesn't
 require user input.
- ConnectedPeer: Represents an appliance (JCNR in CN2) that establishes BGP sessions with the transit gateway. A ConnectedPeer is an internally-created object that doesn't require user input.

The following is an example of a TransitGateway manifest.

```
apiVersion: core.gsi.juniper.net/v1
kind: TransitGateway
metadata:
  name: tgw1
  namespace: contrail-gsi
spec:
  subnetIDs:
    - subnet-*****
    - subnet-*****
    - subnet-*****
  connectedPeerScale: 1
  transitASN: 64513
  peerASN: 64513
  transitCIDR: 192.0.2.0/24
  bgpCidr: 169.254.10.0
  controlNodeASN: 64512
  licenseSecretName: crpd-license
  controllerContainer:
    name: controller
    command: ["/manager", "-mode=client"]
    image: <repository>/contrail-gsi-plugin:<tag>
    imagePullPolicy: Always
  crpdContainer:
    name: crpd
    image: <repository>/crpd:<tag>
  initContainer:
    name: init
    image: <repository>/busybox:<tag>
```

Use the following command for detailed information about the TransitGateway spec:

kubectl explain transitgateway.spec

Custom Controller Implementation

The GSI is implemented through the use of custom Kubernetes controllers with a client/server plugiin. The server-side custom controllers run on the CN2 control plane nodes. The client runs alongside JCNR. These controllers are automatically configured when you apply the TransitGateway and GSI objects.

Troubleshooting

This section provides information about troubleshooting various ConnectedPeer connectivity issues, custom controller issues, and workload reachability issues.

For custom controller issues:

• After you apply the GSI manifest, ensure that all of the custom controller pods associated with the GSI manifest (Server, Client) are active.

kubectl get pods -n contrail-gsi -l app=contrail-gsi-plugin

The CLI output should show three active controller pods in a regular EKS deployment. If you don't receive the correct CLI output, use the following command to verify that the GSI plugin is installed.

kubectl get gsiplugins -n contrail-gsi

Check the logs of the contrail-k8s-deployer pod. Filter results for the GSI plugin reconciler and look for any errors.

- Ensure that the custom controllers can make create, read, update, delete (CRUD) requests to the required AWS resources.
 - Check the logs of the contrail-gsi pods; one of the three pods should be active and will output log messages.
 - Verify that the logs of the active pod don't contain errors about not being able to make API calls to AWS. If you do see these errors, ensure that the IAM role granted to the contrail-gsi-serviceaccount is configured properly (refer to the "Prerequistes" on page 252 section of this topic).

For TransitGateway issues:

• After you install the TransitGateways, ensure that their statuses change from "pending" to "available."

• Ensure that the ConnectedPeer/cRPD pod is active.

kubectl get pods -n contrail-gsi -l app=connectedpeer

If no pods show up in the output, ensure that a node is available for the ConnectedPeer pod to be scheduled on. A valid pod contains the following label: core.juniper.net/crpd-node: "".

For ConnectedPeer issues:

• After a ConnectedPeer pod is active, ensure that the cRPD can establish BGP sessions with CN2 control nodes, and AWS's transit gateway. Run the following command in the CLI of the cRPD:

show bgp summary

This process might fail for the following reasons:

- A valid, active license is not installed in the cluster
- IP connectivity for BGP is not correct

For workoad reachability issues:

- If you cannot access an EKS cluster from an EC2 instance:
 - Ensure that the workload's VN is exposed to the TransitGateway.
 - Ensure that the route from the exposed VN to the VPC appears in the VPC's routing table.
 - Ensure that the EC2 instance has security groups configured to access the CIDR of the VN.
 - The custom controllers automatically create one security group (gsi-sg) that allows access to all of the routes exposed to a transit gateway.


Stickiness for Load-Balanced Flows


Starting in Contrail Networking Release 23.2, CN2 supports flow stickiness. Flow stickiness helps minimize flow remapping across equal-cost multipath (ECMP) groups in a load-balanced system.

Traditional ECMP load-balances traffic over a number of available paths toward a destination. When one path fails (scale-down) or a new path gets added (scale-up), the traffic gets reshuffled over the available number of paths. Flow stickiness reduces the flow being remapped and retains the flow with the original

path when the ECMP group's member change. When a flow is affected by a member change, the vRouter reprograms the flow table and rebalances the flow.

Figure 1 on page 260 shows an example of a flow remapping scenario that occurs when a new member is added to a 3-member ECMP load-balancing system.





In this example, a flow request is sent to IP address: 172.16.0.20. Because this three members group have the virtual IP address: 172.16.0.20, the vRouter sends the request to pod1 based on the flow hash calculation. When a new member (pod4) is added to the same virtual IP group, the request is diverted and redirected to pod4 based on the flow hash recalculation.

Flow stickiness reduces the flow being remapped and retains the flow with the original path to pod1 through the new member (pod4). If adding pod4 affects the flow, the vRouter reprograms the flow table and rebalances the flow with pod1.

Table 1 on page 261 shows the expected results for normal hash and flow stickiness for scale-up and scale-down scenarios.

Example Scenario	Normal (Static) Hash Result	Flow Stickiness Result
ECMP group size is 3.	Based on the flow hash, traffic is directed to pod1.	Based on the flow hash, traffic is directed to pod1.
Adding one more pod to the same service. ECMP group size is 4.	Flow redistribution is possible and traffic can be redirected to another pod.	Traffic continues to be directed to pod1.
Deleting one pod from same service. ECMP group size is 2.	Flow redistribution is possible and traffic can be redirected to another pod.	Unless pod1 is deleted, traffic continues to be directed to pod1. If pod1 is deleted, the session must be reinitiated from client.

Table 17: Expected Results: Members Added or Deleted from an ECMP Group

NOTE: Flow stickiness is only supported for an ECMP flow before and after scale up (stickiness is not maintained when scaling up from one pod to multiple pods). We recommend that you add at least two pods to an ECMP group and then scale up.

RELATED DOCUMENTATION

Customized Hash Field Selection for ECMP Load Balancing

Configure BFD Health Check for BGPaaS Sessions

SUMMARY

This topic describes how to configure Bidirectional Forwarding and Detection (BFD) health check for BGP as a Service (BGPaaS) sessions. Juniper Networks supports this feature using Contrail Networking Release 23.2 or later in a Kubernetesorchestrated environment.

IN THIS SECTION

Configure BFD Health Check | 262

Bidirectional Forwarding and Detection (BFD) is a protocol-based health check. This topic describes how to configure BFD for BGPaaS sessions in CN2.

NOTE: BFD health check for BGPaaS is not the same as the BFD health check over the virtual machine interface (VMI) feature. You cannot use BFD health check for VMIs. This is because the BGPaaS session shares the same tenant destination address over a set of VMIs, with only one VMI active at any given time.

To configure BFD health check for BGPaaS, you must associate the health check service with a BGPaaS object. This association triggers the establishment of BFD sessions to all BGPaaS neighbors for that service. If the BFD session goes down, the resulting BGPaaS session terminates and the routes are withdrawn.

NOTE: It is not necessary for a BFD session to be Up to establish a BGP neighbor.

Whenever BFD health check detects a BFD session as Up or Down, corresponding logs are generated. Logging is enabled in the contrail-vrouter-agent.conf file with the log level SYS_NOTICE. You can view the log file in the location /var/log/contrail/vrouter-agent.log.

The following is a snippet of a sample log message for BFD session events:

2023-02-26 Tue 14:38:49:417.479 SYS_NOTICE BFD session Down interface: test-bfd-hc-vmi.st2 vrf: default-domain:admin:VN.hc.st2:VN.hc.st2 2023-02-26 Tue 14:38:49:479.733 PST SYS_NOTICE BFD session Up interface: test-bfd-hc-vmi.st2 vrf: default-domain:admin:VN.hc.st2:VN.hc.st2

Configure BFD Health Check

To configure BFD health check for BGPaaS, you must associate the health check service with a BGPaaS object.

NOTE: We assume that you've already performed the preliminary steps required to establish a BGPaaS session without BFD (create the NAD (virtual network and subnet) and create the pod with appropriate references to the attached VN). For instructions, see Enable BGP as a Service.

To set up the BGPaaS session with BFD Service Health Check:

1. Create the ServiceHealthCheck and BGPAsAService objects, as shown in the following examples:

NOTE: Under ServiceHealthCheckProperties, you can specify delay, delayUSecs, or both. Delay is calculated in seconds whereas delayUsecs is calculated in microseconds. In the following example, packets are sent with a delay of 2 seconds and 200000 microseconds (2.2 seconds).

```
apiVersion: core.contrail.juniper.net/v4
kind: ServiceHealthCheck
metadata:
  name: bfd-hc
  namespace: bfd-on-bgpaas
spec:
  serviceHealthCheckProperties:
    delay: 2
    delayUsecs: 200000
    enabled: true
    healthCheckType: link-local
    maxRetries: 2
    monitorType: BFD
    timeoutUsecs: 500000
apiVersion: core.contrail.juniper.net/v4
kind: BGPAsAService
metadata:
  namespace: bfd-on-bgpaas
  name: bgpaas-test
spec:
  shared: false
  autonomousSystem: 10
  bgpAsAServiceSessionAttributes:
    loopCount: 2
    routeOriginOverride:
      origin: EGP
    addressFamilies:
      family:
        - inet
        - inet6
  serviceHealthCheckReference:
```

```
apiVersion: core.contrail.juniper.net/v4
kind: ServiceHealthCheck
namespace: bfd-on-bgpaas
name: bfd-hc
virtualMachineInterfacesSelector:
    matchLabels:
        core.juniper.net/bgpaasVN: bgpaas-vn-1
    matchLabels:
        core.juniper.net/bgpaasVN: bgpaas-vn-2
```

- **2.** Verify your configuration.
 - Enter the kubectl get ServiceHealthCheck -n bfd-on-bgpaas command to verify that the object was created. For example:

kubectl get ServiceHealthCheck -n bfd-on-bgpaasNAMEMONITORTYPEENABLEDHEALTHCHECKTYPEMAXRETRIESTIMEOUTbfd-hcBFDtruelink-local20

• Enter the kubectl describe servicehealthcheck bfd-hc -bfd-on-bgpaas command. The object is successfully created when the State field indicates **Success**. For example:

Spec:	
Fq Name:	
bfd-on-bgpaas	
bfd-hc	
Service Health Check	Properties:
Delay:	2
Delay Usecs:	200000
Enabled:	true
Health Check Type:	link-local
Max Retries:	2
Monitor Type:	BFD
Timeout:	0
Timeout Usecs:	500000
Status:	
Observation:	
State: Success	

• Verify the status of the BFD session you just created.

kubectl get bgg	basaservice -A					
NAMESPACE	NAME	AS	IPADDRESS	SHARED	STATE	AGE
bfd-on-bgpaas	bgpaas-test-1	10		false	Success	21h
bfd-on-bgpaas	bgpaas-test-2	11		false	Success	21h

SEE ALSO

Understanding BGP as a Service Enable BGP as a Service Bidirectional Forwarding Detection

Configure a Service Account to Assume an IAM role

SUMMARY

This topic provides information about how to configure a Kubernetes service account to assume an AWS Identity and Access Management (IAM) role. This is a prerequisite for configuring VPC to CN2 communication in Juniper Cloud-Native Contrail release 23.1.

IN THIS SECTION

 Configure a Service Account to Assume an IAM Role | 265

Configure a Service Account to Assume an IAM Role

CN2 release 23.1 supports the ability to access Amazon VPC networks from CN2 or EKS clusters. In order to enable this feature, you must associate a Kubernetes service account with an AWS IAM role. Since this feature creates AWS resources, the custom CN2 controllers that reside in the contrail-gsi namespace need create, read, update, and delete (CRUD) access for these resources.

In order to grant CRUD access to the custom CN2 controllers, you must configure a service account to assume an IAM role with access to the CRUD operations the controllers must perform. Follow the steps in the following Amazon Web Services link to complete this process: Configuring a Kubernetes service account to assume an IAM role.

In step 1a under the "To associate an IAM role with a Kubernetes account" section, you are prompted to create a file that includes permissions for the AWS services that you want your controller pods to access. Juniper provides the JSON file below for this purpose.

```
{
    "Version": "2012-10-17",
    "Statement": [
        {
            "Sid": "Stmt1674864366447",
            "Action": [
                "ec2:AuthorizeSecurityGroupEgress",
                "ec2:AuthorizeSecurityGroupIngress",
                "ec2:CreateRoute",
                "ec2:CreateSecurityGroup",
                "ec2:CreateTags",
                "ec2:CreateTransitGateway",
                "ec2:CreateTransitGatewayConnect",
                "ec2:CreateTransitGatewayConnectPeer",
                "ec2:CreateTransitGatewayVpcAttachment",
                "ec2:DeleteRoute",
                "ec2:DeleteSecurityGroup",
                "ec2:DeleteTags",
                "ec2:DeleteTransitGateway",
                "ec2:DeleteTransitGatewayConnect",
                "ec2:DeleteTransitGatewayConnectPeer",
                "ec2:DeleteTransitGatewayVpcAttachment",
                "ec2:DescribeRouteTables",
                "ec2:DescribeSecurityGroups",
                "ec2:DescribeTags",
                "ec2:DescribeTransitGatewayConnectPeers",
                "ec2:DescribeTransitGatewayConnects",
                "ec2:DescribeTransitGatewayVpcAttachments",
                "ec2:DescribeTransitGateways",
                "ec2:RevokeSecurityGroupEgress",
                "ec2:RevokeSecurityGroupIngress"
            ],
            "Effect": "Allow",
            "Resource": "*"
        }
    ]
}
```

In step 2, you are prompted to create a Kubernetes service account. You can use the example service account YAML provided in the AWS article, but you must use contrail-gsi for the namespace and contrail-gsi-serviceaccount for the name of the service account.

RELATED DOCUMENTATION

VPC to CN2 Communication in AWS EKS | 251



Configure DPDK

Deploy DPDK vRouter | 269

Deploy DPDK vRouter

IN THIS SECTION

- DPDK Overview | 269
- DPDK vRouter Support for DPDK and Non-DPDK Workloads | 270
- Non-DPDK Pod Overview | 270
- DPDK Pod Overview | 270
- Mix of Non-DPDK and DPDK Pod Overview | 271
- DPDK vRouter Architecture | 271
- DPDK Interface Support for Containers | 271
- DPDK vRouter Host Prerequisites | 272
- Deploy a Kubernetes Cluster with DPDK vRouter in Compute Node | 274
- DPDK vRouter Custom Resource Settings | 275

DPDK Overview

Cloud-Native Contrail[®] Networking[™] supports the Data Plane Development Kit (DPDK). DPDK is an open-source set of libraries and drivers for rapid packet processing. Cloud-Native Contrail Networking accelerates container networking with DPDK vRouter technology. DPDK enables fast packet processing by allowing network interface cards (NICs) to send direct memory access (DMA) packets directly into an application's address space. This method of packet routing lets the application poll for packets, which prevents the overhead of interrupts from the NIC.

Utilizing DPDK enables the Cloud-Native Contrail vRouter to process more packets per second than it could when running as a kernel module DPDK interface for container service functions. CN2 utilizes DPDK vRouter's processing power leverages the processing power for high-demand container service functions.

When you provision a Contrail compute node with DPDK, the corresponding YAML file specifies the:

- Number of CPU cores to use for forwarding packets.
- Number of huge pages to allocate for DPDK.
- UIO driver to use for DPDK.

DPDK vRouter Support for DPDK and Non-DPDK Workloads

When a container or pod needs access to the DPDK vRouter, the following workload types occur:

- Non-DPDK workload (pod): This workload includes non-DPDK pod applications that are unaware of the underlying DPDK vRouter. These applications are not designed for DPDK and do not use DPDK capabilities. In Cloud-Native Contrail Networking, this workload type functions normally in a DPDK vRouter-enabled cluster.
- 2. Containerized DPDK workload: These workloads are built on the DPDK platform. DPDK interfaces are brought up using (Virtual Host) vhost protocol, which acts as a datapath for management and control functions. The vhost protocol enables virtualized host devices to be mapped to virtual input & output (virtio) devices. Pods act as the vHost Server, and the underlying DPDK vRouter acts as the vHost Client.
- **3.** Mix of Non-DPDK and DPDK workloads: The management or control channel on an application in this pod is a non-DPDK (Veth pair), and the datapath is a DPDK interface. A Veth pair is a pair of connected virtual Ethernet interfaces.

Non-DPDK Pod Overview

A virtual ethernet (Veth) pair plumbs the networking of a non-DPDK pod. One end of the Veth pair attaches to the pod's namespace. The other end attaches to the kernel of the host machine. The Container Networking Interface (CNI) establishes the Veth pair and allocates IP addresses using IP Address Management (IPAM).

DPDK Pod Overview

A DPDK pod contains a vhost interface and a virtio interface. The pod uses the vhost interface for management purposes and the virtio interface for high-throughput packet processing applications. A DPDK application in the pod uses the vhost protocol to establish communication with the DPDK vRouter in the host. The DPDK application receives an argument to establish a filepath for a UNIX socket. The vRouter uses this socket to establish the control channel, run negotiations, and create vrings over huge pages of shared memory for high-speed datapaths.

Mix of Non-DPDK and DPDK Pod Overview

This pod might contain non-DPDK and DPDK applications. A non-DPDK application uses a non-DPDK interface (Veth pair), and the DPDK application uses the DPDK interfaces (vhost, virtio). These two workloads occur simultaneously.

DPDK vRouter Architecture

The Contrail DPDK vRouter is a container that runs inside the Contrail compute node. The vRouter runs as either a Linux kernel module or a user space DPDK process. The vRouter is responsible for transmitting packets between virtual workloads (tenants, guests) on physical devices. The vRouter also transmits packets between virtual interfaces and physical interfaces.

The CN2 vRouter supports the following encapsulation protocols:

- MPLS over UDP (MPLSoUDP)
- MPLS over GRE (MPLSoGRE)
- Virtual Extensible LAN (VXLAN)

Compared with the traditional Linux kernel deployment, deploying the vRouter as a user space DPDK process drastically increases the performance and processing speed of the vRouter application. This increase in performance is the result of the following factors:

- The virtual network functions (VNFs) operating in user space are built for DPDK and designed to take advantage of DPDK's packet processing power.
- DPDK's poll mode drivers (PMDs) use the physical interface (NIC) of a VM's host instead of the Linux kernel's interrupt-based drivers. The NIC's registers operate in user space, which makes them accessible by DPDK's PMDs.

As a result, the Linux OS does not need to manage the NIC's registers. This means that the DPDK application manages all packet polling, packet processing, and packet forwarding of a NIC. Instead of waiting for an I/O interrupt to occur, a DPDK application constantly polls for packets and processes these packets immediately upon receiving them.

DPDK Interface Support for Containers

The benefits and architecture of DPDK usually optimize VM networking. Cloud-Native Contrail Networking lets your Kubernetes containers take full advantage of these features. In Kubernetes, a

containerized DPDK pod typically contains two or more interfaces. The following interfaces form the backbone of a DPDK pod:

- Vhost user protocol (for management): The vhost user protocol is a backend component that interfaces with the host. In Cloud-Native Contrail Networking, the vhost interface acts as a datapath for management and control functions between the pod and vRouter. This protocol comprises the following two planes:
 - The control plane exchanges information (memory mapping for DMA, capability negotiation for establishing and terminating the data plane) between a pod and vRouter through a Unix socket.
 - The data plane is implemented through direct memory access and transmits data packets between a pod and vRouter.
- Virtio interface (for high-throughput applications): At a high level, virtio is a virtual device that transmits packets between a pod and vRouter. The virtio interface is a shared memory (shm) solution that lets pods access DPDK libraries and features.

These interfaces enable the DPDK vRouter to transmit packets between pods. The interfaces give pods access to advanced networking features provided by the vRouter (huge pages, lockless ring buffers, poll mode drivers). For more information about these features, visit A journey to the vhost-users realm.

Applications use DPDK to create vhost and virtio interfaces. The application or pod then uses DPDK libraries directly to establish control channels using Unix domain sockets. The interfaces establish datapaths between a pod and vRouter using shared memory vrings.

DPDK vRouter Host Prerequisites

In order to deploy a DPDK vRouter, you must configure the following huge pages and NICs on the host node. Huge pages enable the OS to use memory pages larger than the default 4KB:

• Huge pages configuration: Specify the percentage of host memory to be reserved for the DPDK huge pages. The following command line shows huge pages set at 2MB:

GRUB_CMDLINE_LINUX_DEFAULT="console=tty1 console=ttyS0 default_hugepagesz=2M hugepagesz=2M hugepages=8192"

The following example allocates four 1GB huge pages and 1024 2MB huge pages:

GRUB_CMDLINE_LINUX_DEFAULT="console=tty1 console=ttyS0 default_hugepagesz=1G

NOTE: We recommend that you allocate 1GB for the huge pages size.

- hugepagesz=1G hugepages=4 hugepagesz=2M hugepages=1024"
- Enable (input-output memory management unit (IOMMU): DPDK applications require IOMMU support. Configure IOMMU settings and enable IOMMU from the BIOS. Apply the following flags as boot parameters to enable IOMMU:

"intel_iommu=on iommu=pt"

• Ensure that the Kernel driver is loaded onto Port Forward 0 (port 0) of the host's NIC. Ensure that DPDK PMD drivers are loaded onto Port Forward 1 (port 1) of the host's NIC.

NOTE: I40E Poll Mode Driver

• PCI driver (vfio-pci, uio_pci_generic): Specify which PCI driver to use based on NIC type.

NOTE: The vfio-pci is built-in.

uio_pci_generic

• Manually install the uio_pci_generic module if needed:

```
root@node-dpdk1:~# apt install linux-modules-extra-$(uname -r)
```

• Verify that the uio_pci_generic module is installed:

```
root@node-dpdk1:~# ls /lib/modules/5.4.0-59-generic/kernel/drivers/uio/
uio.ko uio_dmem_genirq.ko uio_netx.ko uio_pruss.ko
uio_aec.ko uio_hv_generic.ko 'uio_pci_generic.ko' uio_sercos3.ko
uio_cif.ko uio_mf624.ko uio_pdrv_genirq.ko
```

Deploy a Kubernetes Cluster with DPDK vRouter in Compute Node

Cloud-Native Contrail Networking utilizes a DPDK deployer to launch a Kubernetes cluster with DPDK compatibility. This deployer performs lifecycle management functions and applies DPDK vRouter prerequisites. A custom resource (CR) for the DPDK vRouter is a subset of the deployer. The CR contains the following:

- Controllers for deploying Cloud-Native Contrail Networking resources
- Built-in controller logic for the vRouter

Apply the DPDK deployer YAML file, and deploy the DPDK vRouter CR with agentModeType: dpdk using the following command:

kubectl apply -f <vrouter_cr.yaml>

After applying the CR YAML file, the deployer creates a daemonset for the vRouter. This deamonset spins up a pod with a DPDK container.

If you get an error message, ensure that your cluster has the custom resource definition (CRD) for the vRouter using the following command:

kubectl get crds

The following is an example of the output you receive:

NAME	CREATED AT
vrouters.dataplane.juniper.net	2021-06-16T16:06:34Z

If no CRD is present in the cluster, check the deployer using the following command:

kubectl get deployment contrail-k8s-deployer -n contrail-deploy -o yaml

Check the image used by the contrail-k8s-crdloader container. This image should be the latest image the deployer uses. Update the image and ensure that your new pod uses this image.

After you verify that your new pod is running the latest image, use the following command to verify that the CRD for the vRouter is present:

kubectl get crds

After you verify that the CRD for the vRouter is present, use the following command to apply the vRouter CR:

kubectl apply -f <vrouter_cr.yaml>

DPDK vRouter Custom Resource Settings

You can configure the following settings of the vRouter's CR:

- service_core_mask: Specify a service core mask. The service core mask enables you to dynamically
 allocate CPU cores for services.
- You can enter the following input formats:
 - Hexadecimal (for example, 0xf)
 - List of CPUs separated by commas (for example, 1,2,4)
 - Range of CPUs separated by a dash (for example, 1-4)

NOTE: PMDs require the bulk of your available CPU cores for packet processing. As a result, we recommend that you reserve a maximum of 1 to 2 CPU cores for service_core_mask and dpdk_ctrl_thread_mask. These two cores share CPU power.

 cpu_core_mask: Specify a CPU core mask. DPDK's PMDs use these cores for high-throughput packetprocessing applications.

The following are supported input formats:

- Hexadecimal (for example, 0xf)
- List of CPUs separated by commas (for example, 1,2,4)
- Range of CPUs separated by a dash (for example, 1-4)
- dpdk_ctrl_thread_mask: Specify a control thread mask. DPDK uses these core threads for internal processing.

The following are supported input formats:

• Hexadecimal (for example, 0xf)

- List of CPUs separated by commas (for example, 1,2,4)
- Range of CPUs separated by a dash (for example, 1-4)

NOTE: PMDs require the bulk of your available CPU cores for packet processing. As a result, we recommend that you reserve a maximum of 1 to 2 CPU cores for service_core_mask and dpdk_ctrl_thread_mask. These two cores share CPU power.

• dpdk_command_additional_args: Specify DPDK vRouter settings that are not default settings. Arguments that you enter here are appended to the DPDK PMD command line.

The following is an example argument:--yield_option 0.



Configure eBPF

eBPF Kernel Data Plane (Tech Preview) | 278

eBPF Kernel Data Plane (Tech Preview)

SUMMARY

Juniper Cloud-Native Contrail Networking (CN2) release 23.3 supports an extended Berkeley Packet Filter (eBPF) data plane for the Linux kernel. An eBPF-based data plane enables programs to be loaded into the kernel for high-performance applications.

IN THIS SECTION

•	Linux Kernel Overview 278
•	eBPF Overview 279
•	eBPF Kernel Data Plane 280
•	Understanding eBPF Programs 280
•	Events and Hooking 280
•	Helper Functions 280
•	eBPF Maps 281
•	Executing an eBPF Program 281
•	XDP Overview 282
•	XDP and Traffic Control Hooks 282
•	XDP Control and Data Plane 284
•	XDP Action and Behavior 284
•	XDP and eBPF 284
•	Kernel to User Space Communication 285
•	Supported eBPF Features 285
•	Enable eBPF Data Plane 286
•	XDP Supported Drivers 287
•	eBPF Data Plane Design and CN2 Implementation 288
•	eBPF Data Plane Components 288

Linux Kernel Overview

The Linux kernel memory is broadly divided into the following two areas:

• Kernel space: The core of the OS operates in kernel space. The OS has unrestricted access to all host resources including: memory, storage, and CPU. Kernel space is strictly reserved for running a

privileged OS kernel, kernel extensions, and the majority of the host's device drivers. Kernel space is protected and only runs trusted code.

 User-space library: Non-kernel processes, such as regular applications, operate within user-space. The code running in user-space has limited access to hardware resources and typically relies on kernel space for performing privileged operations such as disk or network I/O. User-space applications request a service from the kernel through APIs, or system calls. System calls provide an interface between a process and the OS to allow user-space processes to request services of the OS.

In some cases, a developer might require more kernel performance than is allocated through the system call interface. Custom system calls, support for new hardware, and new file sytems all might require additional kernel flexibility. Cases like this require enhancements to the kernel without adding to its source code. A Linux Kernel Module (LKM) extends the base kernel without adding or altering its source code. LKMs, unlike system calls, are directly loaded into the kernel at runtime. This means that the kernel does not need to be recompiled and rebooted each time a new LKM is required. Although LKMs extend the kernel, when it comes to use cases like high performance packet processing, LKMs are still constrained by the overhead and networking limitations of the kernel itself. Additionally, LKMs often have kernel version compatibility issues that need resolution, and non-upstreamed LKMs can have trust issues.

NOTE: For additional information, see Juniper CN2 Technology Previews (Tech Previews) or contact Juniper Support.

eBPF Overview

The Berkeley Packet Filter (BPF) provides a way to filter packets efficiently, avoiding useless packet copies from kernel to user-space. eBPF is a mechanism for writing code that is executed in kernel space. Developers write eBPF programs in a restricted C language. This code, known as bytecode, is compiled and produced by compiler toolchains like Clang/LLVM.

One security advantage of BPF is the requirement that BPF programs must be verified before becoming active in the kernel. BPF programs run in a virtual machine (VM) in the kernel. The verification process ensures that BPF programs run to completion without looping, within the VM. The verification process also includes checks for valid register state, the size of the program, and out-of-bound-jumps. After the verification process, the program becomes active in the kernel.

eBPF Kernel Data Plane

The eBPF kernel data plane enables you to extend and customize the kernel's behavior more safely and efficiently than is possible with traditional LKMs. Like LKMs, the kernel is not reloaded and the kernel's code is not altered. eBPF in the kernel data plane means that user-space applications can process data as it flows through the kernel. In other words, applications that take advantage of eBPF are written and processed within the kernel, drastically reducing the networking layer overhead of typical kernel processes. Tasks like high-performance packet processing, packet filtering, tracing, and security monitoring all benefit from the additional kernel performance eBPF provides.

Understanding eBPF Programs

Events and Hooking

eBPF programs execute in an event-driven environment. Events are specific situations or conditions that are monitored, traced, or analyzed. For example, network packets arriving at an interface is an event. An eBPF program is attached to this event and can analyze ingress network packets or trace a packet's path.

Hooking refers to the process of attaching an eBPF program to specific execution points within the kernel flow. When a hook triggers, the eBPF program is executed. The eBPF program can modify event behavior or record data related to the event. For example, a system call might act as a hook. When the system call is initiated, a hook triggers, enabling the eBPF program to monitor system processes.

Other examples of hooks include:

- Function entry and exit: The eBPF program intercepts calls to pre-existing functions.
- Network events: The program executes when packets are received on a specified interface.
- Kprobes and Uprobes: The program attaches to probes for kernel or user-space functions.

Helper Functions

eBPF programs call helper functions, effectively making eBPF programs feature-rich. Helper functions perform the following:

• Search, update and delete key-value pairs

- Generate a pseudo-random number
- Get and set tunnel metadata
- Chain eBPF programs together (tail calls)
- · Perform tasks with sockets such as binding, retrieving cookies, and redirecting packets

The kernel defines helper functions, meaning that the kernel whitelists the range of calls that eBPF programs make.

eBPF Maps

Maps are the main data structures used by eBPF programs. Maps allow the communication of data between the kernel and user space. A map is a key-value store where values are treated as binary blobs of arbitrary data. When the map is no longer needed, it is removed by closing the associated file descriptor.

Each map has the following four attributes: its type, the maximum quantity of elements it can contain, the size of its values in bytes, and the size of its keys in bytes. Various map types are available, each offering distinct behaviors and trade-offs. All maps can be accessed and manipulated from both eBPF programs and user space programs through the utilization of bpf_map_lookup_elem() and bpf_map_update_elem() functions.

Executing an eBPF Program


The kernel expects all eBPF programs to be loaded as bytecode. As a result, eBPF programs must be compiled into bytecode using toolchains. Once compiled, eBPF programs undergo verification within the kernel prior to their deployment at the designated hook point. eBPF supports modern architecture, meaning it is upgraded to be 64-bit encoded with 11 total registers. This closely maps eBPF to hardware for x86_64, ARM, and arm64 architecture, among others.

Most importantly, eBPF unlocks access to kernel-level events, avoiding the typical constraints associated with directly altering kernel code. In summary, eBPF works by:

- Compiling eBPF programs into bytecode
- Verifying programs execute safely in a VM loading at the hook point
- Attaching programs to hook points within the kernel that are triggered by specified events
- Compiling into native bytecode at runtime for greater portability

- Calling helper functions to manipulate data when a program runs
- Using maps (key-value pairs) to share data between the user space and kernel space and for maintaining state

Figure 13: eBPF Program Execution



XDP Overview

eXpress Data Path (XDP) is a newer programmable layer in the kernel network stack. XDP is one of the newer hook points where eBPF bytecode is attached and executed from. XDP object files are loaded on multiple kernels and architectures without the need for recompiling required by traditional eBPF programs. Although XDP programs narrow the performance gap in comparison to kernel-bypass solutions, the programs do not bypass the kernel. The following are some key characteristics that define XDP:

- Not intended to be faster than kernel-bypass
- Operates directly on packet buffers
- Decreases number of instructions executed per packet

The kernel network stack is designed for socket-delivery use cases. As a result, it always converts all the incoming packets to socket buffers (SKBs). XDP enables the processing of packets before they are converted to SKBs. XDP operates in conjunctions with the existing kernel stack, all without necessitating kernel modifications. This makes XDP an in-kernel alternative that offers greater flexibility.

XDP and Traffic Control Hooks

All eBPF bytecode loading, map creation, updating, and reading is processed through the BPF syscall. It's important to note that the XDP driver hooks are only available on the ingress. If egress packets must be


processed, an alternative hook, such as TC (Traffic Control), might need to be employed. At a broader level, there are several differences between XDP BPF programs and TC BPF programs:

- XDP hooks occur earlier, resulting in faster performance.
 - TC hooks occur later. As a result, they have access to the socket buffer (sk_buff) structure and fields. This is a significant contributor to the performance difference between the XDP and TC hooks because the sk_buff data structure contains metadata and information that enables the kernel's network stack to process and route packets efficiently. Accessing the sk_buff structure and its attributes incurs a certain overhead, because the kernel stack must allocate, extract metadata, and manage the packet until it reaches the TC hook.
- TC hooks enable better packet mangling.
- XDP is better for complete packet rewrites.
 - The sk_buff use case contains extensive protocol-specific details, such as state information related to GSO (Generic Segmentation Offload). This makes it challenging to switch protocols solely by rewriting the packet data. As a result, further conversion is necessary, accomplished through BPF helper functions. These helper functions ensure that the internal components of the sk_buff are properly converted.

In contrast, the xdp_buff use case doesn't encounter these issues. It operates at an early stage in packet processing, even before the kernel allocates an sk_buff. As a result, making any type of packet rewrite in this scenario is straightforward.

- TC eBPF and XDP as complementary programs.
 - In instances where the use case requires both packet rewrite and intricate mangling of data, then the limitations of each program type can be overcome by operating complementary programs of both types. For example, an XDP program at the ingress point can perform a complete packet rewrite and transmit custom metadata from XDP BPF to TC BPF. The TC BPF program can then leverage the XDP metadata and sk_buff fields to perform complex packet processing.
- TC BPF does not require hardware driver changes. XDP uses native driver mode for best performance.

Figure 14: XDP and TC Hooks



XDP Control and Data Plane

With XDP, the data plane resides within the kernel, dividing it into two components: the kernel core and the in-kernel eBPF program. The control plane resides in user space, operating in conjunction with the kernel space to perform essential tasks such as loading BPF programs into the kernel and managing program behavior through the use of maps.

XDP Action and Behavior

An eBPF program running at an XDP hook point returns the following actions based on how the program processes the packet:

- Redirects ingress packets to other interfaces or to user space.
- Sends the received packet back out the same interface it arrived on.
- Sends the packet to the kernel stack for processing.
- Drops the packet.

XDP and eBPF

XDP serves as a software offload layer for the kernel's networking stack. An ideal use case is in conjunction with the Linux kernel's network stack to enhance performance. For example, in an IP routing use case, the kernel handles route table management and neighbor lookups, while XDP accelerates packet processing by efficiently accessing these routing tables with helper functions. After the lookup is complete and the next hop is identified, packet headers are modified accordingly. If no modification is needed, the packet is forwarded to the kernel as-is.

It is important to note that XDP imposes the following restrictions on the RX memory model:

- Does not currently support jumbo frames for all popular drivers, although i40e, Veth, and virtio support jumbo frames.
- Multicast support exists in the kernel space

Utilizing an eBPF XDP driver mode-based approach offers benefits over a proprietary kernel module like the vRouter kernel module. Some of the benefits include improved Lifecycle Management (LCM), safety, and performance. When compared to a kernel module integrated into the Linux upstream tree, maintaining an alternative eBPF XDP kernel program is more efficient across kernel versions. This is because kernel dependencies are limited to a small set of eBPF helper functions.

It is important to note that in the event of a controller/library crash, the XDP or TC program still forwards traffic. The re-attachment or replacement of an XDP or TC program does not disrupt network traffic.

Kernel to User Space Communication

AF_XDP sockets are used to facilitate communication between the kernel-space program operating at the XDP hook and the user space library. AF_XDP was introduced in Linux 4.1.8. AF_XDP is a new socket type for fast raw packet delivery to user space applications. AF_XDP leverages Linux kernel drivers for high performance and scalability. Notably, it also provides features such as support for zero-copy data transfer, minimal reliance on interrupts, and optimization for networking drivers similar to what Data Plane Development Kit (DPDK) and Vector Packet Processing (VPP) provide.

The path of a packet flowing through an AF_XDP socket is as follows:

The NIC-specific driver accesses incoming packets at the NIC. The driver intercepts and processes them through the eBPF program running at the XDP hook, which is bound to the corresponding interface. The XDP program processes each packet individually, and upon completion, it generates an action, as detailed in the XDP Action and Cooperation section. By utilizing XDP_REDIRECT, the packet is directed to user space via an AF_XDP socket associated with that interface. This makes it possible to receive raw packets straight from the NIC. By bypassing kernel space, kernel overhead is avoided and the packet accesses user space libraries directly.

Supported eBPF Features

Supported features in CN2 release 23.2

• Default pod network

- Pod to pod connectivity
- "Kubernetes network policy" on page 90
- "ClusterIP service" on page 329

Supported features in CN2 release 23.3

- "LoadBalancer service" on page 307
- "Fabric SNAT" on page 2
- "BGPaaS" on page 291

Enable eBPF Data Plane

You can enable the eBPF data plane feature by specifying agentModeType: xdp in the vRouter's spec. Since not all XDP drivers currently support jumbo frames, the CN2 deployer sets the Maximum Transmission Unit (MTU) values of the fabric, loopback, and veth interfaces.

The following example is a vRouter resource with XDP-eBPF enabled.

```
apiVersion: dataplane.juniper.net/v1
kind: Vrouter
metadata:
 name: contrail-vrouter-masters
 namespace: contrail
spec:
 agent:
   default:
      collectors:
      - localhost:6700
      xmppAuthEnable: true
    sandesh:
      introspectSslEnable: true
      sandeshSslEnable: true
 agentModeType: xdp
 common:
    containers:
    - name: contrail-vrouter-agent
      image: contrail-vrouter-agent
    - name: contrail-watcher
```

```
image: contrail-init
- name: contrail-vrouter-telemetry-exporter
image: contrail-vrouter-telemetry-exporter
initContainers:
- name: contrail-init
image: contrail-init
- name: contrail-cni-init
image: contrail-cni-init
```

Note the name: contrail-vrouter-masters field. Since this vRouter is designated as a master node, all available master nodes are set to agentModeType: xdp when the deployer is applied. This logic also applies to worker nodes; if you specify "xdp" for the worker node resource in the deployer, all worker nodes are configured for XDP-eBPF.

XDP Supported Drivers

The following table lists the CN2-validated XDP drivers with eBPF-XDP datapath.

Driver name	Underlying platform
ENA	AWS
veth	Pod connectivity
virtio	CN2-On-CN2
i40e	Bare Metal

Table 18: Validated XDP Drivers

NOTE: If your cluster uses AWS ENA underlying drivers for NIC interfaces, the deployer sets the queue config of 4 receiving (RX) and 4 transmission (TX) for physical interfaces. This change occurs because the default RX and TX queue count of ENA drivers is not supported for XDP.

eBPF Data Plane Design and CN2 Implementation

The eBPF kernel data plane consists of two core components: the in-kernel XDP program and a complementary user space library. This eBPF-powered data plane is the third data plane option for vRouter, along with the kernel module-based vRouter and DPDK. The subsequent sections explain the design and implementation specifics of the various data plane features provided by this technology.

eBPF Data Plane Components

As previously mentioned, the eBPF data plane is based in XDP. For features that require packets to originate from the default namespace, there might also be a necessity for an egress TC hook. This is due to the absence of the XDP hook on the egress path. The TC program also introduces new parsing functions, given that TC hooks operate with SKBs.

Figure 15: eBPF Data Plane Components



The eBPF data plane is not intended as a separate daemon; instead, it will be integrated as a library within the controller (vRouter agent in the case of CN2). This implementation is divided into two components:

- User space library: The user space library acts as an interface between the kernel eBPF program and a controller running in user space (vRouter agent). It exposes APIs that the vRouter agent utilizes to program the data path. This component performs the following functions:
 - Loads and unloads eBPF program into the kernel
 - Binds eBPF programs to interfaces
 - Configures and reads map entries
 - Forwards, modifies, and filters packets within the user space data path
- Kernel space program: These eBPF programs constitute the main data path that runs in the kernel core. This program is loaded onto the XDP-hook of interfaces and processes all incoming packets for those interfaces. TC is also used on the loopback interface's egress. As mentioned earlier, the user

space eBPF library is responsible for loading the eBPF program into the kernel core. The kernel space program does the following:

- Forwards, modifies, and filters packets in the kernel
- Uses helper functions to interact with rest of kernel
- Creates, updates, and reads maps (maps are data structures shared between the user space library and the kernel space program)

The vRouter agent interacts with the eBPF data plane via the user space library in several ways:

- The controller (vRouter agent) calls APIs exposed by the user space eBPF library directly.
 - The public APIs exposed by the library replaces the functionality provided by the ksync/Sandesh layer used for othe datapaths
 - The agent registers callbacks with the user space library for flow misses and to receive packets of interest
- The library also listens on netlink socket events; the user-space library can listen on routes, and arp and address updates from the kernel
- The library also queries the kernel for other information



Configure Services

Enable BGP as a Service | 291 Configure BGP Color Extended Communities | 304 Create a Load Balancer Service | 307 NodePort Service Support in Cloud-Native Contrail Networking | 319 Configure ClusterIP Service by Assigning Endpoints | 329 FloatingIP/DNAT for IPv6 Addresses | 333

Enable BGP as a Service

IN THIS SECTION

- Benefits of BGP as a Service in Cloud-Native Contrail | 291
- Prerequisites | 292
- Overview of BGP as a Service in Cloud-Native Contrail Networking | 292
- Enable BGPaaS in a Pod | 293
- Configure the IP Address Allocation Method for BGPasaS | 297
- Configure the BGPasaService Object | 298
- Validate the BGP as a Service Configuration | 302
- Configure BGP in Pod | 303

Cloud-Native Contrail® Networking[™] supports BGP as a Service (BGPaaS). This document should be used to enable BGPaaS in environments using Release 22.1 or later.

The BGPaaS feature in Cloud-Native Contrail Networking provides the network support for BGP to operate within a virtual network in cloud networking environments using Cloud-Native Contrail Networking.

Benefits of BGP as a Service in Cloud-Native Contrail

With BGPaaS in Kubernetes environments using Cloud-Native Contrail Networking, you gain the following functionality:

- A BGP protocol service that runs in the virtual network. This BGP service creates BGP neighbor sessions to pods, virtual machines, and other workloads in the virtual network.
- A routing protocol that supports IPv4 neighbors, the IPv4 and IPv6 unicast address family, and IPv6over-IPv4 next-hop mapping.
- A BGP protocol service that is user-configurable using most well-known BGP configuration parameters.

You can use BGPaaS in any cloud networking environment that needs the functionality provided by a routing protocol. You may find BGPaaS especially useful in the following scenarios:

- If you manage a large cloud networking environment that runs multiple workloads, you may want to use BGPaaS to scale network services.
- If you use tunneling protocols that need network reachability information from a routing protocol to create and maintain tunnels, BGPaaS can help.

Prerequisites

We assume that before you enable BGP as a service:

- You are operating in a working cloud networking environment using Kubernetes orchestration, and Cloud-Native Contrail Networking is operational.
- You have a working knowledge of BGP.

Overview of BGP as a Service in Cloud-Native Contrail Networking

Cloud-Native Contrail Networking provides the networking support for BGPaaS.

You have to find a BGP service to run BGP in your cloud networking environment. This document shows how to enable networking support for BGPaaS with Cloud-Native Contrail Networking using the BGP service provided by the BIRD Internet Routing Daemon (BIRD). This daemon is available as a built-in development tool on many versions of Unix. You can also download it to your environment using a separate image.

In the examples that follow, you see that the BGP daemon from BIRD runs in a pod when BGPaaS is enabled. That daemon then sends BGP messages over the network using the networking capabilities provided by Cloud-Native Contrail Networking. For additional information on BIRD, see the BIRD Internet Routing Daemon homepage.

When BGPaaS is operational, the BGP daemon runs in a pod and manages BGPaaS. The BGP daemon is directly connected to a Contrail vRouter.

The Contrail vRouter has a connection to at least one control plane node and connects the BIRD daemon to the control plane. A BGP peering session between at least one control node and the BIRD daemon is established through this connection with the Contrail vRouter.

After a peering session is created between the control nodes and the BGP daemon, the BGP daemon can manage BGPaaS and send routes to BGP clients over the control plane. The BGPaaS management tasks include assigning IP addresses to workloads, pods, VMs, or other objects.

Enable BGPaaS in a Pod

To enable BGPaaS, you must create a pod to host the BGP service. You must then associate the pod hosting the BGP service with the virtual networks where BGPaaS will run.

You can use either of two methods of associating a pod hosting the BGP service with a virtual network:

- Virtual Machine Interfaces Selector—The pod running the BGP service is directly associated with the virtual network. The pod hosting the BGP service is discovered automatically after the virtual network association is defined.
- Virtual Machine Interface References—The pod running the BGP service is directly associated with the virtual network by explicitly providing the namespace and the name of the virtual machine interface of the pod hosting the BGP service.

The following sections provide the steps for each association method.

Enable BGPaaS in a Pod Using the Virtual Machine Interfaces Selector

You must create a pod to host the BGP service, and then you can enable BGPaaS with the Virtual Machine Interfaces Selector.

The pod must:

- Include at least one IPv4 interface.
- Include annotations using core.juniper.net/bgpaas-networks to specify the associated virtual network names. The value in this annotation must include at least one virtual network name. If you are associating the pod hosting the BIRD daemon with multiple virtual networks, enter the virtual network names as a comma-separated list.

In this example YAML file, a pod is created to host the BGP service. The pod is associated with two virtual networks and BGPaaS is enabled to run on both virtual networks. The **image:** variable in the **containers:** hierarchy points to the BIRD image file that will provide the BGP service in this example.

```
apiVersion: v1
kind: Pod
metadata:
  name: bird-pod-shared-1
  namespace: bgpaas-ns
  annotations:
        k8s.v1.cni.cncf.io/networks: |
        [{
            "name": "bgpaas-vn-1",
```

```
"namespace": "bgpaas-ns",
          "cni-args": null
          "interface": "eth1"
       },{
          "name": "bgpaas-vn-2",
          "namespace": "bgpaas-ns",
          "cni-args": null
          "interface": "eth2"
       }1
   core.juniper.net/bgpaas-networks: bgpaas-vn-1,bgapss-vn-2
spec:
 containers:
    - name: bird-pod-c
      image: somewhere.juniper.net/cn2/bazel-build/dev/bird-sut:1.0
      command: ["bash","-c","while true; do sleep 60s; done"]
      securityContext:
       privileged: true
```

Enter the **kubectl get vmi -n** *virtual-network-name* to confirm that the pod and its associated virtual machine interfaces have been created. You can also enter the **kubectl describe** command to ensure that the virtual machine interfaces exist.

You can confirm the virtual network was created by reviewing the **bgpaasVN=** output in the label section of the **kubectl describe** command.

kubectl ۽	get vmi –	n bgpaas-ns			
CLUSTE	RNAME		NAME	NETWORK	PODNAME
IFCNAME	STATE	AGE			
contra	il-k8s-ku	ıbemanager-kubernetes	bird-pod-1-abb881a8	bgpaas-vn-1	bird-pod-1
eth1	Success	s 13s			
contra	il-k8s-ku	ıbemanager-kubernetes	bird-pod-1-e3f93f05	default-podnetwork	bird-pod-1
eth0	Success	s 13s			
kubect]	l descrik	be vmi bird-pod-1-abb8	81a8 -n bgpaas-ns		
Name:	k	pird-pod-1-abb881a8			
Namespa	ace: k	ogpaas-ns			
Labels	: 0	core.juniper.net/ <i>bgpaa</i>	sVN=bgpaas-vn-1		
	r	namespace=bgpaas-ns			

You must then create a BGPaaS object to configure BGPaaS. The BGPaaS object references the virtual networks in the **virtualMachineInterfacesSelector:** section.

```
apiVersion: core.contrail.juniper.net/v1alpha1
kind: BGPAsAService
metadata:
  namespace: bgpaas-ns
  name: bgpaas-test
spec:
  shared: false
  autonomousSystem: 10
  bgpAsAServiceSessionAttributes:
    loopCount: 2
    routeOriginOverride:
    origin: EGP
    addressFamilies:
      family:
        - inet
        - inet6
  virtualMachineInterfacesSelector:
    - matchLabels:
        core.juniper.net/bgpaasVN: bgpaas-vn-1
    - matchLabels:
        core.juniper.net/bgpaasVN: bgpaas-vn-2
```

Enable BGPaaS in a Pod Using Virtual Machine Interface References

You must first create a pod to host the BIRD daemon to enable BGPaaS with Virtual Machine Interface references. The pod must include at least one IPv4 interface.

In the following example, a pod is created in the **bgpaas-ns** namespace. The annotation associates the pod with the **bgpaas-vn-1** virtual network. The **image:** variable in the **containers:** hierarchy points to the BIRD image file that will provide the BGP service in this example.

```
apiVersion: v1
kind: Pod
metadata:
   name: bird-pod-1
   namespace: bgpaas-ns
   annotations:
    k8s.v1.cni.cncf.io/networks: bgpaas-vn-1
```

```
spec:
containers:
    name: bird-pod-c
    image: somewhere.juniper.net/cn2/bazel-build/dev/bird-sut:1.0
    command: ["bash","-c","while true; do sleep 60s; done"]
    securityContext:
    privileged: true
```

Confirm that the pod was created after committing the pod object configuration file by entering the **kubectl get vmi -n bgpaas-ns** command.

Note the name of the virtual machine interface for the pod in this command output. You will need to specify the virtual machine interface name later in this procedure when configuring the BGPaaS object.

kubectl g	get vmi -n	bgpaas-ns			
CLUSTE	RNAME		NAME	NETWORK	PODNAME
IFCNAME	STATE	AGE			
contra	il-k8s-kube	emanager-kubernetes	bird-pod-1-abb881a8	bgpaas-vn-1	bird-pod-1
eth1	Success	13s			
contra	il-k8s-kube	emanager-kubernetes	bird-pod-1-e3f93f05	default-podnetwork	bird-pod-1
eth0	Success	13s			

The Virtual Machine interface references are defined while creating the BGPaaS object using the **virtualMachineInterfaceReferences:** hierarchy. The **namespace:** is the pod namespace and the **name:** is the virtual machine interface name that you retrieved using the **kubectl get vmi -n bgpaas-ns** command.

```
apiVersion: core.contrail.juniper.net/v1alpha1
kind: BGPAsAService
metadata:
 namespace: bgpaas-ns
 name: bgpaas-sample
spec:
 shared: false
 autonomousSystem: 100
 bgpAsAServiceSessionAttributes:
   localAutonomousSystem: 10
   loopCount: 2
    routeOriginOverride:
      origin: EGP
    addressFamilies:
      family:
        - inet
```

- inet6

virtualMachineInterfaceReferences:
 apiVersion: core.contrail.juniper.net/v1alpha1
 kind: VirtualMachineInterface
 namespace: bgpaas-ns
 name: bird-pod-1-abb881a8

Configure the IP Address Allocation Method for BGPasaS

You can configure BGPaaService with one of the following IP address allocation methods:

- automatic IP address allocation—The BGP service assigns IP addresses.
- user-specified IP address allocation—You assign the IP address.

You configure the IP address allocation method in the Subnet object.

Automatic IP address allocation is enabled by default. If you enable BGPaaS without manually disabling automatic IP address allocation, BGPaaS uses automatic IP address allocation.

You disable automatic IP address allocation by setting the *disableBGPaaSIPAutoAllocation:* variable in the Subnet object to *true.* If the *disableBGPaaSIPAutoAllocation:* variable is not present in the **Subnet** object file, automatic IP address allocation is enabled.

In the following configuration sample, automatic IP address allocation is enabled because the *disableBGPaaSIPAutoAllocation:* variable isn't present in the **Subnet** object configuration file.

```
apiVersion: core.contrail.juniper.net/v1alpha1
kind: Subnet
metadata:
   namespace: bgpaas-ns
   name: bgpaas-subnet-1
spec:
   cidr: "172.20.10.0/24"
```

In this configuration sample, automatic IP address allocation is enabled because the *disableBGPaaSIPAutoAllocation:* variable is set to **false**.

apiVersion: core.contrail.juniper.net/v1alpha1 kind: Subnet metadata:

```
namespace: bgpaas-ns
name: bgpaas-subnet-2
spec:
cidr: "172.20.20.0/24"
disableBGPaaSIPAutoAllocation: false
```

To enable user-specified IP address allocation, set the *disableBGPaaSIPAutoAllocation:* variable to true. When user-specified IP address allocation is enabled, you must also configure the BGP addresses that BGPaaS can assign to endpoints within the subnet. You must set a primary IP address using the *bgpaasPrimaryIP:* variable. You can also set an optional secondary IP address, which you can see in this example with the *bgpaasSecondaryIP:* variable.

```
apiVersion: core.contrail.juniper.net/v1alpha1
kind: Subnet
metadata:
   namespace: bgpaas-ns
   name: bgpaas-subnet-2
spec:
   cidr: "172.20.20.0/24"
disableBGPaaSIPAutoAllocation: true
   bgpaasPrimaryIP: 172.20.20.3
   bgpaasSecondaryIP: 172.20.20.4
```

Configure the BGPasaService Object

You enable BGPaaS in a cluster by creating a BGPAsAService object.

Create the BGPAsAService object by creating a YAML file that uses BGPAsAService in the kind: field:

```
apiVersion: core.contrail.juniper.net/v1alpha1
kind: BGPAsAService
metadata:
    namespace: bgpaas-ns
    name: bgpaas-test
spec:
    shared: false
    autonomousSystem: 10
    bgpAsAServiceSessionAttributes:
    loopCount: 2
```

Table 19: Spec Field Variables for BGPaaS

This table provides a description of each Spec field variable in the BGPaaS object file.

Field Variable	Description
shared:	Specifies whether a common BGP router object can be shared with multiple virtual machine interfaces in the same virtual network. When this field is set to true , one BGP client router can be shared with multiple virtual machine interfaces in the same virtual network. This setting limits the total number of BGP client routers that have to be created in a virtual network for a VMI. When this field is set to false , one BGP client router is created for each virtual machine interface.
autonomousSystem:	Specifies the global Autonomous System number for the BGP instance. The Autonomous System number can be any whole number between 1 and 4294967295.
bgpAsAServiceSessionAttributes:	Defines the BGP session attributes for BGPaaS. See Table 20 on page 300.

Table 19: Spec Field Variables for BGPaaS (Continued)

Field Variable	Description
virtualMachineInterfaceReferences:	Defines the virtual machine interface parameters to associate with BGPaaS when using virtual machine interface references. See Table 21 on page 301.
virtualMachineInterfacesSelector:	Defines the virtual networks where BGPaaS runs when using the virtual machine interfaces selector. See Table 22 on page 301.

Table 20: BgpAsAServiceSessionAttributes Fields for BGPaaS

The bgpAsAServiceSessionAttributes: in the spec: hierarchy are used in all BGPaaS setups. The bgpAsAServiceSessionAttributes: hierarchy includes these fields:

Field	Description
localAutonomousSystem:	Specifies the local Autonomous System number for BGP.
LoopCount:	Specifies the number of times that the same ASN can be seen in a route update before the route is discarded. The LoopCount: can be any whole number up to 16.
routeOriginOverride:	Overrides the original setting and sets the origin attribute to Incomplete when forwarding routes. If you set this field to false , routes are advertised into BGP based on the origin setting. The origin is either IGP or EGP and is set using the origin: field in this file. If you set this field to true , the origin is set to Incomplete for advertised routes. Use this field if you want to change how BGP networks prioritize routes received from the BGP service. By default, BGP networks prioritize routes based on origin, and routes with an Incomplete origin receive lower priority than routes received from IGP or EGP.

Table 20: BgpAsAServiceSessionAttributes Fields for BGPaaS (Continued)

Field	Description
Origin:	Specifies if BGP operates as an interior gateway protocol (igp) or exterior gateway protocol (egp). The default route origin is igp .
AddressFamilies:	Specifies the address family. You can specify the family as inet for IPv4 or inet6 for IPv6. You can specify both address families simultaneously.

Table 21: virtualMachineInterfaceReferences: in BGPaaS

The virtualMachineInterfaceReferences: in the spec: hierarchy include the following fields:

Field	Description
apiVersion:	Specifies the API version for the virtual machine interface reference.
kind:	Always set this field to VirtualMachineInterface .
namespace:	Specifies the namespace associated with the virtual machine interface reference. You define this namespace while creating the Pod object. See "Enable BGPaaS in a Pod Using Virtual Machine Interface References" on page 295.
name:	Specifies the name of the pod associated with the virtual machine interface reference. You can retrieve the pod name by entering the kubectl get vmi -n bgpaas-ns command. See "Enable BGPaaS in a Pod Using Virtual Machine Interface References" on page 295.

Table 22: The virtualMachineInterfacesSelector: Fields in BGPaaS

The virtualMachineInterfacesSelector: in the spec: hierarchy includes the following fields:

Field	Description
matchLabels:	Define the match labels for the Virtual Machine Interfaces selector.
	The match labels in this context are always used to reference the virtual networks where the Virtual Machine interfaces selector is running.
	Always enter the match label values in this section as core.juniper.net/bgpaasVN: <i>virtual-network-name</i> . See "Enable BGPaaS in a Pod Using the Virtual Machine Interfaces Selector" on page 293.

Validate the BGP as a Service Configuration

You should confirm that the BGPaaS object is successfully running after you commit the BGPAsAService object file.

Enter the **kubectl get BGPAsAService** command after you create the BGPAsAService object to confirm the object state. The object is successfully created when the **State** field indicates **Success**.

kubectl get BGPAsAService -n bgpaas-ns					
NAME	AS	IPADDRESS	SHARED	STATE	AGE
bgpaas-sample	100		false	Success	33s

You should also ensure the BGPaaS server and the BGPaaS client are created and are in the **Success** state.

Enter the **kubectl get BGPRouter** command to confirm the presence and operational state of the BGPaaS servers and clients.

kubectl get BGPRouter -n bgpaas-ns				
NAME	TYPE	IDENTIFIER	STATE	AGE
bgpaas-ns-bgpaas-vn-1-bgpaas-server	bgpaas-server		Success	2m57s
bgpaas-ns-bgpaas-vn-1-bird-pod-1-abb881a8	bgpaas-client	172.20.10.2	Success	2m57s

Configure BGP in Pod

You must also configure the networking parameters for the BGP service running in the pod. The configuration for each individual BGP service is unique. Documenting the required networking configuration parameters is beyond the scope of this document. Please check the documentation that accompanies your BGP service.

In this example, we show you how to configure the BGP network configuration using BIRD.

You configure BGP using the BIRD CLI in this example. The parameters of the BGP configuration that need to match the BGPaaS objects defined in Cloud-Native Contrail Networking are noted. Although not shown in this example, you should know that the default location to access the BIRD configuration file in most deployments is /etc/bird.conf or /etc/bird.conf.

```
# Change the router id to your BIRD router ID. It's a world-wide unique identification
  # of your router, usually one of router's IPv4 addresses.
  router id 172.20.10.2;
 protocol direct {
        interface "eth1*"; -> interface on which BGPAsAService needs to be configured
 }
  protocol bgp bgp1_1 {
       import all;
       export all;
       local as 10;
                                        -> AS configured in BGPAsAService
       neighbor 172.20.10.3 as 64512; -> neighbor for primary BGP session, use
BGPaaSPrimaryIP from subnet
        neighbor 172.20.10.3 as 64512;
                                         -> neighbor for secondary BGP session, use
BGPaaSSecondaryIP from subnet
```

From your BGP service, verify that the BGP protocol is running.

In this example from BIRD, you enter the **show protocol** command to verify that the BGP protocol is established in BIRD.

birdc show protocol bgp1_1						
BIRD 1.6	6.8 ready					
name	proto	table	state	since	info	
bgp1_1	BGP	master	up	10:31:27	Established	

Configure BGP Color Extended Communities

SUMMARY

Starting with Cloud-Native Contrail Networking (CN2) Release 23.3, BGP color extended communities are supported.

IN THIS SECTION

- Overview | 304
- Configure a BGP Color Extended Community | **304**

Overview

Using Border Gateway Protocol (BGP) communities and extended communities, you can group prefixes or subnets to share a common property. You can match for a specific prefix, match for multiple prefixes, or match for a whole subnet based on routing policy and attach communities through the routes. Community information is included in the BGP update messages. Colored prefixes can be advertised for end-to-end network slicing across 5G deployments. A set of actions can be taken based on routing policies. These actions can be preferred services given to routes based on tags. CN2 currently supports adding BGP communities, extended communities, and now color extended communities information to the routes. Color is a BGP extended community configured using color:0:<tag>.

You can set the community using their hexadecimal representation that determines the Type and Sub-Type of the community. For example, 0x030b is the hexadecimal value for a color extended community. In Release 23.3, you can add a color extended community using the name color versus the hexadecimal value. You define the color value and configure it locally.

Configure a BGP Color Extended Community

CN2 supports configuration of a color extended community using color:0:<tag> or color:<tag>. The tag is basically the number for the color community. Color community is attached to the routes using a routing policy.

To configure a BGP color extended community:

1. Create a namespace, virtual network (VN), and subnet pod. These are all the nodes required to bring up pods and establish connections. **2.** Create a routing policy. The example YAML file checks for a specific prefix and adds the color community to the route accordingly.

You configure a color community using color:0:12345 or color:12345. However, in the control node introspect it shows as color:0:12345 even if you configured the value as color:12345.

NOTE: The color value "12345" is the variable used in these examples.

Example routing policy for color extended community:

```
apiVersion: core.contrail.juniper.net/v5
kind: RoutingPolicy
metadata:
  namespace: rptest-ns
  name: rptest
spec:
  routingPolicyEntries:
    term:
      - termActionList:
          action: accept
          asPathExpand:
          asPathPrepend:
          external:
          update:
            asPath:
              expand: {}
            community:
              add: {}
              remove: {}
              set: {}
            extcommunity:
              add:
                community:
                - color:0:12345
              remove: {}
              set: {}
            service:
              add: {}
              remove: {}
              set: {}
        termMatchCondition:
          asPath:
```

community: communityList: communityMatchAll: extcommunityMatchAll: external: family: localPref: nlriRouteType: prefix: - prefix: 172.100.10.3/32 prefixType: exact prefixList: protocol: routeFilter:

 Add the routing policy reference to the VN. Edit the already created VN and add the routingPolicyReferences as shown in the example. Example:

```
apiVersion: core.contrail.juniper.net/v5
kind: VirtualNetwork
metadata:
    namespace: rptest-ns
    name: rptest-vn-1
spec:
    routingPolicyReferences:
        - apiVersion: core.contrail.juniper.net/v5
        kind: RoutingPolicy
        namespace: rptest-ns
        name: rptest
```

4. After the routing policy is added, you can verify the communities added to the route (or any other action performed in the routing policy) on the control node introspect. Check the route attributes on the control node to verify the respective actions and communities are added.

SEE ALSO

Routing Policies | 106

Enable BGP as a Service

Create a Load Balancer Service

SUMMARY

This topic describes how to create a Load Balancer service in Juniper Cloud-Native Contrail® Networking (CN2). Juniper Networks supports this feature using Contrail Networking Release 22.1 or later in a Kubernetes-orchestrated environment.

IN THIS SECTION

- Load Balancer Service Overview | 307
- Create a Load Balancer Service | 308
- Configure Load Balancer Services Without Selectors | 315

Load Balancer Service Overview

In Kubernetes, a service is an abstract way to expose an application running on a set of pods as a network service. Kubernetes supports three types of services: ClusterIP, NodePort and LoadBalancer. This topic describes how to create a load balancer service in CN2.

In CN2, a load balancer service is implemented with the InstanceIP resource and FloatingIP resource as described below:

- The FloatingIP is used in the service implementation to expose an external IP to the load balancer service. The FloatingIP resource is also associated with the pod's VirtualMachineInterfaces.
- The InstanceIP resource is related to the VirtualNetwork. Two instanceIPs are created, one for the service network and one for the external network.

A controller service is implemented in Contrail's kube-manager. Kube-manager is the interface between Kubernetes core resources and the extended Contrail resources, such as the VirtualNetwork. When you create a load balancer service, kube-manager listens and allocates the IP from an external virtual network. This external virtual network exposes the load balancer service on the external IPs. Any requests received through the provisioned external IP is ECMP load-balanced across the pods associated with the load balancer.

Create a Load Balancer Service

IN THIS SECTION

Dual-Stack Networking Support | 315

The following sections describe how to create a load balancer service in CN2.

Prerequisites

Before you begin, make sure of the following:

- You have set up a working cloud networking environment with Kubernetes.
- CN2 is installed and is operational.
- You have configured kube-manager to define the external networks to be used by the load balancer service.

Define an External Virtual Network

First, define an external virtual network. You can define the virtual network two ways: by creating a Network Attachment Definition (NAD) or by creating a virtual network.

NOTE: A Multus deployment requires that you use a NAD to define an external network.

The following example shows how to define an external virtual network using a NetworkAttachmentDefinition. In this example, the external IP is allocated from the subnet range 192.168.102.0/24. When the NetworkAttachmentDefinition is applied, kube-manager creates a virtual network with the name ecmp-default in the namespace ecmp-project.

```
apiVersion: "k8s.cni.cncf.io/v1"
kind: NetworkAttachmentDefinition
metadata:
  name: ecmp-default
  namespace: ecmp-project
  annotations:
```

```
juniper.net/networks: '{
    "ipamV4Subnet": "192.168.102.0/24",
    "fabricSNAT": false
    "core.juniper.net/display-name: "External Virtual Network"
}'
core.juniper.net/display-name: "External Virtual Network"
labels:
    service.contrail.juniper.net/externalNetworkSelector: default-external
spec:
    config: '{
        "cniVersion": "0.3.1",
        "name": "ecmp-default",
        "type": "contrail-k8s-cni"
}'
```

Specify the External Networks

By default, kube-manager allocates the external IP for a load balancer service from the default-external network. If desired, you can allocate the external IP from a different network by defining custom selectors, as shown in the following example:

```
apiVersion: configplane.juniper.net/v1alpha1
kind: Kubemanager
metadata:
generation: 148
name: contrail-k8s-kubemanager
namespace: contrail
spec:
 externalNetworkSelectors:
  default-external:
   networkSelector:
   matchLabels:
    service.contrail.juniper.net/externalNetwork: default-external
 custom-external:
 namespaceSelector:
  matchLabels:
    customNamespaceKey: custom-namespace-value
 networkSelector:
 matchl abels:
   customNetworkKey: custom-network-value
 custom-external-in-service-namespace:
```

```
networkSelector:
matchLabels:
    customExternalInServiceNetworkKey: custom-external-in-service-network-value
```

The VirtualNetworks in this example match the labels shown in the previous example (in relative order).

```
apiVersion: core.contrail.juniper.net/v3
kind: Subnet
metadata:
 namespace: contrail
 name: external-subnet
spec:
 cidr: "10.244.0.0/16"
 defaultGateway: 10.244.0.1
---
apiVersion: core.contrail.juniper.net/v3kind: VirtualNetwork # matches example 1
metadata:
 name: default-external-vn
 namespace: contrail
 labels:
   service.contrail.juniper.net/externalNetworkSelector: default-external
spec:
 v4SubnetReference:
   apiVersion: core.contrail.juniper.net/v3
   kind: Subnet
   namespace: contrail
   name: external-subnet
# this is how you define namespace selector
# Namespace must have appropriate label if required by namespaceSelector
apiVersion: v1
kind: Namespace
metadata:
 labels:
      customNamespaceKey: custom-namespace-value #user for your external ip
 name: custom-namespace
- -
apiVersion: core.contrail.juniper.net/v3kind: Subnet
metadata:
 namespace: custom-namespace
 name: external-subnet-custom-namespace
spec:
```

```
cidr: "10.0.0.0/16"
 defaultGateway: 10.0.0.1
_ _ _
apiVersion: core.contrail.juniper.net/v3
kind: VirtualNetwork
metadata:
 name: external-vn-1 # matches example 2 and example 3
 namespace: custom-namespace
 labels:
   customNetworkKey: custom-network-value
spec:
 v4SubnetReference:
   apiVersion: core.contrail.juniper.net/v3
   kind: Subnet
   namespace: custom-namespace
   name: external-subnet-custom-namespace
---
apiVersion: core.contrail.juniper.net/v3kind: Subnet
metadata:
 namespace: custom-namespace
 name: external-subnet-in-service
spec:
 cidr: "192.168.0.0/16"
 defaultGateway: 192.168.0.1
_ _ _
apiVersion: core.contrail.juniper.net/v3
kind: VirtualNetwork
metadata:
 name: external-vn-2 # matches example 4
 namespace: custom-namespace
 labels:
   customExternalInServiceNetworkKey: custom-external-in-service-network-value
spec:
 v4SubnetReference:
   apiVersion: core.contrail.juniper.net/v3
   kind: Subnet
   namespace: custom-namespace
   name: external-subnet-in-service
```

Define Service-Level Annotations

Additionally, you can define the following service-level annotations for external network discovery.

Annotation: externalNetwork.

In this example, the externalNetwork annotation allocates an external IP from the evn virtual network in the namespace ns.

```
apiVersion: v1
kind: Service
metadata:
    name: my-service
    annotation:
        service.contrail.juniper.net/externalNetwork: ns/evn
spec:
    type: LoadBalancer
    selector:
        app: MyApp
    ports:
        - protocol: TCP
        port: 80
        targetPort: 9376
```

Annotation: externalNetworkSelector

In this example, the externalNetworkSelector matches the name of the externalNetworkSelector defined in kube-manager.

```
apiVersion: v1
kind: Service
metadata:
    name: my-service
    annotation:
        service.contrail.juniper.net/externalNetworkSelector: custom-external
spec:
    type: LoadBalancer
    selector:
        app: MyApp
    ports:
        - protocol: TCP
        port: 80
        targetPort: 9376
```

NOTE: You can also define service-level annotations in the namespace of the Kubernetes cluster or in the namespace of the Contrail cluster. The service-level annotation take precedence.

Examples: External Network Selection

The external virtual network is selected from one of the following in priority order:

NOTE: The virtual networks defined in "Specify the External Networks" on page 309 are linked to the annotations in the following examples.

Example 1: Default Selector

Kube-manager first searches for the default external network. This example uses the default-external selector because no annotation is specified.

This example matches the network contrail/default-external-vn.

```
apiVersion: v1
kind: Service
metadata:
   name: my-service
spec:
   type: LoadBalancer
   selector:
      app: MyApp
ports:
      - protocol: TCP
      port: 80
      targetPort: 9376
```

Example 2: Custom Namespace

This example matches the network custom-namespace/external-vn-1.

apiVersion: v1 kind: Service

```
metadata:
  name: my-service
  annotation:
    service.contrail.juniper.net/externalNetwork: custom-namespace/external-vn-1
spec:
    type: LoadBalancer
    selector:
    app: MyApp
    ports:
        - protocol: TCP
        port: 80
        targetPort: 9376
```

Example 3: External Network Matches Preconfigured Selector in a Namespace

This example matches the network custom-namespace/external-vn-1.

```
apiVersion: v1
kind: Service
metadata:
    name: my-service
    annotation:
        service.contrail.juniper.net/externalNetworkSelector: custom-external
spec:
    type: LoadBalancer
    selector:
        app: MyApp
    ports:
        - protocol: TCP
        port: 80
        targetPort: 9376
```

Example 4: External Network Matches Preconfigured Selector in Service Namespace

This example matches the network custom-namespace/external-vn-2.

apiVersion: v1 kind: Service metadata: name: my-service

```
namespace: custom-namespace
annotation:
    customExternalInServiceNetworkKey: custom-external-in-service-network-value
spec:
    type: LoadBalancer
    selector:
    app: MyApp
ports:
    - protocol: TCP
    port: 80
    targetPort: 9376
```

Dual-Stack Networking Support

IPv4 or IPv6 dual-stack networking enables the allocation of both IPv4 and IPv6 addresses to pods and services. As an administrator, you might need to select the IP family (IPv4 or IPv6) to use when defining a service. If you do not define the IP family, the default IPv4 address is used.

```
apiVersion: v1
kind: Service
metadata:
  name: MyService
specs:
  ipFamilies: ["IPv4", "IPv6"]
```

For more information, see Overview: IPv4 and IPv6 Dual-Stack Networking.

Configure Load Balancer Services Without Selectors

In Kubernetes, you can expose an application running on a set of pods as a network service. Kubernetes uses selectors to automatically create a load balancer service, but only uses the default primary interface for load balancing.

Starting in CN2 Release 22.3, you can load balance a service across multiple secondary interfaces. You can create secondary interfaces in CN2 without using a selector. Because the load balancer service has no selector, you must create the endpoint manually.

To configure load balancer services without selectors:

1. Create two virtual networks.

The following example shows two networks. One network for the pod's secondary interface (**pod-subnet**) and another network (**Ib-subnet**) for the load balancer service external IP. These networks are connected by a common route target that routes traffic between the two networks.

```
apiVersion: "k8s.cni.cncf.io/v1"
kind: NetworkAttachmentDefinition
metadata:
 name: pod-subnet
 namespace: my-lb
 annotations:
   juniper.net/networks: '{
     "ipamV4Subnet": "172.16.12.0/24",
     "routeTargetList": ["target:64521:1164"]
}'
spec:
 config: '{
    "cniVersion": "0.3.1",
    "name": "pod-subnet",
    "type": "contrail-k8s-cni"
}'
_ _ _
apiVersion: "k8s.cni.cncf.io/v1"
kind: NetworkAttachmentDefinition
metadata:
  name: 1b-subnet
 namespace: my-lb
  annotations:
    juniper.net/networks: '{
      "ipamV4Subnet": "172.16.13.0/24",
      "routeTargetList": ["target:64521:1164"]
   }'
spec:
  config: '{
  "cniVersion": "0.3.1",
  "name": "lb-subnet",
  "type": "contrail-k8s-cni"
}'
```

2. Create the pods on which you want to load balance the service. You can create multiple pods.

In this example, we'll create two pods in the my-lb namespace, each with its own IP address.

```
apiVersion: v1
kind: Pod
metadata:
  name: my-pod
  namespace: my-lb
  labels:
    run: ecmp
  annotations:
    k8s.v1.cni.cncf.io/networks: '[
        {
          "name": "pod-subnet",
          "namespace": "my-lb",
          "ips": ["172.16.23.0"]
        }
      ינ
spec:
  containers:
    - name: front01-multiintf
      image: gcr.io/cos-cloud/toolbox
      command:
        ["bash", "-c", "ip route add 172.16.23.0/24 via 172.16.23.1 dev eth1; while true; do
echo front01 | nc -w 1 -l -p 8080; done"]
      securityContext:
        privileged: true
---
apiVersion: v1
kind: Pod
metadata:
  name: my-pod1
  namespace: my-lb
  labels:
    run: ecmp
  annotations:
    k8s.v1.cni.cncf.io/networks: '[
        {
         "name": "pod-subnet",
          "namespace": "my-lb",
          "ips": ["172.16.24.0"]
        }
      ינ
```

```
spec:
    containers:
        - name: front02-multiintf
        image: gcr.io/cos-cloud/toolbox
        command:
        ["bash", "-c", "ip route add 172.16.24.0/24 via 172.16.23.1 dev eth1; while true; do
echo front02 | nc -w 1 -l -p 8080; done"]
        securityContext:
        privileged: true
; done"]
```

3. Create a Load Balancer service.

In this example, we'll create a load balancer service (**service-lb**) in the **my-lb** namespace without using a selector.

```
kind: Service
metadata:
name: service-lb
namespace: my-lb
annotations:
   service.contrail.juniper.net/externalNetwork: my-lb/lb-subnet
spec:
  type: LoadBalancer
ports:
    - protocol: TCP
    port: 80
    targetPort: 8080
```

4. Specify the endpoints (IP addresses) on which you want to load balance the service. Make sure that the endpoint has the same name as the load balancer service.

In this example, we specified two pod endpoints for the secondary interfaces (ip: 172.16.23.0 and ip: 172.16.24.0).

```
apiVersion: v1
kind: Endpoints
metadata:
   name: service-lb
   namespace: my-lb
subsets:
```

```
- addresses:
    - ip: 172.16.23.0
    - ip: 172.16.24.0
    ports:
    - port: 8080
```

Success! You can now load balance a service across multiple pods with the secondary interface.

NOTE: In addition to creating a load balancer service on the secondary interface, you can use a selector to create a load balancer on the default primary interface. The default primary interface can work in tandem with the secondary interface. You can use either interface to load balance across your desired service.

SEE ALSO

Kubernetes Services

NodePort Service Support in Cloud-Native Contrail Networking

IN THIS SECTION

- Contrail Networking Load Balancer Objects | 320
- NodePort Service in Contrail Networking | 322
- Workflow of Creating NodePort Service | 323
- Kubernetes Probes and Kubernetes NodePort Service | 325
- NodePort Service Port Mapping | 325
- Example: NodePort Service Request Journey | 326
- Local Option Limitation in External Traffic Policy | 328
- Update or Delete a Service, or Remove a Pod from Service | 328

Juniper® Networks supports Kubernetes NodePort service in environments using Cloud-Native Contrail Networking (CN2) Release 22.1 or later in a Kubernetes-orchestrated environment.

In Kubernetes, a service is an abstraction that defines a logical set of pods and the policy by which you (the administrator) can access the pods. Kubernetes selects the set of pods implementing a service based on the LabelSelector object in the service definition. NodePort service exposes a service on each node's IP at a static port. It maps the static port on each node with a port of the application on the pod.

In CN2, Kubernetes NodePort service is implemented using the InstanceIP resource and FloatingIP resource, both of which are similar to the ClusterIP service.

Kubernetes provides a flat networking model in which all pods can talk to each other. Network policy is added to provide security between the pods. CN2 integrated with Kubernetes adds networking functionality, including multi-tenancy, network isolation, micro-segmentation with network policies, and load balancing.


The following table lists the mapping between Kubernetes concepts and CN2 resources.

Kubernetes Concept	CN2 Resource
Namespace	Shared or single project
Pod	Virtual Machine
Service	Equal-cost multipath (ECMP) LoadBalancer
Ingress	HAProxy LoadBalancer for URL
Network Policy	Contrail Security

Table 23: Kubernetes Concepts to CN2 Resource Mapping

Contrail Networking Load Balancer Objects

Figure 16 on page 321 and the following list describe the load balancer objects in CN2.



- Each service in CN2 is represented by a load balancer object.
- For each service port, a listener object is created for the same service load balancer.


- For each listener there is a pool object.
- The pool contains members. Depending on the number of backend pods, one pool might have multiple members.
- Each member object in the pool maps to one of the backend pods.
- The contrail-kube-manager listens to kube-apiserver for the Kubernetes service. When a service is created, a load balancer object with loadbalancer_provider type native is created.
- The load balancer has a virtual IP address (VIP), which is the same as the service IP address.
- The service IP/VIP address is linked to the interface of each backend pod. This is accomplished with an ECMP load-balancer driver.
- The linkage from the service IP address to the interfaces of multiple backend pods creates an ECMP next hop in CN2. Traffic is load balanced from the source pod directly to one of the backend pods.
- The contrail-kube-manager continues to listen to kube-apiserver for any changes. Based on the pod list in the endpoints, contrail-kube-manager identifies the most current backend pods and updates members in the pool.


NodePort Service in Contrail Networking

A controller service is implemented in kube-manager. The kube-manager is the interface between Kubernetes core resources, such as service, and the extended Contrail resources, such as VirtualNetwork and RoutingInstance. This controller service watches events going through the resource endpoints. An endpoint receives an event for any change related to its service. The endpoint also receives an event for pods created and deleted that match the service selector. The controller service handles creating the Contrail resources needed: See Figure 17 on page 323.

- InstanceIP resource related to the ServiceNetwork
- FloatingIP resource and the associated VirtualMachineInterfaces

When you create a service, an associated endpoint is automatically created by Kubernetes, which allows the controller service to receive new requests.






Workflow of Creating NodePort Service

Figure 18 on page 324 and the following steps detail the workflow when NodePort service is created.

Figure 18: Creating NodePort Service



- **1.** When the NodePort service is created, InstanceIP (IIP) is created. The InstanceIP resource specifies a fixed IP address and its characteristics that belong to a subnet of a referred virtual network.
- **2.** Once the endpoint is connected to the NodePort service, the FloatingIP is created. The kube-manager watches for the creation of endpoints connected to a service.
- **3.** After a new endpoint is created, kube-manager creates an InstanceIP in the ServiceVirtualNetwork subnet. The kube-manager then creates a FloatingIP using the InstanceIP as the parent.
- **4.** The FloatingIP resource specifies a special kind of IP address that does not belong to a specific VirtualMachineInterface (VMI). The FloatingIP is assigned from a separate VirtualNetwork subnet and can be associated with multiple VMIs. When associated with multiple VMIs, traffic destined to the FloatingIP is distributed using ECMP across all VMIs.

Notes about VMIs:

- VMIs are dynamically updated as pods and labels are added and deleted.
- A VMI represents an interface (port) into a virtual network and might or might not have a corresponding virtual machine.

• A VMI has at minimum a MAC address and an IP address.

Notes about VMs:

- A VM resource represents a compute container such as VM, baremetal, pod, or container.
- Each VM can communicate with other VMs on the same tenant network, subject to policy restrictions.
- As tenant networks are isolated, VMs in one tenant cannot communicate with VMs in another tenant unless specifically allowed by policy.

Kubernetes Probes and Kubernetes NodePort Service

The kubelet, an agent that runs on each node, needs reachability to pods for liveness and readiness probes. Contrail network policy is created between the IP fabric network and pod network to provide reachability between node and pods. Whenever the pod network is created, the network policy is attached to the pod network to provide reachability between node and pods. As a result, any process in the node can reach the pods.

The Kubernetes NodePort service is based on node reachability to pods. Since CN2 provides connectivity between nodes and pods through the Contrail network policy, NodePort is supported.

The NodePort service supports two types of traffic:

- East-West
- Fabric to Pod

NodePort Service Port Mapping

The port mappings for the Kubernetes NodePort service are located in the FloatingIp resource in the YAML file. In FloatingIp, the ports are added in "floatingIpPortMappings".

If the targetPort is not mentioned in the service, then the port value is specified as the default.

Following is an example spec YAML file for the NodePort service with port details:

spec: clusterIP: 10.100.13.106 clusterIPs:

```
- 10.100.13.106
ports:
- port: 80
protocol: TCP
targetPort: 80
selector:
run: my-nginx
sessionAffinity: None
```

In the preceding example spec YAML file, "floatingIpPortMappings" are created in the FloatingIp resource.

Following is an example "floatingIpPortMappings" YAML file:

Example: NodePort Service Request Journey

Let's follow the journey of a NodePort service request from when the request gets to the node port until the service request reaches the backend pod.

The Nodeport service relies on kubeproxy. The Kubernetes network proxy (kube-proxy) is a daemon running on each node. The daemon reflects the services defined in the cluster and manages the rules to load balance requests to a service's backend pods.

In the following example, the NodePort service apple-service is created and its endpoints are associated with the service.

user@domain ~ % kubectl c	lescribe svc apple-service		
Name:	apple-service		
Namespace:	default		
Labels:	<none></none>		
Annotations:	<none></none>		

Selector:	app=apple
Type:	NodePort
IP Families:	<none></none>
IP:	10.105.135.144
IPs:	10.105.135.144
Port:	<unset> 5678/TCP</unset>
TargetPort:	5678/TCP
NodePort:	<unset> 31050/TCP</unset>
Endpoints:	10.244.0.4:5678
Session Affinity:	None
External Traffic Poli	cy: Cluster
Events:	<none></none>
user@domain ~ % kubec	l get endpoints apple-service
NAME ENDPO	INTS AGE
apple-service 10.24	1.0.4:5678 2d18h

Each time a service is created or deleted or the endpoints are modified, kube-proxy updates the iptables rules on each node of the cluster. View the iptables chains to understand and follow the journey of the request.

First, the KUBE-NODEPORTS chain allows the packets coming on service of type NodePort.

```
$ sudo iptables -L KUBE-NODEPORTS -t nat
Chain KUBE-NODEPORTS (1 references)
target prot opt source destination
KUBE-MARK-MASQ tcp -- anywhere anywhere /* default/apple-service */
tcp dpt:31050
KUBE-SVC-Y4TE457BRBWMNDKG tcp -- anywhere anywhere /* default/apple-
service */ tcp dpt:31050
```

Each packet coming into port 31050 is first handled by the KUBE-MARK-MASQ, which tags the packet with a 0x4000 value.

Next, the packet is handled by the KUBE-SVC-Y4TE457BRBWMNDKG chain (referenced in the KUBE-NODEPORTS chain above). If we take a closer look at that chain, we can see additional iptables chains:

```
$ sudo iptables -L KUBE-SVC-Y4TE457BRBWMNDKG -t nat
Chain KUBE-SVC-Y4TE457BRBWMNDKG (2 references)
target prot opt source destination
```

KUBE-SEP-LCGKUEHRD52LOEFX all -- anywhereanywhere/* default/apple-service */

Inspect the KUBE-SEP-LCGKUEHRD52LOEFX chains to see that they define the routing to one of the backend pods running the apple-service application.

```
$ sudo iptables -L KUBE-SEP-LCGKUEHRD52LOEFX -t nat
Chain KUBE-SEP-LCGKUEHRD52LOEFX (1 references)
target prot opt source destination
KUBE-MARK-MASQ all -- 10.244.0.4 anywhere /* default/apple-service */
DNAT tcp -- anywhere anywhere /* default/apple-service */ tcp
to:10.244.0.4:5678
```

This completes the journey of a NodePort service request from the point at which the request gets to the node port until the service request reaches the backend pod.

Local Option Limitation in External Traffic Policy

The NodePort service with externalTrafficPolicy set as Local is not supported in CN2 Release 22.1.

The externalTrafficPolicy denotes if this service wants to route external traffic to node-local or clusterwide endpoints.

- Local preserves the client source IP address and avoids a second hop for NodePort type services.
- Cluster obscures the client source IP address and might cause a second hop to another node.

Cluster is the default for externalTrafficPolicy.

Update or Delete a Service, or Remove a Pod from Service

- Update service—You can change any modifiable fields, excluding Name and Namespace. For example, you can change Nodeport service to ClusterIp by changing the Type field in the service YAML definition.
- Delete service—You can delete a service, irrespective of Type, with the command

kubectl delete -n <name_space> <service_name> .

 Remove pod from service—You can remove a pod from service by changing the Labels and Selector on the service or pod.

Configure ClusterIP Service by Assigning Endpoints

IN THIS SECTION

- ClusterIP Service without a Selector and Manually Assigned Endpoints | 329
- Configure ClusterIP Service | 330

ClusterIP Service without a Selector and Manually Assigned Endpoints

Juniper® Cloud-Native Contrail Networking (CN2) supports the ClusterIP service to work with manually assigned endpoints without adding a selector in the service. ClusterIP is the default type of service, which is used to expose a service on an IP address internal to the cluster. Access is only permitted from within the cluster.

When creating the endpoint for the service, it's important to add the IP address and targetRef in the endpoint. The targetRef should include the pod details such as kind, name, and namespace. Without these details, connectivity to the ClusterIP service will not work.

Pod details provided in the targetRef of the endpoint are used to add the virtual machine interface (VMI) reference of the corresponding pod in the service floating IP (FIP) object.

See the following example of pod details provided in targetRef:

```
apiVersion: v1
kind: Endpoints
metadata:
   labels:
      app: nginx
   name: nginx
   namespace: clusterip
subsets:
      addresses:
      ip: 10.128.0.151
      targetRef:
        kind: Pod
        name: nginx-7d79f94b45-9tfjm
        namespace: clusterip
```

```
    ip: 10.128.0.175
    targetRef:

            kind: Pod
            name: nginx-7d79f94b45-kcb4s
            namespace: clusterip

    ports:

            name: http
            port: 8080
            protocol: TCP
```

Configure ClusterIP Service

Following is an example procedure to configure ClusterIP service by manually assigning endpoints and without adding a selector.

1. Deploy the application deployment. In this example, the NGINX application is deployed.

```
apiVersion: v1
kind: Namespace
metadata:
  name: clusterip
---
apiVersion: apps/v1 # for versions before 1.9.0 use apps/v1beta2
kind: Deployment
metadata:
  name: nginx
  namespace: clusterip
spec:
  strategy:
    type: Recreate
  selector:
    matchLabels:
      app: nginx
  replicas: 2 # tells deployment to run 1 pods matching the template
  template: # create pods using pod definition in this template
    metadata:
      labels:
        app: nginx
    spec:
      containers:
```

```
    name: nginx
    image: svl-artifactory.juniper.net/atom-docker/nginxinc/nginx-unprivileged:1.21
    ports:
    containerPort: 8080
```

2. Check the pods.

[core@ocp-avyaw-bc6wig-ctrl-3 ~]\$ kubectl get po -n clusterip -o wide						
NAME	READY	STATUS	RESTARTS	AGE	IP	
NODE	NOMIN	NATED NODE	READINES	SS GATE	S	
nginx-7d79f94b45-9tfjm	1/1	Running	0	10m	10.128.0.151	ocp-avyaw-bc6wig-
worker-2 <none></none>	<none< td=""><td>e></td><td></td><td></td><td></td><td></td></none<>	e>				
nginx-7d79f94b45-kcb4s	1/1	Running	0	10m	10.128.0.175	ocp-avyaw-bc6wig-
worker-1 <none></none>	<none< td=""><td>e></td><td></td><td></td><td></td><td></td></none<>	e>				

3. Deploy the ClusterIP service without defining a selector in spec. In this example, the ClusterIP service maps to port 8080 on the application pod.

```
apiVersion: v1
kind: Service
metadata:
   name: nginx
   namespace: clusterip
   labels:
      app: nginx
spec:
   ports:
      name: http
      port: 8080
      protocol: TCP
      targetPort: 8080
   type: ClusterIP
```

4. Verify the service.

[core@ocp-avyaw-bc6wig-ctrl-3 ~]\$ kubectl get svc -n clusterip					
NAME	TYPE	CLUSTER-IP	EXTERNAL-IP	PORT(S)	AGE
nginx	ClusterIP	172.30.74.100	<none></none>	8080/TCP	3m

5. Create the endpoints for the service. Add the IP address and targetRef with pod details in the endpoints.

```
apiVersion: v1
kind: Endpoints
metadata:
  labels:
    app: nginx
  name: nginx
  namespace: clusterip
subsets:
- addresses:
  - ip: 10.128.0.151
    targetRef:
      kind: Pod
      name: nginx-7d79f94b45-9tfjm
      namespace: clusterip
  - ip: 10.128.0.175
    targetRef:
      kind: Pod
      name: nginx-7d79f94b45-kcb4s
      namespace: clusterip
  ports:
  - name: http
    port: 8080
    protocol: TCP
```

6. Check the connectivity to the ClusterIP service from any test pod.

```
[core@ocp-avyaw-bc6wig-ctrl-2 ~]$ kubectl exec -it curl-test -n clusterip sh
# curl 172.30.74.100:8080
<!DOCTYPE html>
<html>
<html>
<head>
<title>Welcome to nginx!</title>
<style>
html { color-scheme: light dark; }
body { width: 35em; margin: 0 auto;
font-family: Tahoma, Verdana, Arial, sans-serif; }
</style>
</head>
```

<body> <h1>Welcome to nginx!</h1> If you see this page, the nginx web server is successfully installed and working. Further configuration is required. For online documentation and support please refer to nginx.org.
br/> Commercial support is available at

nginx.com.

Thank you for using nginx. </body> </html>

FloatingIP/DNAT for IPv6 Addresses

SUMMARY

Juniper Cloud-Native Contrail release 23.1 supports FloatingIP, or Dynamic Network Address Translation (DNAT), for dual stack-enabled services (ClusterIP). This article provides information about how this feature works in CN2.

IN THIS SECTION

Prerequisites | 333
FloatingIP/DNAT Overview | 334
DNAT for IPv6 Overview | 334
Deploy FloatingIP/DNAT | 334

Prerequisites

This feature requires the following:

- An environment running CN2 release 23.1 or later
- A Kubeadm or Kubespray Kubernetes cluster with dual-stack featureGate enabled. For more information, see "IPv4 and IPv6 Dual-Stack Networking" on page 19.
- Kubernetes nodes configured with dual stack network interfaces

FloatingIP/DNAT Overview

In CN2, a FloatingIP implements ClusterIP functionality. After you create a service, a FloatingIP is allocated to that service from the service subnet and associated to all the back-end pod VMIs in the cluster. The vRouter performs DNAT for the back-end pods. This process comprises Equal-Cost Multi-Path Routing (ECMP) load balancing, where the back-end pod VMIs act as ECMP paths.

DNAT for IPv6 Overview

CN2 release 23.1 supports DNAT (FloatingIP) for IPv4 and IPv6 addresses for the CN2 ClusterIP service. DNAT for IPv6 functions the same as DNAT for IPv4; create a service (ClusterIP), specify PreferDualStack for the ipFamilyPolicy, and an IPv6 FloatingIP is allocated to that service. The vRouter performs DNAT and routes traffic to the next hop, or the translated destination address (back end pod VMI). from external networks to your back-end pod VMIs.

Deploy FloatingIP/DNAT

Complete the following steps to deploy this feature.

• Configure and install a Deployment. The Deployment object creates the back-end pods for the ClusterIP service. The following is an example Deployment. This Deployment creates a pod named nginx with a mounted nginx-xconf config.

```
apiVersion: apps/v1
kind: Deployment
metadata:
  name: nginx
  namespace: example-clusterip6
spec:
  selector:
    matchLabels:
      app: nginx
  replicas: 1
  template:
    metadata:
      labels:
        app: nginx
    spec:
      tolerations:
```

- key: "node.kubernetes.io/unreachable" operator: "Exists" effect: "NoExecute" tolerationSeconds: 2 - key: "node.kubernetes.io/not-ready" operator: "Exists" effect: "NoExecute" tolerationSeconds: 2 containers: - name: nginx image: <repository>:<tag> ports: - containerPort: 8080 volumeMounts: - name: nginx-conf mountPath: /etc/nginx/nginx.conf subPath: nginx.conf readOnly: true volumes: - name: nginx-conf configMap: name: nginx-conf items: - key: nginx.conf path: nginx.conf
- Create a ClusterIP service. The following is an example service.

```
apiVersion: v1
kind: Service
metadata:
   name: nginx
   namespace: clusterip6
   labels:
      app: nginx
spec:
   ports:
      name: http
      port: 8080
      protocol: TCP
      targetPort: 8080
   selector:
```

```
app: nginx
ipFamilies:
- "IPv6"
```

Note the following fields:

- labels: Identifies back-end pods with the app: nginx label.
- selector: Instructs the service to select VMIs belonging to back-end pods the with app: nginx label.
- ipFamilies: Specifies the IP family the ClusterIP service uses. The default is IPv4. To use both IP families, use the value IpFamilyPolicy: PreferDualStack.



Analytics

Contrail Networking Analytics | 338 Contrail Networking Metric List | 344 Kubernetes Metric List | 358 Cluster Node Metric List | 396 Contrail Networking Alert List | 414 vRouter Session Analytics in Contrail Networking | 424 Extend TLS Analytics | 432 Centralized Logging | 439 Port-Based Mirroring | 442 Flow-Based Mirroring | 447 Configurable Categories of Metrics Collection and Reporting (Tech Preview) | 453 Juniper CN2 Technology Previews (Tech Previews) | 459

Contrail Networking Analytics

IN THIS SECTION

- Overview: Analytics | 338
- Metrics | 339
- Supported Metrics | 339
- Alerts | 340
- Architecture | 341
- Configuration | 342
- 🖕 🛛 Grafana | 343

Overview: Analytics

Analytics is an optional feature set in Juniper® Cloud-Native Contrail Networking (CN2) Release 22.1. The analytics are packaged separately from the CN2 core Container Network Interface (CNI) components. Analytics also has its own installation procedure. The package consists of a combination of open-source software and Juniper developed software that integrates with CN2.

The analytics features fit into the following high-level functional areas:

- Metrics—Statistical time series data collected from the Contrail Networking components and the base Kubernetes system
- Flow and Session Records-Network traffic information collected from the CN2 vRouter
- Sandesh User Visible Entities (UVE)—Records representing the system-wide state of externally visible objects that are collected from the CN2 vRouter and control node components
- Logs-Log messages collected from Kubernetes pods
- Introspect—A diagnostic utility that provides the ability to browse the internal state of the CN2 components

Metrics

Data Model

Metric information is based on a numerical time series data model. Each data point in a series is a sample of some system state that gets collected at a regular interval. A sampled value is recorded along with a timestamp at which the collection occurred. A sample record can also contain an optional set of key-value pairs called labels. Labels provide a dimension capability for metrics where a given combination of labels for the same metric name identifies a particular dimensional instantiation of that metric. For example, a metric named api_http_requests_total can utilize labels to provide visibility into the request counts at a URL and method type level. In the following example, the metric record for a sample value of 10 includes labels that indicate the type of request.

api_http_requests_total{method="POST", handler="/messages"} 10

Metric Data Types

Although all metric sample values are just numbers, the concept of data type exists within this numerical data model. A metric can be one of the following types:

- Counter—A cumulative metric that represents a single monotonically increasing counter whose value can only increase or be reset to zero on restart.
- Gauge—A metric that represents a single numerical value that can arbitrarily go up and down.
- Histogram—A histogram samples observations (such as request durations or response sizes) and counts them in configurable buckets. The histogram also provides a sum of all observed values.
- Summary—Similar to a histogram, a summary samples observations (such as request durations and response sizes). While it also provides a total count of observations and a sum of all observed values, the summary calculates configurable quantiles over a sliding time window.

The metric functionality in CN2 is implemented by Prometheus. For additional details about the metric data model, see the documentation at Prometheus.

Supported Metrics

The analytics solution supports the following sets of metrics:

 "Contrail Networking Metric List" on page 344—Metrics collected from the vRouter and control node components.

- "Kubernetes Metric List" on page 358—Metrics collected from various Kubernetes components, such as apiserver, etcd, kubelet, and so on.
- "Cluster Node Metrics" on page 396—Host-level metrics collected from the Kubernetes cluster nodes.

Alerts

Alerts are generated based on an analysis of collected metric data. Every supported alert type is based on a rule definition that contains the following information:

- Alert Name—A unique string identifier for the alert type
- Condition Expression—A Prometheus query language expression that gets evaluated against collected metric values to determine if the alert condition exists
- Condition Duration—The amount of time the problematic condition has to exist for the alert to be generated
- Severity—The alert level (critical, major, warning, info.)
- Summary-A short description of the problematic condition
- Description-A detailed description of the problematic condition

The CN2 analytics solution installs a set of "predefined alert rules" on page 414. You can also define your own custom alert rules. The creation of PrometheusRule Kubernetes resources in the namespace where the analytics Helm chart is deployed supports defining custom alerts. Following is an example of a custom alert rule.

```
apiVersion: monitoring.coreos.com/v1
kind: PrometheusRule
metadata:
name: acme-corp-rules
spec:
groups:
- name: acme-corp.rules
rules:
- alert: HostUnusualNetworkThroughputOut
expr: "sum by (instance) (rate(node_network_transmit_bytes_total[2m])) / 1024 / 1024 >
100"
labels:
severity: warning
```


```
annotations:
    summary: "Host unusual network throughput out (instance {{ $labels.instance }})"
    description: "Host network interfaces are sending too much data (> 100 MB/s)\n VALUE
= {{ $value }}"
```

Prometheus stores generated alerts as records that can be viewed in the Grafana UI. The AlertManager component supports integration with external systems, such as PagerDuty, OpsGenie, or email for alert notification.

Architecture

As shown in Figure 19 on page 342, Prometheus is the core component of the metrics architecture. Prometheus implements the following functionality:

- Collection—A periodic polling mechanism that invokes API calls against other components (exporters) to pull values for a set of metrics
- Storage—A time series database that provides persistence for the metrics collected from the exporters
- Query—An API supporting an expression language called PromQL (Prometheus query language) that allows the historical metric information to be retrieved from the database
- Alerting—A framework providing an ability to define rules that produce alerts when certain conditions are observed in the collected metric data



The other components of the metrics architecture are:

- Grafana—A service that provides a Web UI interface allowing the user to visualize the metric data in graphs.
- AlertManager—An integration service that notifies external systems of alerts generated by Prometheus.


Configuration

The metrics functionality does not require any configuration by the end user. The installation of analytics takes care of configuring Prometheus to collect metrics from the exporters that provide all of the metrics described in "Supported Metrics" on page 339. A group of default alerting rules is also automatically set up as part of the installation. You can extend functionality through additional configuration after the installation. For example, you can define customer-specific alerting rules. You can also configure the AlertManager to integrate with any of the supported external systems in your environment.

The configuration of Prometheus and AlertManager involves an additional architectural component called the Prometheus Operator. As shown in Figure 20 on page 343, configuration is specified as Kubernetes custom resources. The Prometheus Operator translates the contents of these resources into

the native configuration that the Prometheus components recognize. The Operator also updates the components accordingly and restarts them whenever a configuration change requires a restart.

Figure 20: Prometheus Operator



Documentation for the full set of resources that the Prometheus Operator supports is available at Prometheus Operator API. Juniper Networks recommends that you limit your configurations to the subset of resource types related to alert rule definition and external system integration.

Grafana

The main UI for viewing metric data and alerts is Grafana. The analytics installation sets up the Grafana service and configures it with Prometheus as a data source. A set of default dashboards are also created.

Access the Grafana Web UI at https://<k8sClusterIP>/grafana/login. The default login credentials are user admin and password prom-operator.

RELATED DOCUMENTATION

vRouter Session Analytics in Contrail Networking | 424

Contrail Networking Metric List

Metric Name	Туре	Description
controller_state	gauge	Controller state (0=Functional, 1=Non- Functional).
controller_connection_status	gauge	Connection status (0=Up, 1=Down, 2=Initializing).
<pre>controller_bgp_router_output_queue_ depth</pre>	gauge	BGP router output queue depth.
controller_bgp_router_num_bgp_peers	gauge	Number of BGP peers.
controller_bgp_router_num_up_bgp_pe ers	gauge	Number of up BGP peers.
<pre>controller_bgp_router_num_deleting_ bgp_peers</pre>	gauge	Number of deleting BGP peers.
controller_bgp_router_num_bgpaas_pe ers	gauge	Number of BGPaas peers.
controller_bgp_router_num_up_bgpaas _peers	gauge	Number of up BGPaas peers.
<pre>controller_bgp_router_num_deleting_ bgpaas_peers</pre>	gauge	Number of deleting BGPaas peers.
<pre>controller_bgp_router_num_xmpp_peer s</pre>	gauge	Number of XMPP peers.

Metric Name	Туре	Description
<pre>controller_bgp_router_num_up_xmpp_p eers</pre>	gauge	Number of up XMPP peers.
<pre>controller_bgp_router_num_deleting_ xmpp_peers</pre>	gauge	Number of deleting XMPP peers.
<pre>controller_bgp_router_num_routing_i nstances</pre>	gauge	BGP router number of routing instances.
<pre>controller_bgp_router_num_deleting_ routing_instances</pre>	gauge	BGP router number of deleting routing instances.
<pre>controller_bgp_router_num_service_c hains</pre>	gauge	Number of service chains.
<pre>controller_bgp_router_num_down_serv ice_chains</pre>	gauge	Number of down service chains.
<pre>controller_bgp_router_num_static_ro utes</pre>	gauge	Number of static routes.
<pre>controller_bgp_router_num_down_stat ic_routes</pre>	gauge	Number of down static routes.
<pre>controller_bgp_router_ifmap_num_pee r_clients</pre>	gauge	Number of IF-MAP peer clients.
<pre>controller_bgp_router_config_db_con n_status</pre>	gauge	Status of config database connection (0=Down, 1=Up).
controller_bgp_peer_state	gauge	BGP peer state (0=Idle, 1=Active, 2=Connect, 3=OpenSent, 4=OpenConfirm, 5=Established).
controller_bgp_peer_flaps_total	counter	BGP peer total flaps.

Metric Name	Туре	Description
controller_bgp_peer_received_messag es_total	counter	Total BGP peer messages received.
<pre>controller_bgp_peer_received_open_m essages_total</pre>	counter	Total BGP peer open messages received.
<pre>controller_bgp_peer_received_keepal ive_messages_total</pre>	counter	Total BGP peer keepalive messages received.
<pre>controller_bgp_peer_received_notifi cation_messages_total</pre>	counter	Total BGP peer notification messages received.
<pre>controller_bgp_peer_received_update _messages_total</pre>	counter	Total BGP peer update messages received.
<pre>controller_bgp_peer_received_close_ messages_total</pre>	counter	Total BGP peer close messages received.
controller_bgp_peer_sent_messages_t otal	counter	Total BGP peer messages sent.
controller_bgp_peer_sent_open_messa ges_total	counter	Total BGP peer open messages sent.
controller_bgp_peer_sent_keepalive_ messages_total	counter	Total BGP peer keepalive messages sent.
<pre>controller_bgp_peer_sent_notificati on_messages_total</pre>	counter	Total BGP peer notification messages sent.
controller_bgp_peer_sent_update_mes sages_total	counter	Total BGP peer update messages sent.
controller_bgp_peer_sent_close_mess ages_total	counter	Total BGP peer close messages sent.

Metric Name	Туре	Description
<pre>controller_bgp_peer_received_reacha ble_routes_total</pre>	counter	Total BGP peer reachable routes received.
<pre>controller_bgp_peer_received_unreac hable_routes_total</pre>	counter	Total BGP peer unreachable routes received.
<pre>controller_bgp_peer_received_end_of _rib_total</pre>	counter	Total BGP peer end-of-RIB markers received.
<pre>controller_bgp_peer_sent_reachable_ routes_total</pre>	counter	Total BGP peer reachable routes sent.
controller_bgp_peer_sent_unreachabl e_routes_total	counter	Total BGP peer unreachable routes sent.
controller_bgp_peer_sent_end_of_rib _total	counter	Total BGP peer end-of-RIB markers sent.
<pre>controller_bgp_peer_received_bytes_ total</pre>	counter	Total BGP peer bytes received.
<pre>controller_bgp_peer_receive_socket_ calls_total</pre>	counter	Total BGP peer receive socket calls.
<pre>controller_bgp_peer_blocked_receive _socket_calls_microsecond_duration_ total</pre>	counter	BGP peer total microseconds blocked on socket receive calls.
<pre>controller_bgp_peer_blocked_receive _socket_calls_total</pre>	counter	Total BGP peer receive socket calls blocked.
controller_bgp_peer_sent_bytes_tota l	counter	Total BGP peer bytes sent.
<pre>controller_bgp_peer_send_socket_cal ls_total</pre>	counter	Total BGP peer send socket calls.

Metric Name	Туре	Description
<pre>controller_bgp_peer_blocked_send_so cket_calls_microsecond_duration_tot al</pre>	counter	BGP peer total microseconds blocked on socket send calls.
<pre>controller_bgp_peer_blocked_send_so cket_calls_total</pre>	counter	Total BGP peer send socket calls blocked.
<pre>controller_bgp_peer_route_update_er ror_bad_inet6_xml_token_total</pre>	counter	BGP peer total route update errors (bad inet6 XML token).
<pre>controller_bgp_peer_route_update_er ror_bad_inet6_prefix_total</pre>	counter	BGP peer total route update errors (bad inet6 prefix).
<pre>controller_bgp_peer_route_update_er ror_bad_inet6_nexthop_total</pre>	counter	BGP peer total route update errors (bad inet6 next hop).
<pre>controller_bgp_peer_route_update_er ror_bad_inet6_afi_safi_total</pre>	counter	BGP peer total route update errors (bad inet6 AFI/SAFI).
<pre>controller_bgp_peer_received_route_ paths_total</pre>	counter	Total BGP peer route paths received.
<pre>controller_bgp_peer_received_route_ primary_paths_total</pre>	counter	Total BGP peer route primary paths received.
<pre>controller_xmpp_peer_state</pre>	counter	XMPP peer state (0=Idle, 1=Active, 2=Connect, 3=OpenSent, 4=OpenConfirm, 5=Established).
<pre>controller_xmpp_peer_received_messa ges_total</pre>	counter	Total messages received from XMPP peer.
<pre>controller_xmpp_peer_received_open_ messages_total</pre>	counter	Total open messages received from XMPP peer.
<pre>controller_xmpp_peer_received_keepa live_messages_total</pre>	counter	Total keepalive messages received from XMPP peer.

Metric Name	Туре	Description
<pre>controller_xmpp_peer_received_notif ication_messages_total</pre>	counter	Total notification messages received from XMPP peer.
<pre>controller_xmpp_peer_received_updat e_messages_total</pre>	counter	Total update messages received from XMPP peer.
<pre>controller_xmpp_peer_received_close _messages_total</pre>	counter	Total close messages received from XMPP peer.
<pre>controller_xmpp_peer_sent_messages_ total</pre>	counter	Total messages sent to XMPP peer.
<pre>controller_xmpp_peer_sent_open_mess ages_total</pre>	counter	Total open messages sent to XMPP peer.
<pre>controller_xmpp_peer_sent_keepalive _messages_total</pre>	counter	Total keepalive messages sent to XMPP peer.
<pre>controller_xmpp_peer_sent_notificat ion_messages_total</pre>	counter	Total notification messages sent to XMPP peer.
<pre>controller_xmpp_peer_sent_update_me ssages_total</pre>	counter	Total update messages sent to XMPP peer.
<pre>controller_xmpp_peer_sent_close_mes sages_total</pre>	counter	Total close messages sent to XMPP peer.
<pre>controller_xmpp_peer_received_reach able_routes_total</pre>	counter	Total reachable routes received from XMPP peer.
<pre>controller_xmpp_peer_received_unrea chable_routes_total</pre>	counter	Total unreachable routes received from XMPP peer.
<pre>controller_xmpp_peer_received_end_o f_rib_total</pre>	counter	Total end-of-RIB markers received from XMPP peer.

Metric Name	Туре	Description
<pre>controller_xmpp_peer_sent_reachable _routes_total</pre>	counter	Total reachable routes sent to XMPP peer.
<pre>controller_xmpp_peer_sent_unreachab le_routes_total</pre>	counter	Total unreachable routes sent to XMPP peer.
<pre>controller_xmpp_peer_sent_end_of_ri b_total</pre>	counter	Total end-of-RIB markers sent to XMPP peer.
<pre>controller_xmpp_peer_route_update_e rror_bad_inet6_xml_token_total</pre>	counter	XMPP peer total route update errors (bad inet6 XML token).
<pre>controller_xmpp_peer_route_update_e rror_bad_inet6_prefix_total</pre>	counter	XMPP peer total route update errors (bad inet6 prefix).
<pre>controller_xmpp_peer_route_update_e rror_bad_inet6_nexthop_total</pre>	counter	XMPP peer total route update errors (bad inet6 next hop).
<pre>controller_xmpp_peer_route_update_e rror_bad_inet6_afi_safi_total</pre>	counter	XMPP peer total route update errors (bad inet6 AFI/SAFI).
<pre>controller_xmpp_peer_received_route _paths_total</pre>	counter	Total XMPP peer route paths received.
<pre>controller_xmpp_peer_received_route _primary_paths_total</pre>	counter	Total XMPP peer route primary paths received.
<pre>controller_peer_received_reachable_ routes_total</pre>	counter	Total reachable routes received from peer.
<pre>controller_peer_received_unreachabl e_routes_total</pre>	counter	Total unreachable routes received from peer.
<pre>controller_peer_received_end_of_rib _total</pre>	counter	Total end-of-RIB markers received from peer.

Metric Name	Туре	Description
<pre>controller_peer_sent_reachable_rout es_total</pre>	counter	Total reachable routes sent to peer.
<pre>controller_peer_sent_unreachable_ro utes_total</pre>	counter	Total unreachable routes sent to peer.
controller_peer_sent_end_of_rib_tot al	counter	Total end-of-RIB markers sent to peer.
<pre>controller_virtual_network_routing_ instance_ipv4_table_prefixes</pre>	gauge	Virtual network IPv4 routing table prefixes.
<pre>controller_virtual_network_routing_ instance_ipv4_table_primary_paths</pre>	gauge	Virtual network IPv4 routing table primary paths.
<pre>controller_virtual_network_routing_ instance_ipv4_table_secondary_paths</pre>	gauge	Virtual network IPv4 routing table secondary paths.
<pre>controller_virtual_network_routing_ instance_ipv4_table_infeasible_path s</pre>	gauge	Virtual network IPv4 routing table infeasible paths.
<pre>controller_virtual_network_routing_ instance_ipv4_table_total_paths</pre>	gauge	Virtual network IPv4 routing table total paths.
<pre>controller_virtual_network_routing_ instance_ipv6_table_prefixes</pre>	gauge	Virtual network IPv6 routing table prefixes.
<pre>controller_virtual_network_routing_ instance_ipv6_table_primary_paths</pre>	gauge	Virtual network IPv6 routing table primary paths.
<pre>controller_virtual_network_routing_ instance_ipv6_table_secondary_paths</pre>	gauge	Virtual network IPv6 routing table secondary paths.
<pre>controller_virtual_network_routing_ instance_ipv6_table_infeasible_path s</pre>	gauge	Virtual network IPv6 routing table infeasible paths.

Metric Name	Туре	Description
<pre>controller_virtual_network_routing_ instance_ipv6_table_total_paths</pre>	gauge	Virtual network IPv6 routing table total paths.
<pre>controller_virtual_network_routing_ instance_evpn_table_prefixes</pre>	gauge	Virtual network EVPN routing table prefixes.
<pre>controller_virtual_network_routing_ instance_evpn_table_primary_paths</pre>	gauge	Virtual network EVPN routing table primary paths.
controller_virtual_network_routing_ instance_evpn_table_secondary_paths	gauge	Virtual network EVPN routing table secondary paths.
<pre>controller_virtual_network_routing_ instance_evpn_table_infeasible_path s</pre>	gauge	Virtual network EVPN routing table infeasible paths.
<pre>controller_virtual_network_routing_ instance_evpn_table_total_paths</pre>	gauge	Virtual network EVPN routing table total paths.
<pre>controller_virtual_network_routing_ instance_ermvpn_table_prefixes</pre>	gauge	Virtual network ERMVPN routing table prefixes.
controller_virtual_network_routing_ instance_ermvpn_table_primary_paths	gauge	Virtual network ERMVPN routing table primary paths.
controller_virtual_network_routing_ instance_ermvpn_table_secondary_pat hs	gauge	Virtual network ERMVPN routing table secondary paths.
controller_virtual_network_routing_ instance_ermvpn_table_infeasible_pa ths	gauge	Virtual network ERMVPN routing table infeasible paths.
controller_virtual_network_routing_ instance_ermvpn_table_total_paths	gauge	Virtual network ERMVPN routing table total paths.

Metric Name	Туре	Description
<pre>controller_virtual_network_routing_ instance_mvpn_table_prefixes</pre>	gauge	Virtual network MVPN routing table prefixes.
<pre>controller_virtual_network_routing_ instance_mvpn_table_primary_paths</pre>	gauge	Virtual network MVPN routing table primary paths.
<pre>controller_virtual_network_routing_ instance_mvpn_table_secondary_paths</pre>	gauge	Virtual network MVPN routing table secondary paths.
<pre>controller_virtual_network_routing_ instance_mvpn_table_infeasible_path s</pre>	gauge	Virtual network MVPN routing table infeasible paths.
<pre>controller_virtual_network_routing_ instance_mvpn_table_total_paths</pre>	gauge	Virtual network MVPN routing table total paths.
virtual_router_cpu_1min_load_avg	gauge	Virtual router CPU 1 minute load average.
virtual_router_cpu_5min_load_avg	gauge	Virtual router CPU 5 minute load average.
virtual_router_cpu_15min_load_avg	gauge	Virtual router CPU 15 minute load average.
virtual_router_system_memory_bytes	gauge	Virtual router total system memory.
virtual_router_system_memory_free_b ytes	gauge	Virtual router system memory free.
virtual_router_system_memory_used_b ytes	gauge	Virtual router system memory used.
virtual_router_system_memory_cached _bytes	gauge	Virtual router system memory cached.
virtual_router_system_memory_buffer s	gauge	Virtual router system memory buffers.

Metric Name	Туре	Description
<pre>virtual_router_virtual_memory_kilob ytes</pre>	gauge	Virtual router virtual memory.
virtual_router_resident_memory_kilo bytes	gauge	Virtual router resident memory.
<pre>virtual_router_peak_virtual_memory_ bytes</pre>	gauge	Virtual router peak virtual memory.
<pre>virtual_router_phys_if_input_packet s_total</pre>	counter	Total packets received by physical interface.
<pre>virtual_router_phys_if_output_packe ts_total</pre>	counter	Total packets sent by physical interface.
<pre>virtual_router_phys_if_input_bytes_ total</pre>	counter	Total bytes received by physical interface.
virtual_router_phys_if_output_bytes _total	counter	Total bytes sent by physical interface.
virtual_router_input_packets_total	counter	Total packets received by virtual router.
virtual_router_output_packets_total	counter	Total packets sent by virtual router.
virtual_router_input_bytes_total	counter	Total bytes received by virtual router.
virtual_router_output_bytes_total	counter	Total bytes sent by virtual router.
virtual_router_flows_total	counter	Total virtual router flows.
virtual_router_aged_flows_total	counter	Total virtual router aged flows.
virtual_router_active_flows	gauge	Current virtual router active flows.
virtual_router_hold_flows	gauge	Current virtual router hold flows.

Metric Name	Туре	Description
virtual_router_added_flows_diff_tot al	gauge	Virtual router added flows since last sample.
<pre>virtual_router_exception_packets_to tal</pre>	counter	Total virtual router exception packets.
<pre>virtual_router_exception_packets_al lowed_total</pre>	counter	Total virtual router exception packets allowed.
<pre>virtual_router_exception_packets_dr opped_total</pre>	counter	Total virtual router exception packets dropped.
virtual_router_dropped_packets_tota l	counter	Total packets dropped.
virtual_router_vhost_dropped_packet s_total	counter	Total virtual host packets dropped.
virtual_router_input_bandwidth_util ization	gauge	Ingress bandwidth of physical interface where the value is obtained by dividing the bandwidth computed in bits per second (bps) by speed of the physical interface.
virtual_router_output_bandwidth_uti lization	gauge	Egress bandwidth of physical interface where the value is obtained by dividing the bandwidth computed in bps by speed of the physical interface.
<pre>virtual_router_vhost_interface_inpu t_bytes_total</pre>	counter	Total bytes received by virtual host interface.
<pre>virtual_router_vhost_interface_outp ut_bytes_total</pre>	counter	Total bytes sent by virtual host interface.
virtual_router_vhost_interface_inpu t_packets_total	counter	Total packets received by virtual host interface.

Metric Name	Туре	Description
virtual_router_vhost_interface_outp ut_packets_total	counter	Total packets sent by virtual host interface.
virtual_router_virtual_networks	gauge	Current number of virtual networks.
virtual_router_virtual_machines	gauge	Current number of virtual machines.
<pre>virtual_router_virtual_machine_inte rfaces</pre>	gauge	Current number of virtual machine interfaces.
virtual_router_interfaces_down	gauge	Current number of down interfaces.
virtual_router_agent_state	gauge	Virtual router agent state (0=Functional, 1=Non-Functional).
virtual_router_connection_status	gauge	Connection status (0=Up, 1=Down, 2=Initializing).
virtual_router_virtual_network_inpu t_packets_total	counter	Total input packets received.
<pre>virtual_router_virtual_network_outp ut_packets_total</pre>	counter	Total output packets sent.
virtual_router_virtual_network_inpu t_bytes_total	counter	Total input bytes received.
<pre>virtual_router_virtual_network_outp ut_bytes_total</pre>	counter	Total output bytes sent.
virtual_router_virtual_network_flow s	gauge	Current number of flows.
<pre>virtual_router_virtual_network_ingr ess_flows</pre>	gauge	Current number of ingress flows.

Metric Name	Туре	Description
<pre>virtual_router_virtual_network_egre ss_flows</pre>	gauge	Current number of egress flows.
<pre>virtual_router_virtual_network_floa ting_ips</pre>	gauge	Current number of floating IP addresses.
<pre>virtual_router_virtual_network_flow _policy_rule_hits_total</pre>	counter	Total number of flow policy rule hits.
<pre>virtual_router_virtual_network_vrf_ bridge_route_table_entries</pre>	gauge	Virtual routing and forwarding bridge route table current entries.
<pre>virtual_router_virtual_network_vrf_ evpn_route_table_entries</pre>	gauge	Virtual routing and forwarding EVPN route table current entries.
<pre>virtual_router_virtual_network_vrf_ inet4_unicast_route_table_entries</pre>	gauge	Virtual routing and forwarding inet4 unicast table current entries.
<pre>virtual_router_virtual_network_vrf_ inet4_multicast_route_table_entries</pre>	gauge	Virtual routing and forwarding inet4 multicast table current entries.
<pre>virtual_router_virtual_network_vrf_ inet6_unicast_route_table_entries</pre>	gauge	Virtual routing and forwarding inet6 unicast table current entries.
<pre>virtual_router_virtual_machine_inte rface_input_bytes_total</pre>	counter	Total input bytes received by virtual machine interface.
<pre>virtual_router_virtual_machine_inte rface_output_bytes_total</pre>	counter	Total output bytes sent by virtual machine interface.
<pre>virtual_router_virtual_machine_inte rface_input_packets_total</pre>	counter	Total input packets received by virtual machine interface.
<pre>virtual_router_virtual_machine_inte rface_output_packets_total</pre>	counter	Total output packets sent by virtual machine interface.

Metric Name	Туре	Description
<pre>virtual_router_virtual_machine_inte rface_active_flows</pre>	gauge	Current virtual machine interface active flows.
<pre>virtual_router_virtual_machine_inte rface_hold_flows</pre>	gauge	Current virtual machine interface hold flows.
<pre>virtual_router_virtual_machine_inte rface_added_flows_diff_total</pre>	gauge	Virtual machine interface added flows since last sample.
<pre>virtual_router_virtual_machine_inte rface_dropped_packets_total</pre>	counter	Virtual machine interface total dropped packets.

RELATED DOCUMENTATION

Contrail Networking Analytics | 338

Kubernetes Metric List | 358

Cluster Node Metric List | 396

Contrail Networking Alert List | 414

Kubernetes Metric List

Table 25: Kubernetes Metric List

Metric Name	Туре	Description
apiextensions_openapi_v2_regenerati on_count	counter	[ALPHA] Counter of OpenAPI v2 spec regeneration count broken down by causing CRD name and reason.

Metric Name	Туре	Description
apiserver_admission_controller_admi ssion_duration_seconds	histogram	[ALPHA] Admission controller latency histogram in seconds, identified by name and broken out for each operation and API resource and type (validate or admit).
apiserver_admission_step_admission_ duration_seconds_summary	summary	[ALPHA] Admission sub-step latency summary in seconds, broken out for each operation and API resource and step type (validate or admit).
apiserver_admission_webhook_admissi on_duration_seconds	histogram	[ALPHA] Admission webhook latency histogram in seconds, identified by name and broken out for each operation and API resource and type (validate or admit).
apiserver_admission_webhook_rejecti on_count	counter	[ALPHA] Admission webhook rejection count, identified by name and broken out for each admission type (validating or admit) and operation. Additional labels specify an error type (calling_webhook_error or apiserver_internal_error if an error occurred; no_error otherwise) and optionally a non-zero rejection code if the webhook rejects the request with an HTTP status code (honored by the apiserver when the code is greater than or equal to 400). Codes greater than 600 are truncated to 600, to keep the metrics bounded by cardinality.
apiserver_audit_event_total	counter	[ALPHA] Counter of audit events generated and sent to the audit backend.

Metric Name	Туре	Description
apiserver_audit_requests_rejected_t otal	counter	[ALPHA] Counter of apiserver requests rejected due to an error in the audit logging backend.
apiserver_client_certificate_expira tion_seconds	histogram	[ALPHA] Distribution of the remaining lifetime on the certificate used to authenticate a request.
apiserver_current_inflight_requests	gauge	[ALPHA] Maximal number of currently used inflight requests limit of this apiserver per request kind in the last second.
apiserver_current_inqueue_requests	gauge	[ALPHA] Maximal number of queued requests in this apiserver per request kind in the last second.
apiserver_envelope_encryption_dek_c ache_fill_percent	gauge	[ALPHA] Percent of the cache slots currently occupied by cached data encryption keys (DEK)s.
apiserver_flowcontrol_current_execu ting_requests	gauge	[ALPHA] Number of requests currently executing in the API Priority and Fairness system.
apiserver_flowcontrol_current_inque ue_requests	gauge	[ALPHA] Number of requests currently pending in queues of the API Priority and Fairness system.
apiserver_flowcontrol_dispatched_re quests_total	counter	[ALPHA] Number of requests released by the API Priority and Fairness system for service.
apiserver_flowcontrol_priority_leve l_request_count_samples	histogram	[ALPHA] Periodic observations of the number of requests.
<pre>apiserver_flowcontrol_priority_leve l_request_count_watermarks</pre>	histogram	[ALPHA] Watermarks of the number of requests.

Metric Name	Туре	Description
<pre>apiserver_flowcontrol_read_vs_write _request_count_samples</pre>	histogram	[ALPHA] Periodic observations of the number of requests.
apiserver_flowcontrol_read_vs_write _request_count_watermarks	histogram	[ALPHA] Watermarks of the number of requests.
apiserver_flowcontrol_request_concu rrency_limit	gauge	[ALPHA] Shared concurrency limit in the API Priority and Fairness system.
apiserver_flowcontrol_request_execu tion_seconds	histogram	[ALPHA] Duration of request execution in the API Priority and Fairness system.
apiserver_flowcontrol_request_queue _length_after_enqueue	histogram	[ALPHA] Length of queue in the API Priority and Fairness system, as seen by each request after it is enqueued.
apiserver_flowcontrol_request_wait_ duration_seconds	histogram	[ALPHA] Length of time a request spent waiting in its queue.
apiserver_init_events_total	counter	[ALPHA] Counter of init events processed in watchcache broken by resource type.
apiserver_longrunning_gauge	gauge	[ALPHA] Gauge of all active long- running apiserver requests broken out by verb, group, version, resource, scope and component. Not all requests are tracked this way.
apiserver_registered_watchers	gauge	[ALPHA] Number of currently registered watchers for a given resources.

Metric Name	Туре	Description
apiserver_request_duration_seconds	histogram	[ALPHA] Response latency distribution in seconds for each verb, dry run value, group, version, resource, subresource, scope, and component.
apiserver_request_filter_duration_s econds	histogram	[ALPHA] Request filter latency distribution in seconds, for each filter type.
apiserver_request_total	counter	[ALPHA] Counter of apiserver requests broken out for each verb, dry run value, group, version, resource, scope, component, and HTTP response contentType and code.
apiserver_requested_deprecated_apis	gauge	[ALPHA] Gauge of deprecated APIs that have been requested, broken out by API group, version, resource, subresource, and removed_release.
apiserver_response_sizes	histogram	[ALPHA] Response size distribution in bytes for each group, version, verb, resource, subresource, scope, and component.
apiserver_selfrequest_total	counter	[ALPHA] Counter of apiserver self- requests broken out for each verb, API resource, and subresource.
apiserver_storage_data_key_generati on_duration_seconds	histogram	[ALPHA] Latencies in seconds of DEK generation operations.
apiserver_storage_data_key_generati on_failures_total	counter	[ALPHA] Total number of failed DEK generation operations.

Metric Name	Туре	Description
apiserver_storage_envelope_transfor mation_cache_misses_total	counter	[ALPHA] Total number of cache misses while accessing key decryption key (KDK).
apiserver_tls_handshake_errors_tota l	counter	[ALPHA] Number of requests dropped with 'TLS handshake error from' error.
apiserver_watch_events_sizes	histogram	[ALPHA] Watch event size distribution in bytes.
apiserver_watch_events_total	counter	[ALPHA] Number of events sent in watch clients.
authenticated_user_requests	counter	[ALPHA] Counter of authenticated requests broken out by username.
authentication_attempts	counter	[ALPHA] Counter of authenticated attempts.
authentication_duration_seconds	histogram	[ALPHA] Authentication duration in seconds broken out by result.
<pre>authentication_token_cache_active_f etch_count</pre>	gauge	[ALPHA]
authentication_token_cache_fetch_to tal	counter	[ALPHA]
authentication_token_cache_request_ duration_seconds	histogram	[ALPHA]
authentication_token_cache_request_ total	counter	[ALPHA]

Metric Name	Туре	Description
cadvisor_version_info	gauge	A metric with a constant '1' value labeled by kernel version, OS version, docker version, cadvisor version, and cadvisor revision.
container_cpu_cfs_periods_total	counter	Number of elapsed enforcement period intervals.
container_cpu_cfs_throttled_periods _total	counter	Number of throttled period intervals.
container_cpu_cfs_throttled_seconds _total	counter	Total time duration the container has been throttled.
container_cpu_load_average_10s	gauge	Value of container CPU load average over the last 10 seconds.
<pre>container_cpu_system_seconds_total</pre>	counter	Cumulative system CPU time consumed in seconds.
container_cpu_usage_seconds_total	counter	Cumulative CPU time consumed in seconds.
container_cpu_user_seconds_total	counter	Cumulative user CPU time consumed in seconds.
container_file_descriptors	gauge	Number of open file descriptors for the container.
container_fs_inodes_free	gauge	Number of available Inodes.
container_fs_inodes_total	gauge	Number of Inodes.
container_fs_io_current	gauge	Number of I/Os currently in progress.
<pre>container_fs_io_time_seconds_total</pre>	counter	Cumulative count of seconds spent doing I/Os.

Table 25: Kubernetes Metric List (Continued)

Metric Name	Туре	Description
container_fs_io_time_weighted_secon ds_total	counter	Cumulative weighted I/O time in seconds.
container_fs_limit_bytes	gauge	Number of bytes that the container on this filesystem can consume.
container_fs_read_seconds_total	counter	Cumulative count of seconds spent reading.
container_fs_reads_bytes_total	counter	Cumulative count of bytes read.
container_fs_reads_merged_total	counter	Cumulative count of reads merged.
container_fs_reads_total	counter	Cumulative count of reads completed.
container_fs_sector_reads_total	counter	Cumulative count of sector reads completed.
<pre>container_fs_sector_writes_total</pre>	counter	Cumulative count of sector writes completed.
container_fs_usage_bytes	gauge	Number of bytes that the container on this filesystem can consume.
container_fs_write_seconds_total	counter	Cumulative count of seconds spent writing.
container_fs_writes_bytes_total	counter	Cumulative count of bytes written.
container_fs_writes_merged_total	counter	Cumulative count of writes merged.
container_fs_writes_total	counter	Cumulative count of writes completed.
container_last_seen	gauge	Last time the exporter recognized a container.

Metric Name	Туре	Description
container_memory_cache	gauge	Number of bytes of page cache memory.
container_memory_failcnt	counter	Number of memory usage hit limits.
container_memory_failures_total	counter	Cumulative count of memory allocation failures.
container_memory_mapped_file	gauge	Size of memory mapped files in bytes.
container_memory_max_usage_bytes	gauge	Maximum memory usage recorded in bytes.
container_memory_rss	gauge	Size of RSS in bytes.
container_memory_swap	gauge	Container swap usage in bytes.
container_memory_usage_bytes	gauge	Current memory usage in bytes, including all memory regardless of when it was accessed.
container_memory_working_set_bytes	gauge	Current working set in bytes.
<pre>container_network_receive_bytes_tot al</pre>	counter	Cumulative count of bytes received.
<pre>container_network_receive_errors_to tal</pre>	counter	Cumulative count of errors encountered while receiving.
<pre>container_network_receive_packets_d ropped_total</pre>	counter	Cumulative count of packets dropped while receiving.
<pre>container_network_receive_packets_t otal</pre>	counter	Cumulative count of packets received.

Metric Name	Туре	Description
container_network_transmit_bytes_to tal	counter	Cumulative count of bytes transmitted.
<pre>container_network_transmit_errors_t otal</pre>	counter	Cumulative count of errors encountered while transmitting.
<pre>container_network_transmit_packets_ dropped_total</pre>	counter	Cumulative count of packets dropped while transmitting.
<pre>container_network_transmit_packets_ total</pre>	counter	Cumulative count of packets transmitted.
container_processes	gauge	Number of processes running inside the container.
container_scrape_error	gauge	1 if there was an error while getting container metrics, 0 otherwise.
container_sockets	gauge	Number of open sockets for the container.
container_spec_cpu_period	gauge	CPU period of the container.
container_spec_cpu_quota	gauge	CPU quota of the container.
container_spec_cpu_shares	gauge	CPU share of the container.
container_spec_memory_limit_bytes	gauge	Memory limit for the container.
<pre>container_spec_memory_reservation_l imit_bytes</pre>	gauge	Memory reservation limit for the container.
<pre>container_spec_memory_swap_limit_by tes</pre>	gauge	Memory swap limit for the container.
container_start_time_seconds	gauge	Start time of the container since Unix epoch in seconds.

Metric Name	Туре	Description
container_tasks_state	gauge	Number of tasks in a given state.
container_threads	gauge	Number of threads running inside the container.
container_threads_max	gauge	Maximum number of threads allowed inside the container; infinity if value is zero.
container_ulimits_soft	gauge	Soft ulimit values for the container root process. Unlimited if -1, except priority and nice.
coredns_build_info	gauge	A metric with a constant '1' value labeled by version, revision, and goversion from which CoreDNS was built.
coredns_cache_entries	gauge	The number of elements in the cache.
coredns_cache_hits_total	counter	The count of cache hits.
coredns_cache_misses_total	counter	The count of cache misses.
coredns_dns_request_duration_second s	histogram	Histogram of the time (in seconds) each request took.
coredns_dns_request_size_bytes	histogram	Size of the EDNS0 UDP buffer in bytes (64K for TCP).
coredns_dns_requests_total	counter	Counter of DNS requests made per zone, protocol, and family.
coredns_dns_response_size_bytes	histogram	Size of the returned response in bytes.
coredns_dns_responses_total	counter	Counter of response status codes.

Metric Name	Туре	Description
coredns_forward_healthcheck_failure s_total	counter	Counter of the number of failed healthchecks.
<pre>coredns_forward_max_concurrent_reje cts_total</pre>	counter	Counter of the number of queries rejected because the concurrent queries were at maximum.
<pre>coredns_forward_request_duration_se conds</pre>	histogram	Histogram of the time each request took.
coredns_forward_requests_total	counter	Counter of requests made per upstream.
coredns_forward_responses_total	counter	Counter of requests made per upstream.
coredns_health_request_duration_sec onds	histogram	Histogram of the time (in seconds) each request took.
coredns_panics_total	counter	A metric that counts the number of panics.
coredns_plugin_enabled	gauge	A metric that indicates whether a plugin is enabled on a per-server and zone basis.
etcd_db_total_size_in_bytes	gauge	[ALPHA] Total size of the etcd database file physically allocated in bytes.
etcd_object_counts	gauge	[ALPHA] Number of stored objects at the time of last check, split by kind.
etcd_request_duration_seconds	histogram	[ALPHA] Etcd request latency in seconds for each operation and object type.

Metric Name	Туре	Description
kube_certificatesigningrequest_anno tations	gauge	Kubernetes annotations converted to Prometheus labels.
kube_certificatesigningrequest_cert _length	gauge	Length of the issued certificate.
kube_certificatesigningrequest_cond ition	gauge	The number of each certificatesigningrequest condition.
kube_certificatesigningrequest_crea ted	gauge	Unix creation timestamp.
kube_certificatesigningrequest_labe ls	gauge	Kubernetes labels converted to Prometheus labels.
kube_configmap_annotations	gauge	Kubernetes annotations converted to Prometheus labels.
kube_configmap_created	gauge	Unix creation timestamp.
kube_configmap_info	gauge	Information about configmap.
kube_configmap_labels	gauge	Kubernetes labels converted to Prometheus labels.
kube_configmap_metadata_resource_ve rsion	gauge	Resource version representing a specific version of the configmap.
kube_cronjob_annotations	gauge	Kubernetes annotations converted to Prometheus labels.
kube_cronjob_created	gauge	Unix creation timestamp.
kube_cronjob_info	gauge	Info about cronjob.
kube_cronjob_labels	gauge	Kubernetes labels converted to Prometheus labels.

Metric Name	Туре	Description
kube_cronjob_metadata_resource_vers ion	gauge	Resource version representing a specific version of the cronjob.
kube_cronjob_next_schedule_time	gauge	Next time the cronjob should be scheduled. The time after lastScheduleTime, or after the cron job's creation time if it has never been scheduled. Use this to determine if the job is delayed.
kube_cronjob_spec_failed_job_histor y_limit	gauge	Failed job history limit tells the controller how many failed jobs should be preserved.
kube_cronjob_spec_starting_deadline _seconds	gauge	Deadline in seconds for starting the job if it misses scheduled time for any reason.
<pre>kube_cronjob_spec_successful_job_hi story_limit</pre>	gauge	Successful job history limit tells the controller how many completed jobs should be preserved.
kube_cronjob_spec_suspend	gauge	Suspend flag tells the controller to suspend subsequent executions.
<pre>kube_cronjob_status_active</pre>	gauge	Active holds pointers to currently running jobs.
<pre>kube_cronjob_status_last_schedule_t ime</pre>	gauge	LastScheduleTime keeps information about the last time the job was successfully scheduled.
kube_daemonset_annotations	gauge	Kubernetes annotations converted to Prometheus labels.
kube_daemonset_created	gauge	Unix creation timestamp.
kube_daemonset_labels	gauge	Kubernetes labels converted to Prometheus labels.

Metric Name	Туре	Description
kube_daemonset_metadata_generation	gauge	Sequence number representing a specific generation of the desired state.
kube_daemonset_status_current_numbe r_scheduled	gauge	The number of nodes running at least one daemon pod.
kube_daemonset_status_desired_numbe r_scheduled	gauge	The number of nodes that should be running the daemon pod.
kube_daemonset_status_number_availa ble	gauge	The number of nodes that should be running the daemon pod and have one or more of the daemon pods running and available.
kube_daemonset_status_number_missch eduled	gauge	The number of nodes running a daemon pod that should not be running a daemon pod.
kube_daemonset_status_number_ready	gauge	The number of nodes that should be running the daemon pod and have one or more of the daemon pods running and ready.
kube_daemonset_status_number_unavai lable	gauge	The number of nodes that should be running the daemon pod but have none of the daemon pods running and available.
kube_daemonset_status_observed_gene ration	gauge	The most recent generation observed by the daemon set controller.
<pre>kube_daemonset_status_updated_numbe r_scheduled</pre>	gauge	The total number of nodes that are running an updated daemon pod.
kube_deployment_annotations	gauge	Kubernetes annotations converted to Prometheus labels.

Metric Name	Туре	Description
kube_deployment_created	gauge	Unix creation timestamp.
kube_deployment_labels	gauge	Kubernetes labels converted to Prometheus labels.
kube_deployment_metadata_generation	gauge	Sequence number representing a specific generation of the desired state.
kube_deployment_spec_paused	gauge	Whether the deployment is paused and will not be processed by the deployment controller.
<pre>kube_deployment_spec_replicas</pre>	gauge	Number of desired pods for a deployment.
kube_deployment_spec_strategy_rolli ngupdate_max_surge	gauge	Maximum number of replicas that can be scheduled above the desired number of replicas during a rolling update of a deployment.
kube_deployment_spec_strategy_rolli ngupdate_max_unavailable	gauge	Maximum number of unavailable replicas during a rolling update of a deployment.
kube_deployment_status_condition	gauge	The current status conditions of a deployment.
kube_deployment_status_observed_gen eration	gauge	The generation observed by the deployment controller.
kube_deployment_status_replicas	gauge	The number of replicas per deployment.
<pre>kube_deployment_status_replicas_ava ilable</pre>	gauge	The number of available replicas per deployment.

Metric Name	Туре	Description
kube_deployment_status_replicas_rea dy	gauge	The number of ready replicas per deployment.
kube_deployment_status_replicas_una vailable	gauge	The number of unavailable replicas per deployment.
kube_deployment_status_replicas_upd ated	gauge	The number of updated replicas per deployment.
kube_endpoint_address_available	gauge	Number of addresses available in the endpoint.
kube_endpoint_address_not_ready	gauge	Number of addresses not ready in the endpoint.
kube_endpoint_annotations	gauge	Kubernetes annotations converted to Prometheus labels.
kube_endpoint_created	gauge	Unix creation timestamp.
kube_endpoint_info	gauge	Information about the endpoint.
kube_endpoint_labels	gauge	Kubernetes labels converted to Prometheus labels.
kube_endpoint_ports	gauge	Information about the endpoint ports.
kube_horizontalpodautoscaler_annota tions	gauge	Kubernetes annotations converted to Prometheus labels.
kube_horizontalpodautoscaler_info	gauge	Information about this autoscaler.
kube_horizontalpodautoscaler_labels	gauge	Kubernetes labels converted to Prometheus labels.

Metric Name	Туре	Description
kube_horizontalpodautoscaler_metada ta_generation	gauge	The generation observed by the HorizontalPodAutoscaler controller.
kube_horizontalpodautoscaler_spec_m ax_replicas	gauge	Upper limit for the number of pods that is set by the autoscaler; cannot be smaller number than MinReplicas.
kube_horizontalpodautoscaler_spec_m in_replicas	gauge	Lower limit for the number of pods that is set by the autoscaler, default 1.
kube_horizontalpodautoscaler_spec_t arget_metric	gauge	The metric specifications used by this autoscaler when calculating the desired replica count.
kube_horizontalpodautoscaler_status _condition	gauge	The condition of this autoscaler.
kube_horizontalpodautoscaler_status _current_replicas	gauge	Current number of replicas of pods managed by this autoscaler.
kube_horizontalpodautoscaler_status _desired_replicas	gauge	Desired number of replicas of pods managed by this autoscaler.
kube_ingress_annotations	gauge	Kubernetes annotations converted to Prometheus labels.
kube_ingress_created	gauge	Unix creation timestamp.
kube_ingress_info	gauge	Information about ingress.
kube_ingress_labels	gauge	Kubernetes labels converted to Prometheus labels.
kube_ingress_metadata_resource_vers ion	gauge	Resource version representing a specific version of ingress.

Metric Name	Туре	Description
kube_ingress_path	gauge	Ingress host, paths, and backend service information.
kube_ingress_tls	gauge	Ingress TLS host and secret information.
kube_job_annotations	gauge	Kubernetes annotations converted to Prometheus labels.
kube_job_complete	gauge	The job has completed its execution.
kube_job_created	gauge	Unix creation timestamp.
kube_job_failed	gauge	The job has failed its execution.
kube_job_info	gauge	Information about the job.
kube_job_labels	gauge	Kubernetes labels converted to Prometheus labels.
kube_job_owner	gauge	Information about the job's owner.
<pre>kube_job_spec_active_deadline_secon ds</pre>	gauge	How long (in seconds) the job can be active after the startTime before the system tries to terminate it.
<pre>kube_job_spec_completions</pre>	gauge	The desired number of successfully finished pods the job should be run with.
<pre>kube_job_spec_parallelism</pre>	gauge	The maximum desired number of pods the job should run at any given time.
kube_job_status_active	gauge	The number of actively running pods.

Metric Name	Туре	Description
<pre>kube_job_status_completion_time</pre>	gauge	The completionTime represents time when the job was completed.
kube_job_status_failed	gauge	The number of pods that reached Phase Failed, and the reason for failure.
kube_job_status_start_time	gauge	The startTime represents thetime when the job was acknowledged by the Job Manager.
<pre>kube_job_status_succeeded</pre>	gauge	The number of pods that reached Phase Succeeded.
kube_limitrange	gauge	Information about limit range.
kube_limitrange_created	gauge	Unix creation timestamp.
kube_mutatingwebhookconfiguration_c reated	gauge	Unix creation timestamp.
kube_mutatingwebhookconfiguration_i nfo	gauge	Information about the MutatingWebhookConfiguration.
kube_mutatingwebhookconfiguration_m etadata_resource_version	gauge	Resource version representing a specific version of the MutatingWebhookConfiguration.
<pre>kube_namespace_annotations</pre>	gauge	Kubernetes annotations converted to Prometheus labels.
kube_namespace_created	gauge	Unix creation timestamp.
kube_namespace_labels	gauge	Kubernetes labels converted to Prometheus labels.
kube_namespace_status_condition	gauge	The condition of a namespace.

Metric Name	Туре	Description
<pre>kube_namespace_status_phase</pre>	gauge	Kubernetes namespace status phase.
kube_networkpolicy_annotations	gauge	Kubernetes annotations converted to Prometheus labels.
kube_networkpolicy_created	gauge	Unix creation timestamp of a network policy.
kube_networkpolicy_labels	gauge	Kubernetes labels converted to Prometheus labels.
<pre>kube_networkpolicy_spec_egress_rule s</pre>	gauge	Number of egress rules on the networkpolicy.
<pre>kube_networkpolicy_spec_ingress_rul es</pre>	gauge	Number of ingress rules on the networkpolicy.
kube_node_annotations	gauge	Kubernetes annotations converted to Prometheus labels.
kube_node_created	gauge	Unix creation timestamp.
kube_node_info	gauge	Information about a cluster node.
kube_node_labels	gauge	Kubernetes labels converted to Prometheus labels.
kube_node_role	gauge	The role of a cluster node.
kube_node_spec_taint	gauge	The taint of a cluster node.
kube_node_spec_unschedulable	gauge	Whether a node can schedule new pods.
kube_node_status_allocatable	gauge	The allocatable for different resources of a node that are available for scheduling.

Metric Name	Туре	Description
kube_node_status_capacity	gauge	The capacity for different resources of a node.
kube_node_status_condition	gauge	The condition of a cluster node.
kube_persistentvolume_annotations	gauge	Kubernetes annotations converted to Prometheus labels.
<pre>kube_persistentvolume_capacity_byte s</pre>	gauge	Persistentvolume capacity in bytes.
<pre>kube_persistentvolume_claim_ref</pre>	gauge	Information about the Persistent Volume Claim Reference.
kube_persistentvolume_info	gauge	Information about persistentvolume.
kube_persistentvolume_labels	gauge	Kubernetes labels converted to Prometheus labels.
kube_persistentvolume_status_phase	gauge	The phase indicates if a volume is available, bound to a claim, or released by a claim.
kube_persistentvolumeclaim_access_m ode	gauge	The access mode(s) specified by the persistent volume claim.
<pre>kube_persistentvolumeclaim_annotati ons</pre>	gauge	Kubernetes annotations converted to Prometheus labels.
kube_persistentvolumeclaim_info	gauge	Information about persistent volume claim.
kube_persistentvolumeclaim_labels	gauge	Kubernetes labels converted to Prometheus labels.
<pre>kube_persistentvolumeclaim_resource _requests_storage_bytes</pre>	gauge	The capacity of storage requested by the persistent volume claim.

Metric Name	Туре	Description
kube_persistentvolumeclaim_status_c ondition	gauge	Information about status of different conditions of persistent volume claim.
kube_persistentvolumeclaim_status_p hase	gauge	The phase the persistent volume claim is currently in.
kube_pod_annotations	gauge	Kubernetes annotations converted to Prometheus labels.
kube_pod_completion_time	gauge	Completion time in Unix timestamp for a pod.
kube_pod_container_info	gauge	Information about a container in a pod.
<pre>kube_pod_container_resource_limits</pre>	gauge	The number of resource limits requested by a container.
<pre>kube_pod_container_resource_request s</pre>	gauge	The number of resources requested by a container.
<pre>kube_pod_container_state_started</pre>	gauge	Start time in Unix timestamp for a pod container.
<pre>kube_pod_container_status_last_term inated_reason</pre>	gauge	Describes the last reason the container was in a terminated state.
kube_pod_container_status_ready	gauge	Describes whether the container's readiness check succeeded.
<pre>kube_pod_container_status_restarts_ total</pre>	counter	The number of restarts per container.
kube_pod_container_status_running	gauge	Describes whether the container is currently in running state.

Metric Name	Туре	Description
<pre>kube_pod_container_status_terminate d</pre>	gauge	Describes whether the container is currently in a terminated state.
<pre>kube_pod_container_status_terminate d_reason</pre>	gauge	Describes the reason the container is currently in a terminated state.
<pre>kube_pod_container_status_waiting</pre>	gauge	Describes whether the container is currently in a waiting state.
<pre>kube_pod_container_status_waiting_r eason</pre>	gauge	Describes the reason the container is currently in a waiting state.
kube_pod_created	gauge	Unix creation timestamp.
kube_pod_deletion_timestamp	gauge	Unix deletion timestamp.
kube_pod_info	gauge	Information about the pod.
<pre>kube_pod_init_container_info</pre>	gauge	Information about an init container in a pod.
<pre>kube_pod_init_container_resource_li mits</pre>	gauge	The number of requested resource limits by an init container.
<pre>kube_pod_init_container_resource_re quests</pre>	gauge	The number of resource requests by an init container.
<pre>kube_pod_init_container_status_last _terminated_reason</pre>	gauge	Describes the last reason the init container was in a terminated state.
<pre>kube_pod_init_container_status_read y</pre>	gauge	Describes whether the init container's readiness check succeeded.
<pre>kube_pod_init_container_status_rest arts_total</pre>	counter	The number of restarts for the init container.

Metric Name	Туре	Description
<pre>kube_pod_init_container_status_runn ing</pre>	gauge	Describes whether the init container is currently in a running state.
<pre>kube_pod_init_container_status_term inated</pre>	gauge	Describes whether the init container is currently in a terminated state.
<pre>kube_pod_init_container_status_term inated_reason</pre>	gauge	Describes the last reason the init container was in a terminated state.
kube_pod_init_container_status_read y	gauge	Describes whether the init container's readiness check succeeded.
<pre>kube_pod_init_container_status_rest arts_total</pre>	counter	The number of restarts for the init container.
<pre>kube_pod_init_container_status_runn ing</pre>	gauge	Describes whether the init container is currently in a running state.
<pre>kube_pod_init_container_status_term inated</pre>	gauge	Describes whether the init container is currently in a terminated state.
<pre>kube_pod_init_container_status_term inated_reason</pre>	gauge	Describes the reason the init container is currently in a terminated state.
<pre>kube_pod_init_container_status_wait ing</pre>	gauge	Describes whether the init container is currently in a waiting state.
<pre>kube_pod_init_container_status_wait ing_reason</pre>	gauge	Describes the reason the init container is currently in a waiting state.

Metric Name	Туре	Description
kube_pod_labels	gauge	Kubernetes labels converted to Prometheus labels.
kube_pod_overhead_cpu_cores	gauge	The pod overhead in regard to CPU cores associated with running a pod.
<pre>kube_pod_overhead_memory_bytes</pre>	gauge	The pod overhead in regard to memory associated with running a pod.
kube_pod_owner	gauge	Information about the pod's owner.
kube_pod_restart_policy	gauge	Describes the restart policy in use by this pod.
<pre>kube_pod_runtimeclass_name_info</pre>	gauge	The runtimeclass associated with the pod.
<pre>kube_pod_spec_volumes_persistentvol umeclaims_info</pre>	gauge	Information about persistentvolumeclaim volumes in a pod.
<pre>kube_pod_spec_volumes_persistentvol umeclaims_readonly</pre>	gauge	Describes whether a persistentvolumeclaim is mounted as read only.
<pre>kube_pod_start_time</pre>	gauge	Start time in the Unix timestamp for a pod.
kube_pod_status_phase	gauge	The pod's current phase.
kube_pod_status_ready	gauge	Describes whether the pod is ready to serve requests.
kube_pod_status_reason	gauge	The pod status reasons.

Metric Name	Туре	Description
<pre>kube_pod_status_scheduled</pre>	gauge	Describes the status of the scheduling process for the pod.
<pre>kube_pod_status_scheduled_time</pre>	gauge	Unix timestamp when a pod moved into scheduled status.
<pre>kube_pod_status_unschedulable</pre>	gauge	Describes the unschedulable status for the pod.
<pre>kube_poddisruptionbudget_annotation s</pre>	gauge	Kubernetes annotations converted to Prometheus labels.
kube_poddisruptionbudget_created	gauge	Unix creation timestamp.
kube_poddisruptionbudget_labels	gauge	Kubernetes labels converted to Prometheus labels.
<pre>kube_poddisruptionbudget_status_cur rent_healthy</pre>	gauge	Current number of healthy pods.
<pre>kube_poddisruptionbudget_status_des ired_healthy</pre>	gauge	Minimum desired number of healthy pods.
<pre>kube_poddisruptionbudget_status_exp ected_pods</pre>	gauge	Total number of pods counted by this disruption budget.
<pre>kube_poddisruptionbudget_status_obs erved_generation</pre>	gauge	Most recent generation observed when updating this disruption budget status.
<pre>kube_poddisruptionbudget_status_pod _disruptions_allowed</pre>	gauge	Number of pod disruptions that are currently allowed.
kube_replicaset_annotations	gauge	Kubernetes annotations converted to Prometheus labels.
kube_replicaset_created	gauge	Unix creation timestamp.

Metric Name	Туре	Description
kube_replicaset_labels	gauge	Kubernetes labels converted to Prometheus labels.
kube_replicaset_metadata_generation	gauge	Sequence number representing a specific generation of the desired state.
kube_replicaset_owner	gauge	Information about the ReplicaSet's owner.
<pre>kube_replicaset_spec_replicas</pre>	gauge	Number of desired pods for a ReplicaSet.
kube_replicaset_status_fully_labele d_replicas	gauge	The number of fully labeled replicas per ReplicaSet.
kube_replicaset_status_observed_gen eration	gauge	The generation observed by the ReplicaSet controller.
<pre>kube_replicaset_status_ready_replic as</pre>	gauge	The number of ready replicas per ReplicaSet.
<pre>kube_replicaset_status_replicas</pre>	gauge	The number of replicas per ReplicaSet.
kube_replicationcontroller_created	gauge	Unix creation timestamp.
kube_replicationcontroller_metadata _generation	gauge	Sequence number representing a specific generation of the desired state.
kube_replicationcontroller_owner	gauge	Information about the ReplicationController's owner.
<pre>kube_replicationcontroller_spec_rep licas</pre>	gauge	Number of desired pods for a ReplicationController.

Metric Name	Туре	Description
kube_replicationcontroller_status_a vailable_replicas	gauge	The number of available replicas per ReplicationController.
<pre>kube_replicationcontroller_status_f ully_labeled_replicas</pre>	gauge	The number of fully labeled replicas per ReplicationController.
kube_replicationcontroller_status_o bserved_generation	gauge	The generation observed by the ReplicationController controller.
<pre>kube_replicationcontroller_status_r eady_replicas</pre>	gauge	The number of ready replicas per ReplicationController.
<pre>kube_replicationcontroller_status_r eplicas</pre>	gauge	The number of replicas per ReplicationController.
kube_resourcequota	gauge	Information about resource quota.
kube_resourcequota_created	gauge	Unix creation timestamp.
kube_secret_annotations	gauge	Kubernetes annotations converted to Prometheus labels.
kube_secret_created	gauge	Unix creation timestamp.
kube_secret_info	gauge	Information about secret.
kube_secret_labels	gauge	Kubernetes labels converted to Prometheus labels.
<pre>kube_secret_metadata_resource_versi on</pre>	gauge	Resource version representing a specific version of secret.
kube_secret_type	gauge	Type about secret.
kube_service_annotations	gauge	Kubernetes annotations converted to Prometheus labels.

Metric Name	Туре	Description
kube_service_created	gauge	Unix creation timestamp.
kube_service_info	gauge	Information about service.
kube_service_labels	gauge	Kubernetes labels converted to Prometheus labels.
kube_service_spec_external_ip	gauge	One series for each service external IP.
kube_service_spec_type	gauge	Specifies the service type.
<pre>kube_service_status_load_balancer_i ngress</pre>	gauge	Service load balancer ingress status.
kube_statefulset_annotations	gauge	Kubernetes annotations converted to Prometheus labels.
kube_statefulset_created	gauge	Unix creation timestamp.
<pre>kube_statefulset_labels</pre>	gauge	Kubernetes labels converted to Prometheus labels.
kube_statefulset_metadata_generatio n	gauge	Sequence number representing a specific generation of the desired state for the StatefulSet.
kube_statefulset_replicas	gauge	Number of desired pods for a StatefulSet.
kube_statefulset_status_current_rev ision	gauge	Indicates the version of the StatefulSet used to generate pods in the sequence (0,currentReplicas).
kube_statefulset_status_observed_ge neration	gauge	The generation observed by the StatefulSet controller.

Metric Name	Туре	Description
kube_statefulset_status_replicas	gauge	The number of replicas per StatefulSet.
kube_statefulset_status_replicas_av ailable	gauge	The number of available replicas per StatefulSet.
<pre>kube_statefulset_status_replicas_cu rrent</pre>	gauge	The number of current replicas per StatefulSet.
<pre>kube_statefulset_status_replicas_re ady</pre>	gauge	The number of ready replicas per StatefulSet.
<pre>kube_statefulset_status_replicas_up dated</pre>	gauge	The number of updated replicas per StatefulSet.
kube_statefulset_status_update_revi sion	gauge	Indicates the version of the StatefulSet used to generate pods in the sequence (replicas- updatedReplicas,replicas).
kube_storageclass_annotations	gauge	Kubernetes annotations converted to Prometheus labels.
kube_storageclass_created	gauge	Unix creation timestamp.
kube_storageclass_info	gauge	Information about storageclass.
kube_storageclass_labels	gauge	Kubernetes labels converted to Prometheus labels.
<pre>kube_validatingwebhookconfiguration _created</pre>	gauge	Unix creation timestamp.
<pre>kube_validatingwebhookconfiguration _info</pre>	gauge	Information about the ValidatingWebhookConfiguration.

Metric Name	Туре	Description
kube_validatingwebhookconfiguration _metadata_resource_version	gauge	Resource version representing a specific version of the ValidatingWebhookConfiguration.
kube_volumeattachment_created	gauge	Unix creation timestamp.
kube_volumeattachment_info	gauge	Information about volumeattachment.
kube_volumeattachment_labels	gauge	Kubernetes labels converted to Prometheus labels.
<pre>kube_volumeattachment_spec_source_p ersistentvolume</pre>	gauge	PersistentVolume source reference.
kube_volumeattachment_status_attach ed	gauge	Information about volumeattachment.
kube_volumeattachment_status_attach ment_metadata	gauge	The volumeattachment metadata.
<pre>kubelet_certificate_manager_client_ expiration_renew_errors</pre>	counter	[ALPHA] Counter of certificate renewal errors.
kubelet_certificate_manager_client_ ttl_seconds	gauge	[ALPHA] Gauge of the time-to-live (TTL) of the Kubelet's client certificate. The value is in seconds until certificate expiry (negative if already expired). If the client certificate is invalid or unused, the value will be +INF.
kubelet_cgroup_manager_duration_sec onds	histogram	[ALPHA] Duration in seconds for cgroup manager operations. Broken down by method.
<pre>kubelet_container_log_filesystem_us ed_bytes</pre>	gauge	[ALPHA] Bytes used by the container's logs on the filesystem.

Metric Name	Туре	Description
<pre>kubelet_containers_per_pod_count</pre>	histogram	[ALPHA] The number of containers per pod.
kubelet_docker_operations_duration_ seconds	histogram	[ALPHA] Latency in seconds of Docker operations. Broken down by operation type.
<pre>kubelet_docker_operations_errors_to tal</pre>	counter	[ALPHA] Cumulative number of Docker operation errors by operation type.
kubelet_docker_operations_total	counter	[ALPHA] Cumulative number of Docker operations by operation type.
kubelet_http_inflight_requests	gauge	[ALPHA] Number of the inflight http requests.
<pre>kubelet_http_requests_duration_seco nds</pre>	histogram	[ALPHA] Duration in seconds to serve http requests.
<pre>kubelet_http_requests_total</pre>	counter	[ALPHA] Number of the http requests received since the server started.
kubelet_network_plugin_operations_d uration_seconds	histogram	[ALPHA] Latency in seconds of network plugin operations, broken down by operation type.
kubelet_network_plugin_operations_t otal	counter	[ALPHA] Cumulative number of network plugin operations by operation type.
kubelet_node_config_error	gauge	[ALPHA] This metric is true (1) if the node is experiencing a configuration-related error, false (0) otherwise.

Metric Name	Туре	Description
kubelet_node_name	gauge	[ALPHA] The node's name. The count is always 1.
kubelet_pleg_discard_events	counter	[ALPHA] The number of discard events in PLEG.
<pre>kubelet_pleg_last_seen_seconds</pre>	gauge	[ALPHA] Timestamp in seconds when PLEG was last seen active.
kubelet_pleg_relist_duration_second s	histogram	[ALPHA] Duration in seconds for relisting pods in PLEG.
<pre>kubelet_pleg_relist_interval_second s</pre>	histogram	[ALPHA] Interval in seconds between relisting in PLEG.
kubelet_pod_start_duration_seconds	histogram	[ALPHA] Duration in seconds for a single pod to go from pending to running.
kubelet_pod_worker_duration_seconds	histogram	[ALPHA] Duration in seconds to sync a single pod. Broken down by operation type: create, update, or sync.
<pre>kubelet_pod_worker_start_duration_s econds</pre>	histogram	[ALPHA] Duration in seconds from seeing a pod to starting a worker.
<pre>kubelet_run_podsandbox_duration_sec onds</pre>	histogram	[ALPHA] Duration in seconds of the run_podsandbox operations. Broken down by RuntimeClass.Handler.
kubelet_running_containers	gauge	[ALPHA] Number of containers currently running.
kubelet_running_pods	gauge	[ALPHA] Number of pods currently running.

Metric Name	Туре	Description
kubelet_runtime_operations_duration _seconds	histogram	[ALPHA] Duration in seconds of runtime operations. Broken down by operation type.
<pre>kubelet_runtime_operations_errors_t otal</pre>	counter	[ALPHA] Cumulative number of runtime operation errors by operation type.
<pre>kubelet_runtime_operations_total</pre>	counter	[ALPHA] Cumulative number of runtime operations by operation type.
<pre>kubelet_volume_stats_available_byte s</pre>	gauge	[ALPHA] Number of available bytes in the volume.
<pre>kubelet_volume_stats_capacity_bytes</pre>	gauge	[ALPHA] Capacity in bytes of the volume.
<pre>kubelet_volume_stats_inodes</pre>	gauge	[ALPHA] Maximum number of inodes in the volume.
<pre>kubelet_volume_stats_inodes_free</pre>	gauge	[ALPHA] Number of free inodes in the volume.
<pre>kubelet_volume_stats_inodes_used</pre>	gauge	[ALPHA] Number of used inodes in the volume.
<pre>kubelet_volume_stats_used_bytes</pre>	gauge	[ALPHA] Number of used bytes in the volume.
<pre>kubeproxy_network_programming_durat ion_seconds</pre>	histogram	[ALPHA] In Cluster Network Programming Latency in seconds.
<pre>kubeproxy_sync_proxy_rules_duration _seconds</pre>	histogram	[ALPHA] SyncProxyRules latency in seconds.
<pre>kubeproxy_sync_proxy_rules_endpoint _changes_pending</pre>	gauge	[ALPHA] Pending proxy rules Endpoint changes.

Metric Name	Туре	Description
kubeproxy_sync_proxy_rules_endpoint _changes_total	counter	[ALPHA] Cumulative proxy rules Endpoint changes.
<pre>kubeproxy_sync_proxy_rules_iptables _restore_failures_total</pre>	counter	[ALPHA] Cumulative proxy iptables restore failures.
<pre>kubeproxy_sync_proxy_rules_last_que ued_timestamp_seconds</pre>	gauge	[ALPHA] The last time a sync of proxy rules was queued.
<pre>kubeproxy_sync_proxy_rules_last_tim estamp_seconds</pre>	gauge	[ALPHA] The last time proxy rules were successfully synced.
<pre>kubeproxy_sync_proxy_rules_service_ changes_pending</pre>	gauge	[ALPHA] Pending proxy rules Service changes.
<pre>kubeproxy_sync_proxy_rules_service_ changes_total</pre>	counter	[ALPHA] Cumulative proxy rules Service changes.
kubernetes_build_info	gauge	[ALPHA] A metric with a constant '1' value labeled by major, minor, git version, git commit, git tree state, build date, Go version, and compiler from which Kubernetes was built, and platform on which it is running.
prober_probe_total	counter	[ALPHA] Cumulative number of a liveness, readiness, or startup probe for a container by result.
process_cpu_seconds_total	counter	Total user and system CPU time spent in seconds.
process_max_fds	gauge	Maximum number of open file descriptors.
process_open_fds	gauge	Number of open file descriptors.

Metric Name	Туре	Description
process_resident_memory_bytes	gauge	Resident memory size in bytes.
<pre>process_start_time_seconds</pre>	gauge	Start time of the process since Unix epoch in seconds.
process_virtual_memory_bytes	gauge	Virtual memory size in bytes.
process_virtual_memory_max_bytes	gauge	Maximum amount of virtual memory available in bytes.
rest_client_exec_plugin_certificate _rotation_age	histogram	[ALPHA] Histogram of the number of seconds the last auth exec plugin client certificate lived before being rotated. If auth exec plugin client certificates are unused, histogram will contain no data.
rest_client_exec_plugin_ttl_seconds	gauge	[ALPHA] Gauge of the shortest TTL of the client certificate or certificates managed by the auth exec plugin. The value is in seconds until certificate expiry (negative if already expired). If auth exec plugins are unused or manage no TLS certificates, the value will be +INF.
rest_client_request_duration_second s	histogram	[ALPHA] Request latency in seconds. Broken down by verb and URL.
rest_client_requests_total	counter	[ALPHA] Number of HTTP requests, partitioned by status code, method, and host.
<pre>serviceaccount_legacy_tokens_total</pre>	counter	[ALPHA] Cumulative legacy service account tokens used.

Metric Name	Туре	Description
<pre>serviceaccount_stale_tokens_total</pre>	counter	[ALPHA] Cumulative stale projected service account tokens used.
<pre>serviceaccount_valid_tokens_total</pre>	counter	[ALPHA] Cumulative valid projected service account tokens used.
<pre>ssh_tunnel_open_count</pre>	counter	[ALPHA] Counter of ssh tunnel total open attempts.
<pre>ssh_tunnel_open_fail_count</pre>	counter	[ALPHA] Counter of ssh tunnel failed open attempts.
storage_operation_duration_seconds	histogram	[ALPHA] Storage operation duration.
storage_operation_errors_total	counter	[ALPHA] Storage operation errors.
<pre>storage_operation_status_count</pre>	counter	[ALPHA] Storage operation return statuses count.
volume_manager_total_volumes	gauge	[ALPHA] Number of volumes in Volume Manager.
workqueue_adds_total	counter	[ALPHA] Total number of adds handled by workqueue.
workqueue_depth	gauge	[ALPHA] Current depth of workqueue.
workqueue_longest_running_processor _seconds	gauge	[ALPHA] Number of seconds the longest-running processor for the workqueue has been running.
workqueue_queue_duration_seconds	histogram	[ALPHA] How long in seconds an item stays in the workqueue before being requested.

Table 25: Kubernetes	Metric List	(Continued)
-----------------------------	--------------------	-------------

Metric Name	Туре	Description
workqueue_retries_total	counter	[ALPHA] Total number of retries handled by the workqueue.
workqueue_unfinished_work_seconds	gauge	[ALPHA] Number of seconds of work that have been done but haven't been observed by work_duration. Large values indicate stuck threads. You can deduce the number of stuck threads by observing the rate at which this value increases.
workqueue_work_duration_seconds	histogram	[ALPHA] How long in seconds it takes to process an item from the workqueue.

RELATED DOCUMENTATION

Contrail Networking Analytics | 338Contrail Networking Metric List | 344Cluster Node Metric List | 396

Contrail Networking Alert List | 414

Cluster Node Metric List

Metric Name	Туре	Description
<pre>node_arp_entries</pre>	gauge	ARP entries by device.

Metric Name	Туре	Description
node_authorizer_graph_actions_durat ion_seconds	histogram	[ALPHA] Histogram of duration of graph actions in node authorizer.
node_boot_time_seconds	gauge	Node boot time, in Unix time.
node_context_switches_total	counter	Total number of context switches.
node_cooling_device_cur_state	gauge	Current throttle state of the cooling device.
node_cooling_device_max_state	gauge	Maximum throttle state of the cooling device.
node_cpu_guest_seconds_total	counter	Seconds the CPUs spent in guests (VMs) for each mode.
node_cpu_seconds_total	counter	Seconds the CPUs spent in each mode.
node_disk_info	gauge	info of /sys/block/ <block_device>.</block_device>
node_disk_io_now	gauge	The number of I/Os currently in progress.
node_disk_io_time_seconds_total	counter	Total seconds spent doing I/Os.
<pre>node_disk_io_time_weighted_seconds_ total</pre>	counter	The weighted number of seconds spent doing I/Os.
node_disk_read_bytes_total	counter	The total number of bytes read successfully.
<pre>node_disk_read_time_seconds_total</pre>	counter	The total number of seconds spent by all reads.
<pre>node_disk_reads_completed_total</pre>	counter	The total number of reads completed successfully.

Metric Name	Туре	Description
<pre>node_disk_reads_merged_total</pre>	counter	The total number of reads merged.
<pre>node_disk_write_time_seconds_total</pre>	counter	The total number of seconds spent by all writes.
<pre>node_disk_writes_completed_total</pre>	counter	The total number of writes completed successfully.
<pre>node_disk_writes_merged_total</pre>	counter	The number of writes merged.
node_disk_written_bytes_total	counter	The total number of bytes written successfully.
node_dmi_info	gauge	A metric with a constant '1' value labeled by bios_date, bios_release, bios_vendor, bios_version, board_asset_tag, board_name, board_serial, board_vendor, board_version, chassis_asset_tag, chassis_serial, chassis_vendor, chassis_version, product_family, product_name, product_serial, product_sku, product_uuid, product_version, and system_vendor if provided by DMI.
<pre>node_entropy_available_bits</pre>	gauge	Bits of available entropy.
<pre>node_entropy_pool_size_bits</pre>	gauge	Bits of entropy pool.
node_exporter_build_info	gauge	A metric with a constant '1' value labeled by version, revision, branch, and goversion from which node_exporter was built.
<pre>node_filefd_allocated</pre>	gauge	File descriptor statistics: allocated.
node_filefd_maximum	gauge	File descriptor statistics: maximum.

Metric Name	Туре	Description
<pre>node_filesystem_avail_bytes</pre>	gauge	Filesystem space available to non- root users in bytes.
node_filesystem_device_error	gauge	Whether an error occurred while getting statistics for the given device.
node_filesystem_files	gauge	Filesystem total file nodes.
<pre>node_filesystem_files_free</pre>	gauge	Filesystem total free file nodes.
<pre>node_filesystem_free_bytes</pre>	gauge	Filesystem free space in bytes.
node_filesystem_readonly	gauge	Filesystem read-only status.
node_filesystem_size_bytes	gauge	Filesystem size in bytes.
node_forks_total	counter	Total number of forks.
node_intr_total	counter	Total number of interrupts serviced.
node_ipvs_connections_total	counter	The total number of connections made.
<pre>node_ipvs_incoming_bytes_total</pre>	counter	The total amount of incoming data.
<pre>node_ipvs_incoming_packets_total</pre>	counter	The total number of incoming packets.
node_ipvs_outgoing_bytes_total	counter	The total amount of outgoing data.
node_ipvs_outgoing_packets_total	counter	The total number of outgoing packets.
node_load1	gauge	1m load average.
node_load15	gauge	15m load average.

Metric Name	Туре	Description
node_load5	gauge	5m load average.
<pre>node_memory_Active_anon_bytes</pre>	gauge	Memory information field Active_anon_bytes.
<pre>node_memory_Active_bytes</pre>	gauge	Memory information field Active_bytes.
<pre>node_memory_Active_file_bytes</pre>	gauge	Memory information field Active_file_bytes.
node_memory_AnonHugePages_bytes	gauge	Memory information field AnonHugePages_bytes.
node_memory_AnonPages_bytes	gauge	Memory information field AnonPages_bytes.
<pre>node_memory_Bounce_bytes</pre>	gauge	Memory information field Bounce_bytes.
<pre>node_memory_Buffers_bytes</pre>	gauge	Memory information field Buffers_bytes.
node_memory_Cached_bytes	gauge	Memory information field Cached_bytes.
node_memory_CmaFree_bytes	gauge	Memory information field CmaFree_bytes.
<pre>node_memory_CmaTotal_bytes</pre>	gauge	Memory information field CmaTotal_bytes.
<pre>node_memory_CommitLimit_bytes</pre>	gauge	Memory information field CommitLimit_bytes.
<pre>node_memory_Committed_AS_bytes</pre>	gauge	Memory information field Committed_AS_bytes.

Metric Name	Туре	Description
node_memory_DirectMap2M_bytes	gauge	Memory information field DirectMap2M_bytes.
<pre>node_memory_DirectMap4k_bytes</pre>	gauge	Memory information field DirectMap4k_bytes.
node_memory_Dirty_bytes	gauge	Memory information field Dirty_bytes.
<pre>node_memory_HardwareCorrupted_bytes</pre>	gauge	Memory information field HardwareCorrupted_bytes.
node_memory_HugePages_Free	gauge	Memory information field HugePages_Free.
node_memory_HugePages_Rsvd	gauge	Memory information field HugePages_Rsvd.
node_memory_HugePages_Surp	gauge	Memory information field HugePages_Surp.
node_memory_HugePages_Total	gauge	Memory information field HugePages_Total.
node_memory_Hugepagesize_bytes	gauge	Memory information field Hugepagesize_bytes.
<pre>node_memory_Inactive_anon_bytes</pre>	gauge	Memory information field Inactive_anon_bytes.
node_memory_Inactive_bytes	gauge	Memory information field Inactive_bytes.
<pre>node_memory_Inactive_file_bytes</pre>	gauge	Memory information field Inactive_file_bytes.
<pre>node_memory_KernelStack_bytes</pre>	gauge	Memory information field KernelStack_bytes.

Table 26: Cloud-Native Contrail Networking (CN2) Cluster Node Metric List (Continued)

Metric Name	Туре	Description
<pre>node_memory_Mapped_bytes</pre>	gauge	Memory information field Mapped_bytes.
<pre>node_memory_MemAvailable_bytes</pre>	gauge	Memory information field MemAvailable_bytes.
<pre>node_memory_MemFree_bytes</pre>	gauge	Memory information field MemFree_bytes.
<pre>node_memory_MemTotal_bytes</pre>	gauge	Memory information field MemTotal_bytes.
node_memory_Mlocked_bytes	gauge	Memory information field Mlocked_bytes.
<pre>node_memory_NFS_Unstable_bytes</pre>	gauge	Memory information field NFS_Unstable_bytes.
<pre>node_memory_PageTables_bytes</pre>	gauge	Memory information field PageTables_bytes.
<pre>node_memory_SReclaimable_bytes</pre>	gauge	Memory information field SReclaimable_bytes.
<pre>node_memory_SUnreclaim_bytes</pre>	gauge	Memory information field SUnreclaim_bytes.
node_memory_ShmemHugePages_bytes	gauge	Memory information field ShmemHugePages_bytes.
<pre>node_memory_ShmemPmdMapped_bytes</pre>	gauge	Memory information field ShmemPmdMapped_bytes.
node_memory_Shmem_bytes	gauge	Memory information field Shmem_bytes.
<pre>node_memory_Slab_bytes</pre>	gauge	Memory information field Slab_bytes.

Metric Name	Туре	Description
<pre>node_memory_SwapCached_bytes</pre>	gauge	Memory information field SwapCached_bytes.
<pre>node_memory_SwapFree_bytes</pre>	gauge	Memory information field SwapFree_bytes.
<pre>node_memory_SwapTotal_bytes</pre>	gauge	Memory information field SwapTotal_bytes.
<pre>node_memory_Unevictable_bytes</pre>	gauge	Memory information field Unevictable_bytes.
<pre>node_memory_VmallocChunk_bytes</pre>	gauge	Memory information field VmallocChunk_bytes.
<pre>node_memory_VmallocTotal_bytes</pre>	gauge	Memory information field VmallocTotal_bytes.
<pre>node_memory_VmallocUsed_bytes</pre>	gauge	Memory information field VmallocUsed_bytes.
<pre>node_memory_WritebackTmp_bytes</pre>	gauge	Memory information field WritebackTmp_bytes.
<pre>node_memory_Writeback_bytes</pre>	gauge	Memory information field Writeback_bytes.
<pre>node_netstat_Icmp6_InErrors</pre>	counter	Statistic Icmp6InErrors.
<pre>node_netstat_Icmp6_InMsgs</pre>	counter	Statistic Icmp6InMsgs.
<pre>node_netstat_Icmp6_OutMsgs</pre>	counter	Statistic Icmp6OutMsgs.
<pre>node_netstat_Icmp_InErrors</pre>	counter	Statistic IcmpInErrors.
<pre>node_netstat_Icmp_InMsgs</pre>	counter	Statistic IcmpInMsgs.

Table 26: Cloud-Native Contrail Networking (CN2) Cluster Node Metric List (Continued)

Metric Name	Туре	Description
<pre>node_netstat_Icmp_OutMsgs</pre>	counter	Statistic IcmpOutMsgs.
<pre>node_netstat_Ip6_In0ctets</pre>	counter	Statistic Ip6InOctets.
<pre>node_netstat_Ip6_OutOctets</pre>	counter	Statistic Ip60ut0ctets.
<pre>node_netstat_IpExt_InOctets</pre>	counter	Statistic IpExtInOctets.
<pre>node_netstat_IpExt_OutOctets</pre>	counter	Statistic IpExtOutOctets.
node_netstat_Ip_Forwarding	counter	Statistic IpForwarding.
<pre>node_netstat_TcpExt_ListenDrops</pre>	counter	Statistic TcpExtListenDrops.
<pre>node_netstat_TcpExt_ListenOverflows</pre>	counter	Statistic TcpExtListenOverflows.
<pre>node_netstat_TcpExt_SyncookiesFaile d</pre>	counter	Statistic TcpExtSyncookiesFailed.
node_netstat_TcpExt_SyncookiesRecv	counter	Statistic TcpExtSyncookiesRecv.
<pre>node_netstat_TcpExt_SyncookiesSent</pre>	counter	Statistic TcpExtSyncookiesSent.
<pre>node_netstat_TcpExt_TCPSynRetrans</pre>	counter	Statistic TcpExtTCPSynRetrans.
<pre>node_netstat_TcpExt_TCPTimeouts</pre>	counter	Statistic TcpExtTCPTimeouts.
<pre>node_netstat_Tcp_ActiveOpens</pre>	counter	Statistic TcpActiveOpens.
node_netstat_Tcp_CurrEstab	counter	Statistic TcpCurrEstab.
node_netstat_Tcp_InErrs	counter	Statistic TcpInErrs.
node_netstat_Tcp_InSegs	counter	Statistic TcpInSegs.
node_netstat_Tcp_OutRsts	counter	Statistic TcpOutRsts.

Table 26: Cloud-Native Contrail Networking (CN2) Cluster Node Metric List (Continued)
- · · · · · · · · · · · · · · · · · · ·

Metric Name	Туре	Description
<pre>node_netstat_Tcp_OutSegs</pre>	counter	Statistic TcpOutSegs.
<pre>node_netstat_Tcp_PassiveOpens</pre>	counter	Statistic TcpPassiveOpens.
<pre>node_netstat_Tcp_RetransSegs</pre>	counter	Statistic TcpRetransSegs.
node_netstat_Udp6_InDatagrams	counter	Statistic Udp6InDatagrams.
node_netstat_Udp6_InErrors	counter	Statistic Udp6InErrors.
node_netstat_Udp6_NoPorts	counter	Statistic Udp6NoPorts.
node_netstat_Udp6_OutDatagrams	counter	Statistic Udp6OutDatagrams.
<pre>node_netstat_Udp6_RcvbufErrors</pre>	counter	Statistic Udp6RcvbufErrors.
node_netstat_Udp6_SndbufErrors	counter	Statistic Udp6SndbufErrors.
node_netstat_UdpLite6_InErrors	counter	Statistic UdpLite6InErrors.
<pre>node_netstat_UdpLite_InErrors</pre>	counter	Statistic UdpLiteInErrors.
node_netstat_Udp_InDatagrams	counter	Statistic UdpInDatagrams.
node_netstat_Udp_InErrors	counter	Statistic UdpInErrors.
node_netstat_Udp_NoPorts	counter	Statistic UdpNoPorts.
node_netstat_Udp_OutDatagrams	counter	Statistic UdpOutDatagrams.
node_netstat_Udp_RcvbufErrors	counter	Statistic UdpRcvbufErrors.
node_netstat_Udp_SndbufErrors	counter	Statistic UdpSndbufErrors.
node_network_address_assign_type	gauge	address_assign_type value of /sys/ class/net/.

Metric Name	Туре	Description
<pre>node_network_carrier</pre>	gauge	carrier value of /sys/class/net/.
<pre>node_network_carrier_changes_total</pre>	counter	carrier_changes_total value of /sys/ class/net/.
<pre>node_network_carrier_down_changes_t otal</pre>	counter	carrier_down_changes_total value of /sys/class/net/.
<pre>node_network_carrier_up_changes_tot al</pre>	counter	<pre>carrier_up_changes_total value of /sys/class/net/.</pre>
<pre>node_network_device_id</pre>	gauge	device_id value of /sys/class/net/.
node_network_dormant	gauge	dormant value of /sys/class/net/.
node_network_flags	gauge	flags value of / sys/class/net/ .
<pre>node_network_iface_id</pre>	gauge	iface_id value of /sys/class/net/.
<pre>node_network_iface_link</pre>	gauge	iface_link value of /sys/class/net/.
<pre>node_network_iface_link_mode</pre>	gauge	iface_link_mode value of /sys/class/ net/.
node_network_info	gauge	Non-numeric data from /sys/class/ net/ , value is always 1.
<pre>node_network_mtu_bytes</pre>	gauge	mtu_bytes value of /sys/class/net/.
<pre>node_network_name_assign_type</pre>	gauge	name_assign_type value of /sys/ class/net/.
node_network_net_dev_group	gauge	net_dev_group value of /sys/class/ net/.
<pre>node_network_protocol_type</pre>	gauge	protocol_type value of /sys/class/ net/.

Metric Name	Туре	Description
<pre>node_network_receive_bytes_total</pre>	counter	Network device statistic receive_bytes.
<pre>node_network_receive_compressed_tot al</pre>	counter	Network device statistic receive_compressed.
<pre>node_network_receive_drop_total</pre>	counter	Network device statistic receive_drop.
<pre>node_network_receive_errs_total</pre>	counter	Network device statistic receive_errs.
<pre>node_network_receive_fifo_total</pre>	counter	Network device statistic receive_fifo.
<pre>node_network_receive_frame_total</pre>	counter	Network device statistic receive_frame.
<pre>node_network_receive_multicast_tota 1</pre>	counter	Network device statistic receive_multicast.
<pre>node_network_receive_packets_total</pre>	counter	Network device statistic receive_packets.
node_network_speed_bytes	gauge	speed_bytes value of /sys/class/ net/.
<pre>node_network_transmit_bytes_total</pre>	counter	Network device statistic transmit_bytes.
<pre>node_network_transmit_carrier_total</pre>	counter	Network device statistic transmit_carrier.
<pre>node_network_transmit_colls_total</pre>	counter	Network device statistic transmit_colls.

Metric Name	Туре	Description
<pre>node_network_transmit_compressed_to tal</pre>	counter	Network device statistic transmit_compressed.
<pre>node_network_transmit_drop_total</pre>	counter	Network device statistic transmit_drop.
<pre>node_network_transmit_errs_total</pre>	counter	Network device statistic transmit_errs.
<pre>node_network_transmit_fifo_total</pre>	counter	Network device statistic transmit_fifo.
<pre>node_network_transmit_packets_total</pre>	counter	Network device statistic transmit_packets.
<pre>node_network_transmit_queue_length</pre>	gauge	transmit_queue_length value of /sys/ class/net/.
node_network_up	gauge	Value is 1 if operstate is 'up', 0 otherwise.
<pre>node_nf_conntrack_entries</pre>	gauge	Number of currently allocated flow entries for connection tracking.
<pre>node_nf_conntrack_entries_limit</pre>	gauge	Maximum size of connection tracking table.
node_os_info	gauge	A metric with a constant '1' value labeled by build_id, id, id_like, image_id, image_version, name, pretty_name, variant, variant_id, version, version_codename, version_id.
node_os_version	gauge	Metric containing the major.minor part of the OS version.

Metric Name	Туре	Description
<pre>node_power_supply_info</pre>	gauge	info of /sys/class/power_supply/ <power_supply>.</power_supply>
<pre>node_power_supply_online</pre>	gauge	online value of /sys/class/ power_supply/ <power_supply>.</power_supply>
node_procs_blocked	gauge	Number of processes blocked waiting for I/O to be completed.
node_procs_running	gauge	Number of processes in runnable state.
node_schedstat_running_seconds_tota l	counter	Number of seconds CPU spent running a process.
<pre>node_schedstat_timeslices_total</pre>	counter	Number of timeslices executed by CPU.
node_schedstat_waiting_seconds_tota l	counter	Number of seconds spent by processing waiting for this CPU.
<pre>node_scrape_collector_duration_seco nds</pre>	gauge	node_exporter: Duration of a collector scrape.
<pre>node_scrape_collector_success</pre>	gauge	node_exporter: Whether a collector succeeded.
<pre>node_sockstat_FRAG6_inuse</pre>	gauge	Number of FRAG6 sockets in state inuse.
node_sockstat_FRAG6_memory	gauge	Number of FRAG6 sockets in state memory.
<pre>node_sockstat_FRAG_inuse</pre>	gauge	Number of FRAG sockets in state inuse.

Metric Name	Туре	Description
<pre>node_sockstat_FRAG_memory</pre>	gauge	Number of FRAG sockets in state memory.
<pre>node_sockstat_RAW6_inuse</pre>	gauge	Number of RAW6 sockets in state inuse.
<pre>node_sockstat_RAW_inuse</pre>	gauge	Number of RAW sockets in state inuse.
<pre>node_sockstat_TCP6_inuse</pre>	gauge	Number of TCP6 sockets in state inuse.
<pre>node_sockstat_TCP_alloc</pre>	gauge	Number of TCP sockets in state alloc.
<pre>node_sockstat_TCP_inuse</pre>	gauge	Number of TCP sockets in state inuse.
<pre>node_sockstat_TCP_mem</pre>	gauge	Number of TCP sockets in state mem.
<pre>node_sockstat_TCP_mem_bytes</pre>	gauge	Number of TCP sockets in state mem_bytes.
node_sockstat_TCP_orphan	gauge	Number of TCP sockets in state orphan.
node_sockstat_TCP_tw	gauge	Number of TCP sockets in state tw.
<pre>node_sockstat_UDP6_inuse</pre>	gauge	Number of UDP6 sockets in state inuse.
<pre>node_sockstat_UDPLITE6_inuse</pre>	gauge	Number of UDPLITE6 sockets in state inuse.
<pre>node_sockstat_UDPLITE_inuse</pre>	gauge	Number of UDPLITE sockets in state inuse.

Metric Name	Туре	Description
<pre>node_sockstat_UDP_inuse</pre>	gauge	Number of UDP sockets in state inuse.
<pre>node_sockstat_UDP_mem</pre>	gauge	Number of UDP sockets in state mem.
<pre>node_sockstat_UDP_mem_bytes</pre>	gauge	Number of UDP sockets in state mem_bytes.
<pre>node_sockstat_sockets_used</pre>	gauge	Number of IPv4 sockets in use.
<pre>node_softnet_dropped_total</pre>	counter	Number of dropped packets.
<pre>node_softnet_processed_total</pre>	counter	Number of processed packets
<pre>node_softnet_times_squeezed_total</pre>	counter	Number of times processing packets ran out of quota.
<pre>node_textfile_scrape_error</pre>	gauge	1 if there was an error opening or reading a file, otherwise, 0.
<pre>node_time_clocksource_available_inf o</pre>	gauge	Available clocksources read from /sys/devices/system/ clocksource.
<pre>node_time_clocksource_current_info</pre>	gauge	Current clocksource read from /sys/ devices/system/clocksource.
node_time_seconds	gauge	System time in seconds since epoch (1970).
<pre>node_time_zone_offset_seconds</pre>	gauge	System time zone offset in seconds.
<pre>node_timex_estimated_error_seconds</pre>	gauge	Estimated error in seconds.
<pre>node_timex_frequency_adjustment_rat .</pre>	gauge	Local clock frequency adjustment.

io

Table 26: Cloud-Native Contrail Networking (CN2) Cluster Node Metric List (Continued)

Metric Name	Туре	Description
<pre>node_timex_loop_time_constant</pre>	gauge	Phase-locked loop time constant.
<pre>node_timex_maxerror_seconds</pre>	gauge	Maximum error in seconds.
<pre>node_timex_offset_seconds</pre>	gauge	Time offset in between local system and reference clock.
<pre>node_timex_pps_calibration_total</pre>	counter	Pulse-per-second count of calibration intervals.
<pre>node_timex_pps_error_total</pre>	counter	Pulse-per-second of calibration errors.
<pre>node_timex_pps_frequency_hertz</pre>	gauge	Pulse-per-second frequency.
<pre>node_timex_pps_jitter_seconds</pre>	gauge	Pulse-per-second jitter.
<pre>node_timex_pps_jitter_total</pre>	counter	Pulse-per-second count of jitter- limit-exceeded events.
<pre>node_timex_pps_shift_seconds</pre>	gauge	Pulse-per-second interval duration.
<pre>node_timex_pps_stability_exceeded_t otal</pre>	counter	Pulse-per-second count of stability limit exceeded events.
<pre>node_timex_pps_stability_hertz</pre>	gauge	Pulse-per-second stability, average of recent frequency changes.
<pre>node_timex_status</pre>	gauge	Value of the status array bits.
<pre>node_timex_sync_status</pre>	gauge	ls clock synchronized to a reliable server (1 = yes, 0 = no)
<pre>node_timex_tai_offset_seconds</pre>	gauge	International Atomic Time (TAI) offset.
<pre>node_timex_tick_seconds</pre>	gauge	Seconds between clock ticks.

Metric Name	Туре	Description
node_udp_queues	gauge	Number of allocated memory in the kernel for UDP datagrams in bytes.
node_uname_info	gauge	Labeled system information as provided by the uname system call.
node_vmstat_oom_kill	counter	/proc/vmstat information field oom_kill.
node_vmstat_pgfault	counter	/proc/vmstat information field pgfault.
node_vmstat_pgmajfault	counter	/proc/vmstat information field pgmajfault.
node_vmstat_pgpgin	counter	/proc/vmstat information field pgpgin.
node_vmstat_pgpgout	counter	/proc/vmstat information field pgpgout.
node_vmstat_pswpin	counter	/proc/vmstat information field pswpin.
node_vmstat_pswpout	counter	<pre>/proc/vmstat information field pswpout.</pre>

RELATED DOCUMENTATION

Contrail Networking Analytics 338	
Contrail Networking Metric List 344	
Kubernetes Metric List 358	

Contrail Networking Alert List | 414

Contrail Networking Alert List

Alert Name	Severity	Description
VRouterConnectionDown	major	VRouter <name> <connection_type> connection to <connection_id> is down.</connection_id></connection_type></name>
VRouterNonFunctional	major	VRouter <name> is non-functional.</name>
ControllerNonFunctional	major	Controller <name> is non-functional.</name>
ControllerConnectionDown	major	Controller <name> <connection_type> connection to <connection_id> is down.</connection_id></connection_type></name>
ControllerDBConnectionDown	major	Controller <name> connection to database is down.</name>
AlertmanagerFailedReload	critical	Reloading an Alertmanager configuration has failed.
AlertmanagerMembersInconsistent	critical	A member of an Alertmanager cluster has not found all other cluster members.
AlertmanagerFailedToSendAlerts	warning	An Alertmanager instance failed to send notifications.
AlertmanagerClusterFailedToSendAler ts	critical	All Alertmanager instances in a cluster failed to send notifications to a critical integration.
AlertmanagerClusterFailedToSendAler ts	warning	All Alertmanager instances in a cluster failed to send notifications to a non-critical integration.

Alert Name	Severity	Description
AlertmanagerConfigInconsistent	critical	Alertmanager instances within the same cluster have different configurations.
AlertmanagerClusterDown	critical	Half or more of the Alertmanager instances within the same cluster are down.
AlertmanagerClusterCrashlooping	critical	Half or more of the Alertmanager instances within the same cluster are crashlooping.
ConfigReloaderSidecarErrors	warning	config-reloader sidecar has not had a successful reload for 10m.
etcdInsufficientMembers	critical	etcd cluster " <name>": insufficient members (<value>).</value></name>
etcdNoLeader	critical	etcd cluster " <name>": member <instance> has no leader.</instance></name>
etcdHighNumberOfLeaderChanges	warning	etcd cluster " <name>": instance <instance> has seen <value> leader changes within the last hour.</value></instance></name>
etcdHighNumberOfFailedGRPCRequests	warning	etcd cluster " <name>": <value>% of requests for <grpc_method> failed on etcd instance <instance>.</instance></grpc_method></value></name>
etcdHighNumberOfFailedGRPCRequests	critical	etcd cluster " <name>": <value>% of requests for <grpc_method> failed on etcd instance <instance>.</instance></grpc_method></value></name>
etcdGRPCRequestsSlow	critical	etcd cluster " <name>": gRPC requests to <grpc_method> are taking <value>s on etcd instance <instance>.</instance></value></grpc_method></name>

Alert Name	Severity	Description
etcdMemberCommunicationSlow	warning	etcd cluster " <name>": member communication with <name> is taking <value>s on etcd instance <instance>.</instance></value></name></name>
etcdHighNumberOfFailedProposals	warning	etcd cluster " <name>": <value> proposal failures within the last hour on etcd instance <instance>.</instance></value></name>
etcdHighFsyncDurations	warning	etcd cluster " <name>": 99th percentile fsync durations are <value>s on etcd instance <instance>.</instance></value></name>
etcdHighCommitDurations	warning	etcd cluster " <name>": 99th percentile commit durations <value>s on etcd instance <instance>.</instance></value></name>
etcdHighNumberOfFailedHTTPRequests	warning	<value>% of requests for <method> failed on etcd instance <instance>.</instance></method></value>
etcdHighNumberOfFailedHTTPRequests	critical	<value>% of requests for <method> failed on etcd instance <instance>.</instance></method></value>
etcdHTTPRequestsSlow	warning	etcd instance <instance> HTTP requests to <method> are slow.</method></instance>
TargetDown	warning	One or more targets are unreachable.
KubeAPIErrorBudgetBurn	critical	The API server is burning too much error budget.
KubeAPIErrorBudgetBurn	warning	The API server is burning too much error budget.

Alert Name	Severity	Description
KubeStateMetricsListErrors	critical	kube-state-metrics is experiencing errors in list operations.
KubeStateMetricsWatchErrors	critical	kube-state-metrics is experiencing errors in watch operations.
KubeStateMetricsShardingMismatch	critical	kube-state-metrics sharding is misconfigured.
KubeStateMetricsShardsMissing	critical	kube-state-metrics shards are missing.
KubePodCrashLooping	warning	Pod is crash looping.
KubePodNotReady	warning	Pod has been in a non-ready state for more than 15 minutes.
KubeDeploymentGenerationMismatch	warning	Deployment generation mismatch due to possible roll-back.
KubeDeploymentReplicasMismatch	warning	Deployment has not matched the expected number of replicas.
KubeStatefulSetReplicasMismatch	warning	Deployment has not matched the expected number of replicas.
KubeStatefulSetGenerationMismatch	warning	StatefulSet generation mismatch due to possible roll-back.
KubeStatefulSetUpdateNotRolledOut	warning	StatefulSet update has not been rolled out.
KubeDaemonSetRolloutStuck	warning	DaemonSet rollout is stuck.
KubeContainerWaiting	warning	Pod container waiting longer than 1 hour.
KubeDaemonSetNotScheduled	warning	DaemonSet pods are not scheduled.

Alert Name	Severity	Description
KubeDaemonSetMisScheduled	warning	DaemonSet pods are misscheduled.
KubeJobCompletion	warning	Job was not complete in time.
KubeJobFailed	warning	Job failed (was not completed).
KubeHpaReplicasMismatch	warning	HPA has not matched desired number of replicas.
KubeHpaMaxedOut	warning	HPA is running at max replicas.
KubeCPUOvercommit	warning	Cluster has overcommitted CPU resource requests.
KubeMemoryOvercommit	warning	Cluster has overcommitted CPU resource requests.
KubeCPUQuotaOvercommit	warning	Cluster has overcommitted CPU resource requests.
KubeMemoryQuotaOvercommit	warning	Cluster has overcommitted memory resource requests.
KubeQuotaAlmostFull	info	Namespace quota is going to be full.
KubeQuotaFullyUsed	info	Namespace quota is fully used.
KubeQuotaExceeded	warning	Namespace quota has exceeded the limits.
CPUThrottlingHigh	info	Processes experience elevated CPU throttling.
KubePersistentVolumeFillingUp	critical	PersistentVolume is filling up.
KubePersistentVolumeFillingUp	warning	PersistentVolume is filling up.

Table 27: Cloud-Native Contrail Networkin	g (CN2) Alert List <i>(Continued)</i>

Alert Name	Severity	Description
KubePersistentVolumeErrors	critical	PersistentVolume is having issues with provisioning.
KubeVersionMismatch	warning	Different semantic versions of Kubernetes components are running.
KubeClientErrors	warning	Kubernetes API server client is experiencing errors.
KubeClientCertificateExpiration	warning	Client certificate is about to expire.
KubeClientCertificateExpiration	critical	Client certificate is about to expire.
KubeAggregatedAPIErrors	warning	Kubernetes aggregated API has reported errors.
KubeAggregatedAPIDown	warning	Kubernetes aggregated API is down.
KubeAPIDown	critical	Target disappeared from Prometheus target discovery.
KubeAPITerminatedRequests	warning	The Kubernetes apiserver has terminated <value> of its incoming requests.</value>
KubeControllerManagerDown	critical	Target disappeared from Prometheus target discovery.
KubeProxyDown	critical	Target disappeared from Prometheus target discovery.
KubeNodeNotReady	warning	Node is not ready.
KubeNodeUnreachable	warning	Node is unreachable.
KubeletTooManyPods	info	Kubelet is running at capacity.

Alert Name	Severity	Description
KubeNodeReadinessFlapping	warning	Node readiness status is flapping.
KubeletPlegDurationHigh	warning	Kubelet Pod Lifecycle Event Generator is taking too long to relist.
KubeletPodStartUpLatencyHigh	warning	Kubelet Pod startup latency is too high.
KubeletClientCertificateExpiration	warning	Kubelet client certificate is about to expire.
KubeletClientCertificateExpiration	critical	Kubelet client certificate is about to expire.
KubeletServerCertificateExpiration	warning	Kubelet server certificate is about to expire.
KubeletServerCertificateExpiration	critical	Kubelet server certificate is about to expire.
KubeletClientCertificateRenewalErro rs	warning	Kubelet has failed to renew its client certificate.
KubeletServerCertificateRenewalErro rs	warning	Kubelet has failed to renew its server certificate.
KubeletDown	critical	Target disappeared from Prometheus target discovery.
KubeSchedulerDown	critical	Target disappeared from Prometheus target discovery.
NodeFilesystemSpaceFillingUp	warning	Filesystem is predicted to run out of space within the next 24 hours.
NodeFilesystemSpaceFillingUp	critical	Filesystem is predicted to run out of space within the next 4 hours.

Alert Name	Severity	Description
NodeFilesystemAlmostOutOfSpace	warning	Filesystem has less than 5% space left.
NodeFilesystemAlmostOutOfSpace	critical	Filesystem has less than 3% space left.
NodeFilesystemFilesFillingUp	warning	Filesystem is predicted to run out of inodes within the next 24 hours.
NodeFilesystemFilesFillingUp	critical	Filesystem is predicted to run out of inodes within the next 4 hours.
NodeFilesystemAlmostOutOfFiles	warning	Filesystem has less than 5% inodes left.
NodeFilesystemAlmostOutOfFiles	critical	Filesystem has less than 3% inodes left.
NodeNetworkReceiveErrs	warning	Network interface is reporting many receive errors.
NodeNetworkTransmitErrs	warning	Network interface is reporting many transmit errors.
NodeHighNumberConntrackEntriesUsed	warning	Number of conntrack are getting close to the limit.
NodeTextFileCollectorScrapeError	warning	Node Exporter text file collector failed to scrape.
NodeClockSkewDetected	warning	Clock skew detected.
NodeClockNotSynchronising	warning	Clock not synchronizing.
NodeRAIDDegraded	critical	RAID array is degraded.
NodeRAIDDiskFailure	warning	Failed device in RAID array.

Table 27: Cloud-Native Contrail Networking (CN2) Alert List (Continued)

Alert Name	Severity	Description
NodeFileDescriptorLimit	warning	Kernel is predicted to exhaust file descriptors limit soon.
NodeFileDescriptorLimit	critical	Kernel is predicted to exhaust file descriptors limit soon.
NodeNetworkInterfaceFlapping	warning	Network interface is often changing its status.
PrometheusBadConfig	critical	Failed Prometheus configuration reload.
PrometheusNotificationQueueRunningF ull	warning	Prometheus alert notification queue predicted to run full in less than 30m.
PrometheusErrorSendingAlertsToSomeA lertmanagers	warning	Prometheus has encountered more than 1% errors sending alerts to a specific Alertmanager.
PrometheusNotConnectedToAlertmanage rs	warning	Prometheus is not connected to any Alertmanagers.
PrometheusTSDBReloadsFailing	warning	Prometheus has issues reloading blocks from disk.
PrometheusTSDBCompactionsFailing	warning	Prometheus has issues compacting blocks.
PrometheusNotIngestingSamples	warning	Prometheus is not ingesting samples.
PrometheusDuplicateTimestamps	warning	Prometheus is dropping samples with duplicate timestamps.
PrometheusOutOfOrderTimestamps	warning	Prometheus drops samples with out-of-order timestamps.

Alert Name	Severity	Description
PrometheusRemoteStorageFailures	critical	Prometheus fails to send samples to remote storage.
PrometheusRemoteWriteBehind	critical	Prometheus remote write is behind.
PrometheusRemoteWriteDesiredShards	warning	Prometheus remote write desired shards calculation wants to run more than configured max shards.
PrometheusRuleFailures	critical	Prometheus is failing rule evaluations.
PrometheusMissingRuleEvaluations	warning	Prometheus is missing rule evaluations due to slow rule group evaluation.
PrometheusTargetLimitHit	warning	Prometheus has dropped targets because some scrape configs have exceeded the target limit.
PrometheusLabelLimitHit	warning	Prometheus has dropped targets because some scrape configs have exceeded the label limit.
PrometheusTargetSyncFailure	critical	Prometheus has failed to sync targets.
PrometheusErrorSendingAlertsToAnyAl ertmanager	critical	Prometheus encounters more than 3% errors sending alerts to any Alertmanager.
PrometheusOperatorListErrors	warning	Errors while performing list operations in controller.
PrometheusOperatorWatchErrors	warning	Errors while performing list operations in controller.
PrometheusOperatorSyncFailed	warning	Last controller reconciliation failed.

Alert Name	Severity	Description
PrometheusOperatorReconcileErrors	warning	Errors while reconciling controller.

warning

warning

warning

RELATED DOCUMENTATION

PrometheusOperatorNodeLookupErrors

PrometheusOperatorRejectedResources

PrometheusOperatorNotReady

Contrail Networking Analytics 338	
Contrail Networking Metric List 344	
Kubernetes Metric List 358	
Cluster Node Metric List 396	

vRouter Session Analytics in Contrail Networking

IN THIS SECTION

- Collector Module | 425
- Collector Deployment | 425
- Data Collection | 425
- Configure Data Collection | 428
- Collector Query | 428
- Run a Query | 428

Errors while reconciling

Prometheus operator not ready.

Resources rejected by Prometheus

Prometheus.

operator.

Juniper® Networks supports the collection, storage, and query for vRouter traffic in environments using Cloud-Native Contrail Networking (CN2) Release 22.1 or later in a Kubernetes-orchestrated environment.

Collector Module

CN2 collects user visible entities (UVEs) and traffic information (session) for traffic analysis and troubleshooting. The collector module stores these objects and provides APIs to access the collected information.

The CN2 vRouter agent exports data records to the collector when events are created or deleted.

Collector Deployment


The following components are installed in the Contrail cluster in the contrail namespace (NS):

- Collector Microservice-Collects incoming events.
- InfluxDB—A time series database built specifically for storing time series data. Works with Grafana as a visualization tool for time series data.
- Fluentd—Logging agent that performs log collection, parsing, and distribution to other services such asOpenSearch.
- OpenSearch–OpenSearch is the search and analytics engine in the AWS OpenSearch Stack, providing real-time search and analytics for all types of data.
- OpenSearch Dashboards—User interface that lets you visualize your OpenSearch data and navigate the OpenSearch Stack.

Data Collection

Figure 21 on page 426 shows the data collection.

Figure 21: Cloud-Native Contrail Collector: Event and Log Ingestion



UVEs

UVEs are stored in OpenSearch in an index named by the name of the UVE.

Session

Session records are stored in InfluxDB. These records are pushed as events from all agents. This data is downsampled for longer duration. Retention periods of live, downsampled table, and downsampling windows are configurable using the configuration.

Column	Filterable	Detail
vn	Yes	Client Virtual Network
vmi	Yes	Interface
remote_vn	Yes	Server Virtual Network
vrouter_ip	Yes	Agent IP
local_ip	Yes	Client IP

Table 28: Session Records I	Information (Continued)
-----------------------------	-------------------------

Column	Filterable	Detail
client_port	Yes	Client Port
remote_ip	Yes	Server IP
server_port	Yes	Server Port
protocol	Yes	Protocol
label.local. <label-name></label-name>	Yes	Client Pod Labels (for example, client pod with label site maps to label.local.site tag in database).
label.remote. <label-name></label-name>	Yes	Server Pod Labels
forward_sampled_bytes	No	Bytes Sent
forward_sampled_pkts	No	Packets Sent
reverse_sampled_bytes	No	Bytes Received
reverse_sampled_pkts	No	Packets Received
total_bytes	No	Total Bytes Exchanged

Configure Data Collection

To configure vRouter agents to send SessionEndpoint messages to the fluentd service, run the following three commands. Replace <cluster-ip> with the cluster IP address of the fluentd service in the contrail-analytics namespace.

kubectl -n contrail patch vrouter contrail-vrouter-masters --type=merge -p '{"spec":{"agent":
 {"default":{"collectors":["<cluster-ip>:24224"]}}}'

kubectl -n contrail patch vrouter contrail-vrouter-nodes --type=merge -p '{"spec":{"agent":
 {"default":{"collectors":["<cluster-ip>:24224"]}}}'

kubectl -n contrail patch gvc default-global-vrouter-config --type=merge -p '{"spec":
{"flowExportRate": 10000}}'

After running the three configuration commands, restart vRouter for the configuration to take effect. To restart vRouter, run the following command:

```
kubectl -n contrail delete $(kubectl get pods -l 'app in (contrail-vrouter-masters, contrail-
vrouter-nodes)' -n contrail -o name)
```

Collector Query

The collector modules provide a query interface for access.

Run a Query

Example Query

The following query gets total bytes exchanged between unique source-destination pairs (by labels) in the contrail-analytics namespace:

```
{
  "granularity": 3600,
  "column": [
   {
      "name": "total_bytes",
      "aggregation": "sum"
    },
    {
      "name": "/^label.*/",
      "regex": true
   }
  ],
  "skip_columns": [
    "label.remote.pod-template-hash",
    "label.local.pod-template-hash"
  ],
  "range":{
    "start_time": -3600
  },
  "filter": [
   {
      "field": "label.local.namespace",
      "operator": "==",
      "value": "contrail-analytics"
   },
    {
      "field": "label.remote.namespace",
      "operator": "==",
      "value": "contrail-analytics"
   }
  ]
}
```

Example Query Response

```
{
    "status": "success",
    "total": 5,
```

```
"data": {
  "resultType": "matrix",
  "result": [
   {
      "metric": {
        "label.local.namespace": "contrail-analytics",
       "label.remote.app": "collector",
       "label.remote.namespace": "contrail-analytics"
     },
     "fields": [
       "_time",
       "total_bytes"
     ],
      "values": [
       Ε
         1645768800,
         31012095
       ]
     ]
   },
   {
      "metric": {
        "label.local.namespace": "contrail-analytics",
        "label.remote.app": "opensearch",
        "label.remote.chart": "opensearch",
        "label.remote.controller-revision-hash": "opensearch-7fcc8df678",
        "label.remote.namespace": "contrail-analytics",
       "label.remote.release": "contrail-analytics"
     },
     "fields": [
       "_time",
       "total_bytes"
     ],
      "values": [
       Ε
         1645768800,
         221493
       ]
     ]
   },
   {
      "metric": {
        "label.local.controller-revision-hash": "5599999fc7",
```

```
"label.local.namespace": "contrail-analytics",
    "label.local.pod-template-generation": "1",
    "label.remote.namespace": "contrail-analytics"
 },
  "fields": [
    "_time",
   "total_bytes"
  ],
  "values": [
    Ε
     1645768800,
     23349247
    ]
  ]
},
{
  "metric": {
    "label.local.app": "collector",
    "label.local.namespace": "contrail-analytics",
    "label.remote.controller-revision-hash": "influxdb-7bdd86f8c",
    "label.remote.namespace": "contrail-analytics"
 },
  "fields": [
    "_time",
    "total_bytes"
  ],
  "values": [
    Ε
     1645768800,
     10412552
    1
  ]
},
{
  "metric": {
    "label.local.app": "opensearch-dashboards",
    "label.local.namespace": "contrail-analytics",
    "label.local.release": "contrail-analytics",
    "label.remote.app": "opensearch",
    "label.remote.chart": "opensearch",
    "label.remote.controller-revision-hash": "opensearch-7fcc8df678",
    "label.remote.namespace": "contrail-analytics",
    "label.remote.release": "contrail-analytics"
```

```
},
    "fields": [
        "_time",
        "total_bytes"
    ],
        "values": [
        [
            1645768800,
            25152
        ]
        ]
        }
    ]
    }
}
```

RELATED DOCUMENTATION

Contrail Networking Analytics | 338

Centralized Logging | 439

Extend TLS Analytics

SUMMARY

This topic describes how to enable TLS certificates for analytics components in Juniper® Cloud-Native Contrail Networking (CN2) Release 23.2 and later in a Kubernetes-orchestrated environment.

IN THIS SECTION

- Overview | 432
- Enable TLS on Analytics Components | 433

Overview

Starting in Release 23.2, you can enable TLS certificates for analytics components in CN2. TLS is a security protocol used for certificate exchange, mutual authentication, and negotiating ciphers to secure the stream from potential tampering and eavesdropping.

Certificates are part of the deployment used to start CN2. In Kubernetes all certificates are translated to secrets. By default, the certificate and secrets for the Contrail control plane and vRouter are automatically generated in the Juniper ContrailCertificateManager CRD.

Helm is used to install the TLS analytic components. When you install the components, certificate manager automatically creates the certificates and secrets needed for each analytic component. Once the certificate (secret) is created, each component has the secret name defined in its own deployment.yaml file that pulls the certificates when the pod comes up.

Enable TLS on Analytics Components

IN THIS SECTION

- Prerequisites | 433
- Enable TLS on CN2 Analytics Components | 433
- Enable TLS on Third Party Analytics Components | 436

The following sections describe how to enable TLS on CN2 and third party analytics components.

Prerequisites

To use this feature, you must install the following:

- A Kubernetes cluster
- CN2 Release 23.2 or later
- Helm 3.0 or later for Kubernetes, needed to install the analytic components. For more information, see the Helm website.

Enable TLS on CN2 Analytics Components

By default, TLS is automatically enabled on CN2 components during a Helm installation. When you install analytic components with Helm, certificate manager creates the certificates and secrets needed for each CN2 component. The secret is then added to the component's deployment.yaml file as shown in the following examples:

• Collector: A collector is a component that gathers data from various sources and transforms it into a format that can be easily analyzed. Collectors can apply transformations to the data such as filtering or aggregation.

The following is an example of collector with TLS enabled:

```
volumeMounts:
    - name: tls
    mountPath: /etc/config/tls
volumes:
    - name: tls
    secret:
    secretName: collector-tls
```

• Dashboard: The Dashboard component is a back-end service that serves the CN2 GUI.

The following is an example of Dashboard with TLS enabled:

```
volumeMounts:
    name: tls
    mountPath: /etc/config/tls
volumes:
    name: tls
    secret:
    secretName: dashboard-tls
```

• Portal: The portal analytics component enables a high-level overview of traffic patterns aggregated across a single portal in a dashboard-style visualization. This data can be used to analyze portal traffic and application rates over time.

The following is an example of portal analytics with TLS enabled:

```
volumeMounts:
    name: tls
    mountPath: /etc/config/tls
volumes:
    name: tls
    secret:
    secretName: portal-tls
```

Introspect: Introspect is a diagnostic utility that allows you to browse the internal state of CN2 components.

The following is an example of Introspect with TLS enabled:

```
volumeMounts:
    name: tls
    mountPath: /etc/config/tls
volumes:
    name: tls
    secret:
    secretName: introspect-tls
```

Multicluster Proxy: Multicluster is used to serve requests pertaining to multiple clusters and RBAC management.

The following is an example of Multicluster Proxy with TLS enabled:

```
volumeMounts:
    name: tls
    mountPath: /etc/config/tls
volumes:
    name: tls
    secret:
    secretName: multiclusterproxy-tls
```

• Contrail config exporter: Config exporter is used to get metrics related to deployments, and the virtual machine interface.

The following is an example of Contrail config exporter with TLS enabled:

```
volumeMounts:
    name: tls
    mountPath: /etc/config/tls
volumes:
    name: tls
    secret:
    secretName: contrailconfigexporter-tls
```

Enable TLS on Third Party Analytics Components

You can also enable TLS on third party analytics components. Certificate manager creates the certificate and secrets, but these components require additional configurations to enable TLS, as shown in the following examples:



Ambassador

Ambassador serves as an ingress for all incoming API requests (Prometheus, Collector, Dashboard, Proxy) from the outside.

The following is an example of Ambassador with TLS enabled:

```
---
apiVersion: getambassador.io
kind: Host
metadata:
   name: wildcard-host
spec:
   hostname: "*"
   acmeProvider:
    authority: none
   tlsSecret:
    name: tls-cert
    name: tls-cert
    name: tls-amabassador
   selector:
   matchLabels:
   hostname: wildcard-host
```

Fluentd

Fluentd collects logs, events, and flows running on each CN2 node. Fluentd is the logging agent that performs log collection, parsing, and distribution to other services such as OpenSearch.

The following is an example of Fluentd with TLS enabled:

```
<source>
@type forward
bind 0.0.0.0
port 24225
<transport tls>
   ca_path /etc/tls/ca.crt
   cert_path /etc/tls/tls.crt
   private_key_path /etc/tls/tls.key
</transport>
```

InfluxDB

InfluxDB is a time series database built specifically for storing time series data. InfluxDB works with Grafana as a visualization tools for time series data. Enabling TLS encrypts the communication between clients and the InfluxD server.

The following is an example of InfluxDB with TLS enabled:

```
env:

    name: INFLUXD_TLS_CERT

    value: /etc/ssl/tls/tls.crt

    name: INFLUXD_TLS_KEY

    value: /etc/ssl/tls/tls.key

volumes:

    name: tls

    secret:

    secretName: influxdb-tls

mountPoints:

    name: tls

    mountPoints:

    name: tls

    mountPath: /etc/ssl/tls
```

Kube Prometheus Stack

Kube Prometheus Stack is a collection of Kubernetes manifests, Grafana dashboards, and Prometheus rules that provides easy to operate end-to-end Kubernetes cluster monitoring.

The following is an example of Kube Prometheus Stack with TLS enabled:

```
web:
  tlsConfig:Kube
   keySecret:
   name: prometheus-tls
   key: tls.key
  cert:
   secret:
   name: prometheus-tls
   key: tls.crt
```

OpenSearch and OpenSearch Dashboards

OpenSearch is the search and analytics engine in the AWS OpenSearch Stack that provides real time search and analytics for all types of data. OpenSearch Dashboards is the GUI that lets you visualize your OpenSearch data and navigate the OpenSearch Stack.

The following is an example of OpenStack with TLS enabled:

```
ssl:
    transport:
    pemcert_filepath: tls/tls.crt
    pemkey_filepath: tls/tls.key
    pemtrustedcas_filepath: tls/ca.crt
    enforce_hostname_verification: false
```

The following is an example of OpenSearch dashboards with TLS enabled:

opensearch_dashboards.yaml

```
opensearch_security.multitenancy.enabled: true
    opensearch_security.multitenancy.tenants.preferred: ["Private", "Global"]
    opensearch_security.readonly_mode.roles: ["kibana_read_only"]
    opensearch_security.cookie.secure: true
    server.ssl.enabled: true
    opensearch.ssl.certificateAuthorities: [ "/usr/share/opensearch-dashboards/tls/ca.crt"]
    server.ssl.certificate: /usr/share/opensearch-dashboards/tls/tls.crt
    server.ssl.key: /usr/share/opensearch-dashboards/tls/tls.key
```

SEE ALSO

Configure Management and Control Plane Authentication with TLS Encryption

Contrail Networking Analytics

Install Contrail Analytics and the CN2 GUI

Centralized Logging

IN THIS SECTION

- Benefits of Centralized Logging | 439
- Overview: Centralized Logging | 439
- Logs, Events, and Flows with Fluentd | 440

Juniper® Networks supports centralized logging using Cloud-Native Contrail Networking[™] (CN2) Release 22.1 or later in a Kubernetes-orchestrated environment.

Benefits of Centralized Logging

- The centralization of all platform logs eases troubleshooting. Centralization allows you (the
 administrator) to take a holistic view of events or outages extending across the many components
 within the deployment.
- You have one portal, allowing you to monitor, view, filter, and search for events across all platform components from a single view.

Overview: Centralized Logging

Instead of browsing through individual log files, collected logs from all components of CN2 are available to you in a centralized location. The centralized location enables you to correlate the log files from multiple software components. For security, strict logging exists for all create, read, update, and delete

(CRUD) actions. You perform these actions with individual access credentials so that you can identify individuals.

AWS OpenSearch Stack, an open source log collector and analyzer framework, provides out-of-box log collection and analysis functionality. The OpenSearch stack allows a single portal for analyzing logs from CN2. OpenSearch stack also analyzes logs from other software components and platforms deployed in the cluster. Examples include Linux OS logs, Kubernetes logs, and software components such as virtualized network functions (VNFs) and container network functions (CNFs).

OpenSearch Stack includes:


- OpenSearch—Real-time and scalable search engine that allows for full-text and structured search as well as analytics. This search engine indexes and searches through large volumes of log data.
- OpenSearch Dashboard—Allows you to explore your OpenSearch log data through a web interface and enables you to build dashboards and queries.
- Fluentd–Logging agent that performs log collection, parsing, and distribution to other services such as OpenSearch.
- Fluent Bit—Log processor and forwarder that collects data, such as metrics and logs, from different sources. High throughput with low CPU and memory usage. Fluent Bit is installed in every workload cluster.

The logging components are included and deployed in the optional telemetry node deployment. Installation commands are integrated in the telemetry installation.

Logs, Events, and Flows with Fluentd

Fluentd collects logs, events, and flows running on each CN2 node. Fluentd is the logging agent that performs log collection, parsing, and distribution to other services such as OpenSearch.

Figure 22: Logs, Events, and Flows with Fluentd



Logs

Logs are collected from log files or stdout/stderr data streams and directed to the OpenSearch library stack with cluster quorum. Each CN2 node (configuration, control, compute, Web UI, and telemetry node) runs Fluent Bit or Fluentd to collect logs. The logs are sent to multiple configured sinks, such as OpenSearch. Fluentd supports multiple output options to send collected logs.

- Control and compute nodes generate unstructured and structured logs through the Sandesh library. The Contrail Networking Sandesh library generates structured JSON files.
- Configuration, Web UI, and telemetry node components produce standard logs to files or to stdout/ stderr, which are then sent to Fluentd or Fluent Bit.

Multiple Kubernetes clusters in any CN2 cluster or in multiple CN2 clusters can connect with a Fluentd/ OpenSearch monitoring component.

Events

The vRouter agent and control node produce events through Sandesh. The Sandesh library produces JSON structured data and sends those files to the configured options. Configured options are stdout, file, or TCP port (Fluentd). Fluentd is configured with multiple output options to send data either to OpenSearch or to the telemetry node's gRPC server. The telemetry node keeps cache for the latest status events.

Flows

The vRouter agent produces flow data at regular configured intervals. Configuration options for flow data generation supported by the vRouter agent are syslogs, JSON structure, and the default Sandesh.

RELATED DOCUMENTATION

Contrail Networking Analytics | 338

vRouter Session Analytics in Contrail Networking | 424

Port-Based Mirroring

SUMMARY


This section describes port-based mirroring in Juniper® Cloud-Native Contrail Networking (CN2) Release 22.2 and later in a Kubernetes-orchestrated environment.

IN THIS SECTION

- Overview: Port-Based Mirroring | 442
- Example: Configure Port-Based Mirroring | 443
- Summary | 445

Overview: Port-Based Mirroring

Figure 23: CN2 Port-Based Mirror Topology



Port mirroring sends network traffic from defined ports to a network analyzer where you can monitor and analyze the data. In CN2, the following is supported:

• Mirroring configuration is primarily driven from the pod configuration for both the receiver and interface being mirrored. You don't need to configure the virtual machine interface (VMI) directly.

- MirrorDestination involves creating a MirrorDestination resource and associating the MirrorDestination resource to the pod interface to be mirrored.
- MirrorDestination identifies the mirrored traffic receiver pod and interface. When juniperHeader is enabled, the receiver pod IP address and port are used. When juniperHeader is disabled, the receiver pod MAC address routingInstance is used to forward mirrored traffic.
- A MirrorDestination can be associated with multiple VMIs to be mirrored.
- A MirrorDestination resource defines the mirrored traffic receiver such as IP address, port used for receiving mirrored traffic, Juniper header configuration, dynamic or static next-hop, and so on.
- A pod interface to be mirrored can be configured when creating the pod or by editing the pod.

Example: Configure Port-Based Mirroring

The following procedure is an example configuration that creates a MirrorDestination resource and specifies the MirrorDestination resource name, such as mirrordestinationprofile1, on the interface to be mirrored.

 Use the MirrorDestination YAML file to create a MirrorDestination resource by adding multiple destination pods with the label core.juniper.net/analyzer-pod-selector: analyzerpod.

The MirrorDestination resource uses the label core.juniper.net/analyzer-pod-selector: analyzerpod to calculate and determine the mirrored traffic pod receiver.

Example MirrorDestination YAML file:

```
apiVersion: core.contrail.juniper.net/v1alpha1
kind: MirrorDestination
metadata:
    name: mirrordestinationprofile1
    labels:
        core.juniper.net/analyzer-pod-selector: analyzerpod
spec:
    trafficDirection: <ingress|egress|both>
    juniperHeader: <boolean>
    udpPort: <integer>
    staticNhHeader: <null for dynamic nh|vtep tunnel destip, mac, vxlanid for static nh>
    nextHopMode: <static|dynamic>
    nicAssistedMirroring: <boolean>
        nicAssistedVlanID:
    staticNextHopHeader:
```

vTEPDestinationIP: vTEPDestinationMac: vxlanID:

When you deploy the YAML file, multiple pods could match the label analyzerpod. The first matching pod is selected as the mirrored traffic receiver. The selected pod remains sticky until the pod or interface is no longer available.

Following is the analyzer pod YAML file with label analyzerpod, indicating that MirrorDestination can use this pod.

- Note the label value for core.juniper.net/analyzer-podanalyzerpod is the same as specified in the MirrorDestination YAML file.
- The MirrorDestination controller uses this label to calculate the analyzer_ip, macaddress, and routinginstance.
- The pod interface to be used is specified in the annotation below: core.juniper.net/analyzer-interface: true

You can specify the default pod interface directly under annotations. For a custom VN interface, you specify it in the cni-args of the network. The example Pod/analyzerpod YAML file shows both examples.

• core.juniper.net/analyzer-interface: true indicates that the vn-1 pod interface will receive mirrored traffic.

Example Pod/analyzerpod YAML file:

```
"core.juniper.net/analyzer-interface": "true"
}
]
```

2. Add the pod annotations and specify the mirroringDestination resource name on the interface to be mirrored.

In the following example YAML file, we enable mirroring on the pod vn-1 interface. We specify the MirrorDestination resource name mirrordestinationprofile1 on the interface to be mirrored.

Example Pod/mirrored-pod YAML file:

```
apiVersion: v1
kind: Pod
metadata:
  name: mirrored-pod
  namespace: mirror-ns
  annotations:
    core.juniper.net/mirror-destination: "mirrordestinationprofile1"
    k8s.v1.cni.cncf.io/networks: |
      Ε
        {
          "name": "vn-1",
          "namespace": "mirror-ns",
          "cni-args": {
            "core.juniper.net/mirror-destination": "mirrordestinationprofile1"
          }
        }
      ]
```

Summary

SUMMARY

IN THIS SECTION

This section describes configuration changes for port-based mirroring in CN2 Release 22.2.

From the analyzer pod annotations and labels, the VM and VMI are associated with the pod to be used in the MirrorDestination controller.

Analyzer VM Labels:

The VirtualMachine resource corresponding to the pod will have the label core.juniper.net/analyzer-pod label.

```
apiVersion: core.contrail.juniper.net/v1alpha1
kind: VirtualMachine
metadata:
  annotations:
    kube-manager.juniper.net/pod-cluster-name: contrail-k8s-kubemanager-ocp-kparmar-6mpccd
    kube-manager.juniper.net/pod-name: analyzerpod
    kube-manager.juniper.net/pod-namespace: multinode-ns
    labels:
    core.juniper.net/analyzer-pod: analyzerpod
```

Analyzer VMI Labels:

The VirtualMachineInterface resource for the analyzer pod will have the label core.juniper.net/analyzer-interface.

```
apiVersion: core.contrail.juniper.net/v1alpha1
kind: VirtualMachineInterface
metadata:
  annotations:
    index: 0/1
    interface: eth0
    kube-manager.juniper.net/pod-cluster-name: contrail-k8s-kubemanager-ocp-kparmar-6mpccd
    kube-manager.juniper.net/pod-name: analyzerpod
    kube-manager.juniper.net/pod-namespace: multinode-ns
    labels:
    core.juniper.net/analyzer-interface: ""
```

Source VMI Label indicating MirrorDestination:

Source VirtualMachineInterface corresponding to the pod interface being mirrored will have the label core.juniper.net/mirror-destination. The annotations will have the mirror configuration.

apiVersion: core.contrail.juniper.net/v1alpha1 kind: VirtualMachineInterface metadata:

```
annotations:
    core.juniper.net/mirroring-configuration:
    '{"analyzer_name":"mirrordestinationprofile1","analyzer_ip_address":"10.128.0.200","analyzer_maca
    ddress":"02:76:6c:25:f2:8c","ri":"default-
        domain:contrail-k8s-kubemanager-ocp-kparmar-6mpccd-contrail:default-podnetwork:default-
    podnetwork"}'
    labels:
        core.juniper.net/mirror-destination: mirrordestinationprofile1
```

Flow-Based Mirroring

SUMMARY

Juniper® Cloud-Native Contrail Networking (CN2) Release 23.2 in a Kubernetes-orchestrated environment supports flow-based network traffic mirroring.


IN THIS SECTION

- Overview | 447
- Configure Flow-Based Mirroring | 448

Overview

The flow-based mirroring feature is an extension to the current "Port-Based Mirroring" on page 442 feature. CN2 can selectively mirror network traffic on the basis of flow when vRouter is in the flow mode. In flow mode, CN2 has port-based mirroring capability as well as flow-based mirroring capability.

Figure 24: Flow-Based Mirroring Topology



With this feature, user can mirror any flow, which is specified by the security policy and sends it to the network analyzer that monitors and analyzes the data. The network analyzer is specified with mirrorDestination resource. It also supports mirrorDestination resource present outside the cluster.

In CN2, the flow-based mirroring feature,

- Uses an existing mirroring functionality of Contrail Networking vRouter to forward the mirrored traffic. There are two cases related to traffic forwarding:
 - If juniperHeader is enabled, the analyzer or destination IP address and UDP port is used to forward the mirrored traffic.
 - If juniperHeader is not enabled, the analyzer or destination mac address should be reachable from the source VMIs VRF. To lookup the destination mac address, L2 lookup is performed in the source VMIs VRF.
- Adjusts the configuration server settings of CN2 to align with anticipated configuration requirements of vRouter agent.
- Uses contrail security policies to select the network traffic flow to be mirrored.
- Is applicable at the policy level or rule level. In case of rule level, the network traffic flow matching the first rule is removed out of two rules.

Configure Flow-Based Mirroring

To configure flow-based mirroring, you need to create a security policy, configure the security policy with MirrorDestination resource that selects the analyzer pod, and create an analyzer pod with the label same as MirrorDestination.

NOTE: If you are using custom network to configure flow-based mirroring, then there is a need to create a Virtual Network Router (VNR) between the custom network and ip-fabric network.

1. Create a security policy to select the traffic flow.

```
``yaml
apiVersion: core.contrail.juniper.net/v3
kind: ContrailSecurityPolicy
metadata:
  name: example-policy
  namespace: default
spec:
  rules:
    - srcEP:
        endPoints:
          - podSelector:
              matchLabels:
                app: frontend
      dstEP:
        endPoints:
          - podSelector:
              matchLabels:
                app: backend
      ports:
        - protocol: TCP
          port: 80
     action: pass
     secondaryActions:
            mirrorTo: mirrordestinationprofile1
```

Use the following code snippet to create a security policy that mirrors network traffic to an analyzer port:

apiVersion: core.contrail.juniper.net/v4
kind: ContrailSecurityPolicy
metadata:

```
name: mirror-policy-seq1
namespace: fm-test
spec:
rules:
    - srcEP:
    endPoints:
        - namespaceSelector: {}
    dstEP:
    endPoints:
        - podSelector:
        matchLabels:
        app : analyzer
action: pass
```

If you define SecondaryAction at the rule level, then mirroring is applicable only at the rule level. In this case, flows matching the rules with mirror destination are mirrored.

```
apiVersion: core.contrail.juniper.net/v3
kind: ContrailSecurityPolicy
metadata:
  name: example-policy
  namespace: default
spec:
  rules:
    - srcEP:
        endPoints:
          - podSelector:
              matchLabels:
                app: frontend
        ports:
          - protocol: TCP
            port: 80
      dstEP:
        endPoints:
          - podSelector:
              matchLabels:
                app: backend
        ports:
          - protocol: TCP
            port: 80
      secondaryActions:
            mirrorTo: mirrordestinationprofile1
```

```
- srcEP:
    endPoints:
      - ipBlock:
          cidr: 174.19.12.0/24
          except:
            - 174.19.12.11/32
  dstEP:
    endPoints:
      - ipBlock:
          cidr: 174.19.11.0/24
          except:
            - 174.19.11.11/32
  ports:
    - protocol: TCP
      port: 80
 action: pass
```

2. Configure MirrorDestination in the security policy. The MirrorDestination potentially resolves multiple destination pods matching the label (internal or external). Only one pod from the matching pods is selected and used to get analyzer-ip-address, mac-address and routing instance.

In the following example, the MirrorDestination resolves an internal label, core.juniper.net/analyzer-pod-selector.

```
``yaml
apiVersion: core.contrail.juniper.net/v1alpha1
kind: MirrorDestination
metadata:
  name: mirrordestinationprofile1
  labels:
    core.juniper.net/analyzer-pod-selector: analyzerpod
spec:
  externalAnalyzer: <bool>
  analyzerIP: <ipaddress>
  trafficDirection: <ingress|egress|both>
  juniperHeader: <bool>
  udpPort: <int>
  staticNhHeader: <null for dynamic nh|vtep tunnel destip, mac, vxlanid for static nh>
  nextHopMode: <static|dynamic>
  nicAssistedMirroring: <bool>
    nicAssistedVlanID:
```

```
staticNextHopHeader:
    vTEPDestinationIP:
    vTEPDestinationMac:
    vxlanID:
....
```

In the following example, an external analyzer has been used. The externalAnalyzer is set as 'true' and analyzerIP is set as '10.87.88.88', which is an external IP address.

```
apiVersion: core.contrail.juniper.net/v4
kind: MirrorDestination
metadata:
    name: mirrordestinationprofile4
    labels:
        core.juniper.net/analyzer-pod-selector: FMAnalyzerVM
spec:
    trafficDirection: both
    juniperHeader: true
    nextHopMode: dynamic
    udpPort: 9088
    nicAssistedMirroring: false
    externalAnalyzer: true
    analyzerIP: 10.87.88.88
```

NOTE: A MirrorDestination resource was introduced as part of port-based mirroring in Juniper® Cloud-Native Contrail Networking (CN2) Release 22.2

3. Create an analyzer pod with label and set the label value same as specified on mirrorDestination. The mirrorDestination controller uses this label to calculate the analyzer-ip-address, mac-address and routing instance. If analyzer-interface is not specified, default interface is used.

```
```yaml
apiVersion: v1
kind: Pod
metadata:
 name: analyzerpod
 namespace: mirror-ns
 labels:
 core.juniper.net/analyzer-pod: analyzerpod
 annotations:
```

# **Configurable Categories of Metrics Collection and Reporting (Tech Preview)**

#### SUMMARY

In Juniper® Cloud-Native Contrail Networking (CN2) Release 22.2, you can enable and disable selected metrics for exporting.

#### IN THIS SECTION

- Overview: Configurable Categories of Metrics Collection and Reporting | 453
- Install and Upgrade | 455
- Manage MetricGroup with Kubectl
   Commands | 456
- Manage Metric Groups with UI | 457

## **Overview: Configurable Categories of Metrics Collection and Reporting**

To provide more flexibility in the telemetry export component, CN2 Release 22.2 introduces a new Kubernetes custom resource: MetricGroup. MetricGroup allows you to enable or disable selected metrics for exporting.

• MetricGroup contains and manages a set of metrics for exporting.


- Metrics are grouped by their category. You can choose to enable or disable the metric export function at the group level.
- MetricGroup is implemented through a Kubernetes custom resource.

MetricGroup provides fine-grained control on which metrics the system collects and reports. You can turn on and off a subset of metrics reporting. At times, you may want to collect only a subset of metrics for efficiency and the lightest weight deployment possible.

**NOTE**: This feature is classified as a Juniper CN2 Technology Preview feature. These features are "as is" and are for voluntary use. Juniper Support will attempt to resolve any issues that customers experience when using these features and create bug reports on behalf of support cases. However, Juniper may not provide comprehensive support services to Tech Preview features.

For additional information, see "Juniper CN2 Technology Previews (Tech Previews)" on page 459 or contact Juniper Support.

#### Figure 25: Metrics Collection and Reporting Architecture



Telemetry Operator, see Figure 25 on page 454, monitors any change of metric groups. Based on the enabled metric groups, a list of enabled metrics is created and sent in the form of ConfigMap to metric export agents. Metric export agents collect and export these enabled metrics, instead of all metrics on the system.

- The MetricGroup reconciler builds a ConfigMap for each type of metric (vrouter or controller) from the enabled MetricGroup(s) and applies the ConfigMap to all clusters.
- The kube-manager reconciler does the same for a new cluster.

Telemetry Exporter combines metric specifications with this ConfigMap to create enabled metric specifications. The metric export function only exports metrics from the enabled metric specifications, instead of all metrics.

The following items list the YAML values for ConfigMap and MetricGroup.

#### ConfigMap: vrouter-export-enabled-metrics

- Revision number
- Array of enabled metric names

#### Custom Resource: MetricGroup

- Type: vrouter or controller
- Name: String
- Export: Boolean
- Metrics: Array of strings (metric name)

# Install and Upgrade

MetricGroup is included in the analytics component in CN2 Release 22.2. The predefined metric groups are automatically installed during the CN2 analytics deployment. See Install Contrail Analytics for Upstream Kubernetes or Install Contrail Analytics for OpenShift Container Platform.Install Contrail Analytics for Amazon EKS.

Example: Predefined Metric Group

Bgpaas
Controller-bgp
Controller-info
Controller-peer
Controller-xmpp
Ermvpn
Evpn
Ipv4
Ipv6
Mvpn
Vrouter-cpu
Vrouter-info
Vrotuer-inv6
Vrouter-mem

Vrouter-traffic Vrouter vmi

Example predefined MetricGroup: vrouter-cpu YAML file:

```
apiVersion: telemetry.juniper.net/v1alpha1
kind: MetricGroup
metadata:
 name: vrouter-cpu
 namespace: contrail-analytics
spec:
 export: true
 metricType: VROUTER
 metrics:
 virtual_router_cpu_1min_load_avg
 virtual_router_cpu_15min_load_avg
```

## Manage MetricGroup with Kubectl Commands

You (the administrator) can manage MetricGroup with kubect1 commands. Examples follow.

To delete MetricGroup:

kubectl delete metricgroup ipv6 -n contrail-analytics

To apply MetricGroup:

kubectl apply -f <yaml file with metric group definition>

To view MetricGroup resource:

kubectl get metricgroup ipv4 -n contrail-analytics -oyaml

To verify the existence of ConfigMap(s) run the following command.

kubectl get cm -n contrail
Names of ConfigMap
controller-export-enabled-metrics
vrouter-export-enabled-metrics

Each cluster has its own copy of the two ConfigMap(s); controller-export-enabled-metrics and vrouter-exportenabled-metrics.

# Manage Metric Groups with UI

With this Tech Preview, you can manage MetricGroups using the CN2 Manager UI. To manage Metric Groups in the UI:

1. Access the CN2 Manager UI from your browser:

https://<cluster-ip-address>/

- **2.** Log in to CN2 Manager by either method:
  - Browse and select a kubeconfig file to upload.
  - Log in using a token.
- **3.** From the left-navigation menu, select **Configure** > **Metric Groups**. The Metric Groups window appears.
- **4.** To add a Metric Group, click the "+" icon in the upper right.

Add the Name, select Type, and select the metrics to apply. Click Save.

### Add Metric Group 🕫

Name *						
Туре*	<ul> <li>Cont</li> <li>vRou</li> </ul>					
Metrics ⑦				Show Selected		7. Q
		Type 🌣	Name	Description		
		gauge	controller_state	Controller state (0=Functional, 1=Non-Functional)		
		gauge	controller_connection_status	Connection status (0=Up, 1=Down, 2=Initializing) BGP router output queue depth		
		gauge	controller_bgp_router_output_queue_depth			
	110 it	tems				
Status	💽 En	abled				
				c	Cancel	Save

5. Click the detail icon to display the Metric Group you added.

Figure 27: Display Metric Group Detail

				Ę ? C
Configure / Metric Groups /			Details for te	st1 ×
			Туре	CONTROLLER
			Status	< Enabled
Name ÷	Type ÷	Status 🔅	Metrics	
test1	CONTROLLER	Enabled		7. Q
1 items			Type 🗧 Nam	e
			gauge contr	oller_st Controller state (
			gauge contr	oller_co Connection stat
			2 items	

 $\times$ 

# Juniper CN2 Technology Previews (Tech Previews)

Tech Previews give you the ability to test functionality and provide feedback during the development process of innovations that are not final production features. The goal of a Tech Preview is for the feature to gain wider exposure and potential full support in a future release. We encourage you to provide feedback and functionality suggestions for a Technology Preview feature before it becomes fully supported.

Tech Previews may not be functionally complete, may have functional alterations in future releases, or may get dropped under changing markets or unexpected conditions, at Juniper's sole discretion. Juniper recommends that you use Tech Preview features in non-production environments only.

Juniper considers feedback to add and improve future iterations of the general availability of the innovations. Your feedback does not assert any intellectual property claim, and Juniper may implement your feedback without violating your or any other party's rights.

These features are "as is" and are for voluntary use. Juniper Support will attempt to resolve any issues that you experience when using these features and create bug reports on behalf of support cases. However, Juniper may not provide comprehensive support services for Tech Preview features. Certain features may have reduced or modified security, accessibility, availability, and reliability standards relative to General Availability software. Tech Preview features are not eligible for P1/P2 JTAC cases and are not subject to existing SLAs or service agreements.

For additional details, please contact Juniper Support or your local account team.